



# Gene Biotechnology

Third Edition



William Wu  
Helen H. Zhang  
Michael J. Welsh  
Peter B. Kaufman

# Gene Biotechnology

---

Third Edition

William Wu

Helen H. Zhang

Michael J. Welsh

Peter B. Kaufman



**CRC Press**

Taylor & Francis Group

Boca Raton London New York

---

CRC Press is an imprint of the  
Taylor & Francis Group, an **informa** business

CRC Press  
Taylor & Francis Group  
6000 Broken Sound Parkway NW, Suite 300  
Boca Raton, FL 33487-2742

© 2011 by Taylor and Francis Group, LLC  
CRC Press is an imprint of Taylor & Francis Group, an Informa business

No claim to original U.S. Government works

Printed in the United States of America on acid-free paper  
10 9 8 7 6 5 4 3 2 1

International Standard Book Number: 978-1-4398-4830-2 (Hardback)

This book contains information obtained from authentic and highly regarded sources. Reasonable efforts have been made to publish reliable data and information, but the author and publisher cannot assume responsibility for the validity of all materials or the consequences of their use. The authors and publishers have attempted to trace the copyright holders of all material reproduced in this publication and apologize to copyright holders if permission to publish in this form has not been obtained. If any copyright material has not been acknowledged please write and let us know so we may rectify in any future reprint.

Except as permitted under U.S. Copyright Law, no part of this book may be reprinted, reproduced, transmitted, or utilized in any form by any electronic, mechanical, or other means, now known or hereafter invented, including photocopying, micro-filming, and recording, or in any information storage or retrieval system, without written permission from the publishers.

For permission to photocopy or use material electronically from this work, please access [www.copyright.com](http://www.copyright.com) (<http://www.copyright.com>) or contact the Copyright Clearance Center, Inc. (CCC), 222 Rosewood Drive, Danvers, MA 01923, 978-750-8400. CCC is a not-for-profit organization that provides licenses and registration for a variety of users. For organizations that have been granted a photocopy license by the CCC, a separate system of payment has been arranged.

**Trademark Notice:** Product or corporate names may be trademarks or registered trademarks, and are used only for identification and explanation without intent to infringe.

---

#### Library of Congress Cataloging-in-Publication Data

---

Wu, William, author.

Gene biotechnology / William Wu, Helen H. Zhang, Michael J. Welsh, and Peter B. Kaufman. -- Third Edition.

p. ; cm.  
"A CRC title."

Includes bibliographical references and index.

Summary: "The third edition of this popular reference covers a variety of techniques related to gene manipulation, including DNA isolation, preparation, screening, and analysis. Topics range from very basic methods to current and sophisticated technologies, including methodologies created and tested by the authors. Other topics include approaches to grant funding and SiRNA technology. The authors offer detailed, step-by-step explanations of protocols and helpful troubleshooting guides. This edition features new techniques for every chapter, as well as several new chapters"--Provided by publisher.

ISBN 978-1-4398-4830-2 (hardcover : alk. paper)

1. Genetic engineering--Laboratory manuals. 2. Molecular biology--Laboratory manuals. I. Zhang, Helen H., author. II. Welsh, Michael J., author. III. Kaufman, Peter B., author. IV. Gene biotechnology. revision of (work) V. Title.

[DNLN: 1. Genetic Engineering--methods--Laboratory Manuals. 2. Biotechnology--methods--Laboratory Manuals. QU 25]

QH442.M475 2011

660.6'5078--dc22

2010051443

---

Visit the Taylor & Francis Web site at  
<http://www.taylorandfrancis.com>

and the CRC Press Web site at  
<http://www.crcpress.com>

---

# Contents

Preface.....	xxvii
Authors.....	xxix

<b>Chapter 1</b>	Strategies for Novel Research Projects and/or Research Grant Funding.....	1
1.1	Introduction .....	1
	References .....	14
<b>Chapter 2</b>	Rapid Isolation of Specific cDNAs or Genes by PCR.....	17
2.1	Introduction .....	17
2.2	Isolation of Specific Full-Length cDNAs by RT-PCR Method.....	17
2.2.1	Isolation of RNAs.....	18
2.2.2	Design and Synthesis of Specific Forward and Reverse Primers.....	18
2.2.3	Amplification of cDNA of Interest by RT-PCR .....	20
2.2.4	Purification of PCR Products by High-Speed Centrifugation of Agarose Gel Slices .....	22
2.3	Amplification and Isolation of cDNA Ends by 5'-RACE.....	23
2.4	Amplification and Isolation of cDNA Ends by 3'-RACE.....	24
2.5	Isolation of Gene of Interest by PCR.....	24
2.5.1	Isolation of Genomic DNA.....	24
2.5.2	Partial Digestion of Genomic DNA Using <i>Sau3AI</i> .....	26
2.5.2.1	Optimization of Partial Digestion of Genomic DNA with <i>Sau3AI</i> .....	26
2.5.2.2	Large-Scale Preparation of Partially Digested Genomic DNA.....	27
2.5.3	Design and Synthesis of Specific Forward and Reverse Primers.....	28
2.5.3.1	Amplification and Isolation of Exon and Intron Sequences.....	28
2.5.3.2	Amplification and Isolation of Promoter Sequence .....	29
2.5.4	Amplification of Specific DNA Fragments by PCR .....	29
2.5.5	Purification of PCR Products by Agarose Gels .....	30
2.6	Subcloning of cDNA or Gene of Interest .....	30
2.7	Characterization of PCR Products .....	30
	References .....	30

<b>Chapter 3</b>	<b>Construction and Screening of Subtracted and Complete Expression cDNA Libraries .....</b>	<b>33</b>
3.1	Introduction .....	33
3.2	Construction and Screening of a Subtracted cDNA Library .....	36
3.2.1	Isolation of Total RNAs from Cell- or Tissue-Type A and B of Interest .....	36
3.2.1.1	Protocol A. Rapid Isolation of Total RNA by Acid Guanidinium Thiocyanate–Phenol–Chloroform Method.....	38
3.2.1.2	Protocol B. Rapid Isolation of Total RNA Using Trizol Reagent™.....	39
3.2.1.3	Protocol C. Measurement of RNAs.....	40
3.2.2	Purification of mRNAs from Total RNAs .....	42
3.2.2.1	Protocol A. Purification of Poly(A) <sup>+</sup> RNAs Using Oligo(dT)-Cellulose Column .....	42
3.2.2.2	Protocol B. Minipurification of mRNAs Using Oligo(dT) Cellulose Resin..	44
3.2.3	Synthesis of First Strand cDNAs from Cell/Tissue Type A or B.....	45
3.2.3.1	Protocol A. Synthesis of First Strand cDNAs from mRNAs .....	45
3.2.3.2	Protocol B. TCA Assay and Calculation of cDNA Yield.....	47
3.2.3.3	Protocol C. Analysis of cDNAs by Alkaline Agarose Gel Electrophoresis .....	47
3.2.4	Hybridization of cDNAs from Cell/Tissue Type A or B with mRNAs from Cell/Tissue Type B or A, or Vice Versa .....	49
3.2.5	Separation of cDNA/mRNA Hybrids from Single-Stranded cDNAs by HAP Chromatography ...	50
3.2.6	Synthesis of Double-Stranded cDNAs from Subtracted cDNAs.....	50
3.2.7	Ligation of cDNAs to Lambda gt10 or Appropriate Vectors .....	52
3.2.7.1	Ligation of <i>Eco</i> RI Linkers/Adapters to Double-Stranded, Blunt-End cDNAs.....	52
3.2.7.2	Restriction Enzyme Digestion of Vectors .....	56
3.2.7.3	Ligation of cDNAs to Vectors .....	56
3.2.8	Generation of a Subtracted cDNA Library .....	57
3.2.8.1	<i>In Vitro</i> Packaging .....	57
3.2.8.2	Titration of Packaged Phage .....	58

3.2.8.3	Amplification of cDNA Library (Optional).....	60
3.2.9	Isolation of Specific cDNA from the Subtracted cDNA Library .....	60
3.2.10	Characterization of cDNA.....	60
3.3	Construction and Screening of a Complete Expression cDNA Library.....	61
3.3.1	General Principles and Considerations of an Expression cDNA Library.....	61
3.3.2	Isolation of Total RNAs and Purification of mRNAs from Cells or Tissues of Interest .....	61
3.3.3	Synthesis of cDNAs from mRNAs .....	61
3.3.4	Ligation of cDNAs to $\lambda$ gt11 Expression Vectors.....	61
3.3.5	Generation of an Expression cDNA Library .....	61
3.3.6	Screening of the Expression Library and Isolation of the cDNA of Interest .....	63
3.3.6.1	Method A. Immunoscreening of Expression cDNA Library Using Specific Antibodies.....	63
3.3.6.2	Method B. Screening a cDNA Library Using $^{32}\text{P}$ -Labeled DNA as a Probe .....	67
3.3.6.3	Method C. Screening a cDNA Library Using a Nonradioactive Probe .....	67
3.3.6.4	Method D. Isolation of $\lambda$ Phage DNAs by the Liquid Method .....	67
3.3.7	Characterization of cDNA.....	69
	References .....	71

<b>Chapter 4</b>	<b>Subcloning of Genes or DNA Fragments.....</b>	<b>73</b>
4.1	Introduction .....	73
4.2	Restriction Enzyme Digestion of Vector or DNA Insert for Subcloning .....	73
4.2.1	Selection of Restriction Enzymes .....	73
4.2.2	Selection of Cloning Vectors.....	75
4.2.3	Protocols for Restriction Enzyme Digestion .....	76
4.3	Purification of DNA Fragments from Agarose Gels.....	78
4.3.1	Elution of DNA Bands by High-Speed Centrifugation of Agarose Gel Slices .....	78
4.3.2	Elution of DNA Fragment by Melting and Thawing of Agarose Gel Slices.....	80
4.3.3	Elution of DNA Fragment Using NA45 DEAE Membrane.....	81
4.3.4	Elution of DNA Fragments in Agarose Gel Well.....	81
4.4	Ligation of DNA Fragments.....	81
4.5	Single-Step Cloning by PCR.....	83

4.6	Transformation of Ligated DNA into Bacteria.....	85
4.6.1	Protocol 1. Preparation of Competent Cells for Transformation .....	85
4.6.1.1	Competent Cells for $\text{CaCl}_2$ Transformation before Ligation .....	85
4.6.1.2	Preparation of Competent Cells for Electroporation .....	86
4.6.2	Protocol 2. Transformation of Cells by $\text{CaCl}_2$ Method .....	86
4.6.3	Protocol 3. Transformation by Electroporation.....	87
4.7	Isolation and Purification of Plasmid DNA by Alkaline Method.....	88
4.7.1	Protocol 1. Minipreparation of Plasmid DNA .....	88
4.7.2	Protocol 2. Large-Scale Preparation of Plasmid DNA .....	91
4.7.3	Protocol 3. Purification of Plasmid DNA by $\text{CsCl}$ Gradient.....	92
4.8	Verification of DNA Insertion by Restriction Enzyme Digestion and Agarose Gel Electrophoresis.....	94
4.9	Verification of Insertion Site by DNA Sequencing .....	95
	References .....	96
<b>Chapter 5</b>	<b>Nonisotopic and Isotopic DNA or RNA Sequencing.....</b>	<b>97</b>
5.1	Introduction .....	97
5.2	Nonisotopic DNA Sequencing Method.....	99
5.2.1	Protocol 1. Preparation of DNA Templates for Sequencing .....	99
5.2.1.1	Purification of Double-Stranded Plasmid DNA Using the Alkaline Method.....	99
5.2.1.2	Purification of ssDNA.....	102
5.2.2	Protocol 2. Sequencing Reactions.....	103
5.2.2.1	Method A. Sequencing Reactions for Double-Stranded Plasmid DNA .....	103
5.2.2.2	Method B. Sequencing Reactions for ssDNA.....	107
5.2.3	Protocol 3. Preparation of Sequencing Gels.....	108
5.2.3.1	Method A. Pouring the Gel Mixture Horizontally into the Sandwich .....	109
5.2.3.2	Method B. Pouring the Gel at an Angle ...	110
5.2.4	Protocol 4. Electrophoresis .....	112
5.2.5	Protocol 5. Transferring of DNA from Gel onto a Nylon Membrane.....	114
5.2.6	Protocol 6. Detection.....	115

- 5.2.6.1 Method A. Chemiluminescent Detection..... 115
- 5.2.6.2 Method B. Colorimetric Detection ..... 116
- 5.3 Isotopic DNA Sequencing Method..... 117
- 5.4 Use of Formamide Gels..... 119
- 5.5 Extending Sequencing Far from the Primers ..... 120
- 5.6 DNA Sequencing by Primer Walking ..... 120
- 5.7 DNA Sequencing by Unidirectional Deletions ..... 120
  - 5.7.1 Protocol 1. Performing a Series of Deletions of the Linearized DNA with Exonuclease III and Recircularization of DNA with T4 DNA Ligase..... 122
- 5.8 Direct DNA Sequencing by PCR ..... 124
- 5.9 RNA Sequencing ..... 127
  - 5.9.1 Protocol 1. Annealing of Primer and RNA Template ..... 127
  - 5.9.2 Protocol 2. Labeling Reactions ..... 127
  - 5.9.3 Protocol 3. Termination Reaction..... 128
- References ..... 132

**Chapter 6** Bioinformation Superhighway and Computer Databases of Nucleic Acids and Proteins ..... 133

- 6.1 Introduction ..... 133
- 6.2 Communication with GenBank via the Internet ..... 133
  - 6.2.1 Submission of a Sequence to GenBank ..... 133
  - 6.2.2 Sequence Similarity Searching Using BLAST Programs ..... 135
    - 6.2.2.1 BLASTN..... 135
    - 6.2.2.2 BLASTX..... 138
    - 6.2.2.3 BLASTP ..... 139
- 6.3 Computer Analysis of DNA Sequences by the GCG Program ..... 140
  - 6.3.1 Entry and Editing of a Sequence Using the GCG Program ..... 140
    - 6.3.1.1 Sequence Entry ..... 140
    - 6.3.1.2 Sequence Editing or Modification ..... 142
    - 6.3.1.3 Review of Sequence Output..... 142
  - 6.3.2 Combination or Assembly of Multiple Fragments into a Single Sequence ..... 142
    - 6.3.2.1 Generating a New Project File Using the GelStart Program..... 142
    - 6.3.2.2 Enter Sequences to Be Assembled into the Project File Generated in the Previous Section (e.g., FRAGMENT) Using the GelEnter Program ..... 143



6.3.2.3	Compare and Identify Overlap Points of the Entered Fragments Using the GelMerge or GelOverlap Program .....	144
6.3.2.4	Assembly and Review of the Combined Sequence Using the GelAssemble Program .....	145
6.3.3	Identification of Restriction Enzyme Digestion Sites, Fragment Sizes, and Potential Protein Translations of a DNA Sequence .....	145
6.3.3.1	Exhibition of Restriction Enzymes above Both Strands of a DNA Sequence and Possible Protein Translation below the Sequence Using the Map Program .....	146
6.3.3.2	Identification of Specific Restriction Enzyme Cutting Sites and Sizes of Fragments Using MapSort Program.....	147
6.3.4	Comparison of Similarity between Two Sequences .....	148
6.3.5	Translation of Nucleic Acid Sequences into Amino Acid Sequences or from an Amino Acid Sequence into a Nucleic Acid Sequence .....	150
6.3.5.1	Translate.....	150
6.3.5.2	BackTranslate .....	150
6.3.6	Identification of Enzyme Digestion Sites within a Peptide or Protein .....	151
6.3.7	Obtaining Nucleotide and Amino Acid Sequences from GenBank.....	152
	References .....	153

<b>Chapter 7</b>	<b>Characterization of DNA or Genes by Southern Blot Hybridization.....</b>	<b>155</b>
7.1	Introduction .....	155
7.2	Principles and General Considerations .....	155
7.3	Isolation of DNA for Analysis .....	157
7.4	Restriction Enzyme Digestion of DNA .....	157
7.5	Agarose Gel Electrophoresis of DNAs.....	157
7.6	Blotting of DNAs onto Nylon Membranes .....	159
7.6.1	Method A. Upward Capillary Transfer (6 to 12 h)...	159
7.6.2	Method B. Downward Capillary Transfer (1 to 1.5 h Using Alkaline Buffer or 3 h Using Neutral Buffer) .....	161
7.7	Preparation of Probes .....	163
7.7.1	Preparation of Nonisotopic DNA Probes .....	163

7.7.1.1	Protocol 1. Direct Labeling of ssDNA Using the ECL Kit .....	163
7.7.1.2	Protocol 2. Random Primer Digoxigenin Labeling of dsDNA.....	165
7.7.1.3	Protocol 3. Nick Translation Labeling of dsDNA with Biotin-11-dUTP or Digoxigenin-11-dUTP.....	167
7.7.2	Preparation of Isotopic DNA Probes.....	168
7.7.2.1	Protocol 1. Nick Translation Labeling of dsDNA .....	168
7.7.2.2	Protocol 2. DE-81 Filter-Binding Assay... ..	168
7.7.2.3	Protocol 3. Trichloroacetic Acid Precipitation.....	168
7.7.2.4	Protocol 4. Random Primer Labeling of dsDNA .....	170
7.7.2.5	Protocol 5. 3'-End Labeling of ssDNA (Oligonucleotides) with a Terminal Transferase.....	170
7.8	Prehybridization and Hybridization .....	171
7.9	Washing and/or Incubation of Antibodies.....	172
7.9.1	Protocol A. Washing of Filters Hybridized with ECL-Labeled Probes .....	172
7.9.2	Protocol B. Washing and Antibody Incubation of Filters Hybridized with Biotin-dUTP- or DIG-UTP-Labeled Probes .....	173
7.9.3	Protocol C. Washing of Filters Hybridized with Isotopic Probes .....	173
7.10	Detection of Hybridized Signal(s) .....	173
7.10.1	Method A. Chemiluminescence Detection .....	173
7.10.2	Method B. Colorimetric Detection of Filters Hybridized with Antibody-Conjugated Probes.....	174
7.10.3	Method C. Detection of Signals by Autoradiography.....	174
	References .....	179

**Chapter 8** Gene Overexpression by Sense RNA in Mammalian Systems..... 181

8.1	Introduction .....	181
8.2	Design and Selection of Plasmid-Based Expression Vectors .....	183
8.2.1	Constitutive Promoter Vectors .....	183
8.2.1.1	Constitutive Promoters .....	183
8.2.1.2	Selectable Marker Genes .....	184
8.2.1.3	Reporter Genes .....	184
8.2.1.4	Splicing Regions .....	185

	8.2.1.5	Kozak Sequence and Enhancer Element .....	185
	8.2.2	Inducible Promoter Vectors.....	185
	8.2.3	Retrovirus Vectors.....	186
8.3		Preparation of Plasmid Sense cDNA Constructs .....	190
8.4		Transient Transfection of Mammalian Cells with Sense Constructs.....	190
	8.4.1	Method A. Transfection by Calcium Phosphate Precipitation .....	190
	8.4.2	Method B. Transfection by Retrovirus Vectors.....	193
	8.4.2.1	Protocol 1. Preparation of Viral Supernatant by Transient Transfection of a Packaging Cell Line with Retrovirus Vector Constructs .....	193
	8.4.2.2	Protocol 2. Production of Stably Transfected Producer Cell Lines .....	194
	8.4.2.3	Protocol 3. Determination of Viral Titer.....	195
	8.4.2.4	Protocol 4. Amplification of Virus Stock by Serial Reinfection of Fresh Target Cells.....	196
	8.4.2.5	Protocol 5. Transfection of Cells of Interest with the High Titer Stock of Replication-Incompetent Retroviruses .....	197
8.5		Stable Transfection of Mammalian Cells with Sense DNA Constructs .....	198
	8.5.1	Method A. Transfection by Liposomes .....	198
	8.5.2	Method B. Transfection by Electroporation.....	198
	8.5.3	Method C. Transfection by Retrovirus Vectors.....	199
8.6		Selection of Stably Transfected Cell Lines with Appropriate Drugs.....	199
8.7		Characterization of Stably Transfected Cell Clones .....	200
	8.7.1	Analysis of Gene Overexpression at the Protein Level by Western Blotting.....	201
	8.7.2	Examination of the Expression of Sense RNA by Northern Blotting .....	202
	8.7.3	Determination of Integration Copy Number by Southern Blot Analysis.....	202
	8.7.3.1	Isolation of Genomic DNA from Cultured Cells .....	202
	8.7.3.2	Analysis of Southern Blot Data .....	203
	8.7.4	Expression Assay of a Reporter Gene.....	203
	8.7.4.1	Activity Assay of CAT.....	203
	8.7.4.2	Luciferase Assay.....	204
	8.7.4.3	$\beta$ -Galactosidase Assay .....	205
	8.7.4.4	$\beta$ -Galactosidase Staining of Cells .....	206

8.8 Generation of Transgenic Mice from Sense ES Clones ..... 207  
 8.9 Characterization of Transgenic Mice ..... 207  
 References ..... 208

**Chapter 9** Gene Underexpression in Cultured Cells and Animals by Antisense DNA and RNA Strategies ..... 209

9.1 Introduction ..... 209

9.2 Antisense Oligonucleotide Approaches..... 209

9.2.1 Design and Synthesis of Antisense Oligonucleotides..... 209

9.2.2 Treatment of Cultured Cells with Antisense Oligomers and Determination of the Optimum Dose of Oligomers by Western Blot Analysis..... 211

9.2.3 Treatment of Cultured Cells Using an Optimum Dose of Oligomers..... 213

9.2.4 Analysis of Inhibition of Gene Expression by Western Blotting..... 213

9.3 Design and Selection of Plasmid-Based Expression Vectors ..... 214

9.4 Preparation of Plasmid Antisense cDNA Constructs ..... 214

9.5 Transient Transfection of Cultured Cells with Antisense Constructs ..... 215

9.6 Stable Transfection of Cultured Cells with Antisense DNA Constructs ..... 215

9.6.1 Method A. Transfection by Liposomes ..... 215

9.6.2 Method B. Transfection by Microinjection ..... 217

9.6.3 Method C. Transfection by Electroporation ..... 218

9.6.4 Method D. Transfection by Retrovirus Vectors ..... 218

9.7 Selection of Stably Transfected Cell Lines with Appropriate Drugs ..... 218

9.8 Characterization of Stably Transfected Cell Clones ..... 218

9.8.1 Analysis of Gene Underexpression at the Protein Level by Western Blotting ..... 218

9.8.2 Examination of the Expression of Antisense RNA by Northern Blotting ..... 219

9.8.3 Determination of Integration Copy Number by Southern Blot Analysis..... 219

9.8.4 Expression Assay of Reporter Genes ..... 220

9.9 Generation of Transgenic Mice ..... 220

9.9.1 Method A. Production of Transgenic Mice from Stably Transfected ES Cells ..... 220

9.9.1.1 Selection of C57BL/6J Estrous Females ..... 220

9.9.1.2 Preparation of a Bank of Sterile Males by Vasectomy ..... 221

9.9.1.3	Pairing of Estrous Females and Sterile Males.....	222
9.9.1.4	Preparation of Blastocyst-Stage Embryos from Pseudopregnant Mice .....	222
9.9.1.5	Preparation of Micromanipulation Apparatus.....	223
9.9.1.6	Injection of ES Cells into Blastocysts.....	224
9.9.1.7	Reimplantation of the Injected Blastocysts into the Uterus of Recipient Females .....	225
9.9.2	Method B. Production of Transgenic Mice from Oocytes.....	225
9.9.2.1	Preparation of Oocytes .....	225
9.9.2.2	Microinjection of DNA Constructs into Oocytes .....	227
9.9.2.3	Reimplantation of Injected Eggs into Recipient Female Mice and Generation of Founder Mice .....	227
9.10	Characterization of Transgenic Mice .....	228
	References .....	229

<b>Chapter 10</b>	<b>Analysis of Gene Expression at Functional Genomic Level Using Northern Blotting or PCR.....</b>	<b>231</b>
10.1	Introduction .....	231
10.2	Principles and General Considerations .....	232
10.3	Isolation of Total RNAs and/or Purification of mRNAs.....	234
10.4	Electrophoresis of RNAs Using Formaldehyde Agarose Gels.....	234
10.5	Blotting of RNAs onto Nylon Membranes by the Capillary Method .....	237
10.6	Preparation of Isotopic or Nonisotopic DNA/RNA Probes .....	237
10.6.1	Protocol A. Preparation of DNA Probes .....	237
10.6.2	Protocol B. Preparation of RNA Probes by Transcription <i>in Vitro</i> .....	238
10.7	Hybridization and Detection of Signals .....	241
10.8	Analysis of mRNA Expression by a Semiquantitative PCR Approach.....	241
	References .....	246

<b>Chapter 11</b>	<b>Analysis of Gene Expression at Proteomic Level via Western Blotting.....</b>	<b>249</b>
11.1	Introduction .....	249
11.2	Principles .....	251

11.3 Extraction of Cellular Proteins..... 253

11.3.1 Method A. Extraction of Total Proteins Using Lauroylsarcosine Buffer..... 253

11.3.2 Method B. Determination of Protein Concentration Using Bradford Assay..... 255

11.4 Analysis of Proteins by SDS-PAGE and Western Blotting ... 255

11.4.1 Protocol 1. Preparation of SDS-Separation Gels ..... 255

11.4.2 Protocol 2. Preparation of Stacking Gels ..... 256

11.4.3 Protocol 3. Electrophoresis..... 257

11.4.4 Protocol 4. Staining and Destaining of SDS-PAGE Using a Modified CB Method ..... 258

11.4.5 Protocol 5. Transfer of Proteins from SDS-PAGE onto a Nitrocellulose or PVDF Membrane by ElectrobloTTing..... 259

11.4.5.1 Method A. Semidry ElectrobloTTing ..... 259

11.4.5.2 Method B. Liquid Transfer Using a Hoeffer TE 42 Blotting Apparatus ..... 260

11.4.6 Protocol 6. Blocking and Hybridization of Membrane Filter Using Specific Antibodies ..... 261

11.4.7 Protocol 7. Detection of Hybridized Signal(s)..... 262

11.4.7.1 Method A. Chemiluminescence Detection for Peroxidase-Conjugated or Biotin-Labeled Antibodies ..... 262

11.4.7.2 Method B. Colorimetric Detection for Alkaline Phosphatase-Conjugated Antibodies..... 262

11.5 Analysis of Proteins by 2-D Gel Electrophoresis..... 263

References ..... 266

**Chapter 12** Analysis of Cellular DNA or Abundance of mRNA by Radioactivity *in Situ* Hybridization..... 269

12.1 Introduction ..... 269

12.2 Tissue Fixation, Embedding, Sectioning, and Mounting of Sections on Slides..... 270

12.2.1 Preparation of Silane-Coated Glass Slides..... 270

12.2.1.1 Method A. Silanization of Slides..... 270

12.2.1.2 Method B. Treatment of Slides with Poly-L-Lysine ..... 270

12.2.1.3 Method C. Gelatin-Coating of Slides ..... 270

12.2.2 Preparation of Fixation Solutions..... 270

12.2.2.1 Preparation of 4% (w/v) PFA Fixative (1 l)..... 270

12.2.3 Fixation of Cultured Cells on Slides ..... 271

12.2.4 Tissue Fixation, Embedding, Sectioning, and Mounting of Sections on Slides..... 271

12.2.4.1	Fixation .....	271
12.2.4.2	Embedding.....	272
12.2.4.3	Sectioning and Mounting .....	273
12.2.5	Cryosectioning .....	273
12.2.5.1	Preparation of Frozen Specimens.....	273
12.2.5.2	Freeze Sectioning .....	274
12.2.5.3	Fixation .....	274
12.3	<i>In Situ</i> Hybridization and Detection Using Isotopic Probes .....	275
12.3.1	Dewaxing of Sections.....	275
12.3.2	Protease Digestion.....	276
12.3.3	DNase Treatment for <i>in Situ</i> Hybridization of RNA .....	277
12.3.4	RNase Treatment for <i>in Situ</i> Hybridization of DNA .....	277
12.3.5	Preparation of Radioactive Probes .....	278
12.3.5.1	Synthesis of Probes for DNA Hybridization Using Random Primer Labeling of dsDNA.....	278
12.3.5.2	Preparation of [ <sup>35</sup> S]UTP Riboprobe for RNA Hybridization by Transcription <i>in Vitro</i> Labeling.....	281
12.3.6	<i>In Situ</i> Hybridization .....	283
12.3.7	Detection of Hybridized Signals .....	285
	References .....	289

## Chapter 13 Localization of DNA or Abundance of mRNA by Fluorescence

	<i>in Situ</i> Hybridization .....	291
13.1	Introduction .....	291
13.2	Cell or Tissue Fixation, Tissue Embedding, Sectioning, and Mounting .....	291
13.3	Dewaxing of Sections, Protease Digestion, and DNase or RNase Treatment of Specimens for <i>in Situ</i> Hybridization.....	292
13.4	Preparation of Nonisotopic Probes Using One of the Following Methods, Depending on Specific Probe and Detection Strategies.....	292
13.4.1	Method A. Random Primer Digoxigenin Labeling of dsDNA .....	292
13.4.2	Method B. Nick Translation Labeling of dsDNA with Biotin-11-dUTP or Digoxigenin-11-dUTP.....	293
13.4.3	Method C. Riboprobe or RNA Labeling.....	293
13.5	<i>In Situ</i> Hybridization of Specimens .....	296
13.6	Enzymatic Detection of Hybridized Signals Using Colorimetric Substrates NBT and BCIP .....	297

13.7 Fluorescence Detection of Hybridized Signals ..... 298  
 References ..... 301

**Chapter 14** *In Situ* PCR Hybridization of Low Copy Genes and *in Situ* RT-PCR Detection of Low Abundance mRNAs ..... 303

14.1 Introduction ..... 303

14.2 Detection of a Low Copy Gene by *in Situ* PCR Hybridization ..... 304

14.2.1 Design of Specific Primers for *in Situ* PCR Amplification of Target DNA Sequences ..... 305

14.2.2 Synthesis and Testing of the Designed Primers ..... 307

14.2.3 Carrying Out Fixation of Cells or Tissues, Tissue Embedding, Sectioning, and Mounting of Sections on Slides ..... 307

14.2.4 Dewaxing of Sections (if Necessary), Protease Digestion, and DNase or RNase Treatment of Specimens ..... 308

14.2.5 Preparation of Radioactive Probes for RISH or Nonradioactive Probes for FISH ..... 308

14.2.6 Performance of *in Situ* PCR ..... 308

14.2.7 Performance of *in Situ* Hybridization and Detection by RISH or by FISH ..... 311

14.3 Detection of Low Abundance mRNA by *in Situ* RT-PCR Hybridization ..... 312

14.3.1 Carrying Out Cell or Tissue Fixation, Tissue Embedding, Sectioning, and Mounting of Sections on Slides ..... 312

14.3.2 Dewaxing of Sections, Protease Digestion, and DNase or RNase Digestion of Specimens ..... 314

14.3.3 Performance *in Situ* Reverse Transcription Reaction on Sections ..... 314

14.3.4 Performance of RNase (DNase-Free) Digestion of Specimens to Eliminate Potential Mispriming between PCR Primers and mRNA Molecules ..... 315

14.3.5 Preparation of Radioactive Probes for RISH or Nonradioactive Probes for FISH ..... 315

14.3.6 Design of Specific Primers for *in Situ* PCR ..... 315

14.3.7 Carrying Out *in Situ* PCR ..... 315

14.3.8 Performance of *in Situ* Hybridization and Detection by RISH or by FISH ..... 315

14.4 *In Situ* PCR or RT-PCR Detection of DNA or mRNA by Direct Incorporation of Digoxigenin-11-dUTP or Biotin-dUTP without Hybridization ..... 316

References ..... 317



<b>Chapter 15</b>	Isolation and Characterization of Genes from Genomic DNA Libraries .....	319
15.1	Introduction .....	319
15.2	Selection of Lambda Vectors.....	320
15.3	Isolation of High Molecular Weight of Genomic DNA .....	320
15.4	Partial Digestion of Genomic DNA Using <i>Sau3AI</i> .....	322
15.4.1	Determination of the Optimal Partial Digestion of Genomic DNA with <i>Sau3AI</i> .....	322
15.4.2	Large-Scale Preparation of Partial Digestion of Genomic DNA.....	323
15.5	Partial Fill-In of Recessed 3'-Termini of Genomic DNA Fragments .....	324
15.6	Ligation of DNA Inserts to Vectors.....	325
15.6.1	Small-Scale Ligation of Partially Filled-In Genomic DNA Fragments and Partially Filled-In LambdaGEM-12 Arms.....	325
15.6.2	Packaging of the Ligated DNA .....	326
15.6.3	Titration of Packaged Phage on Luria–Bertani Plates .....	326
15.6.4	Large-Scale Ligation of the Partially Filled-In Vector Arms and Partially Filled-In Genomic DNA Fragments .....	328
15.7	Screening of Genomic DNA Library and Isolation of Specific Clones .....	328
15.7.1	Method A. Screening of a Genomic Library with $\alpha$ - <sup>32</sup> P-Labeled Probe .....	328
15.7.2	Method B. Screening of a Genomic Library Using a Nonisotope Labeled Probe.....	333
15.8	Isolation of $\lambda$ Phage DNAs by the Liquid Method .....	335
15.9	Restriction Mapping of Recombinant Bacteriophage DNA Containing the Genomic DNA Insert of Interest.....	336
15.10	Subcloning of the Isolated Gene or DNA Fragments.....	338
15.11	Characterization of the Isolated DNA .....	338
	References .....	339
<b>Chapter 16</b>	Mouse Stem Cells as a Model Mammalian Cell Line for Gene Expression .....	341
16.1	Introduction .....	341
16.2	Protocol 1. Culture of ES Cells in Media Containing Leukemia Inhibitory Factor.....	341
16.3	Protocol 2. Preparation of Mitotically Inactivated STO Cells as Feeder Layers for Growth of ES Cells.....	343
16.4	Protocol 3. Culture of ES Cells on Fibroblast Feeder Layers .....	344

16.5 Protocol 4: Trypsinizing, Freezing, and Thawing of Mammalian Cells ..... 344

    16.5.1 Trypsinizing ..... 344

    16.5.2 Freeze Back ..... 346

    16.5.3 Thawing and Reculture ..... 346

16.6 Protocol 5. Cell Counting and Determination of Cell Density ..... 347

References ..... 349

**Chapter 17** Strategies for Gene Double Knockout ..... 351

    17.1 Introduction ..... 351

    17.2 Overview and General Principles of Strategies: Gene Double-Knockout and Temporal Silence ..... 352

    17.3 Manipulation of the Specific Gene to Be Targeted ..... 354

        17.3.1 Protocol A. Disruption of an Exon in a Specific Gene ..... 355

        17.3.2 Protocol B. Deletion of Exons of a Specific Gene ... 355

        17.3.3 Protocol C. Preparation of Isogenic DNA by PCR ..... 356

            17.3.3.1 Design of Two Pairs of Primers ..... 356

            17.3.3.2 Amplification of 5'- and 3'-Isogenic DNA Fragments by PCR ..... 358

            17.3.3.3 Electrophoresis of PCR Products ..... 360

            17.3.3.4 Purification of PCR Bands from the Agarose Gel and Ligation of Isogenic DNA Fragments with a Selectable Marker Gene ..... 362

    17.4 Design and Selection of Vectors and Marker Genes for Gene Double Knockout and Temporal Silence ..... 362

        17.4.1 Type A. *neo<sup>r</sup>* Gene Vector for the First Copy of Gene Knockout ..... 363

        17.4.2 Type B. *hyg<sup>r</sup>* Gene Vector for the Second Copy of Gene Knockout ..... 364

        17.4.3 Type C. *hyr<sup>r</sup>* Gene Vector for Keeping the Double Knockout Gene Silent ..... 364

    17.5 Preparation of DNA Constructs for a Double Knockout and a Silencer ..... 365

    17.6 Transfection of ES Cells with Double Knockout and Silencer DNA Constructs ..... 367

        17.6.1 Method A. Transfection by Electroporation ..... 367

        17.6.2 Method B. Transfection of Cells by Lipofectin Reagents ..... 368

    17.7 Selection and Characterization of Targeted ES Cell Clones ..... 370

17.7.1	Double Selections of Cells Containing a Double Knockout Gene.....	370
17.7.2	Triple Selections of Cells Containing a Double Knockout Gene.....	371
17.7.3	Single Selection of Cells Containing a Silent Knockout Gene.....	371
17.8	Characterization of Targeted ES Cell Clones .....	371
17.8.1	$\beta$ -Galactosidase Staining of Cells .....	371
17.8.2	Southern Blot Analysis.....	372
	17.8.2.1 Isolation of Genomic DNA from Cultured Cells.....	373
	17.8.2.2 Analysis of Southern Blot Data .....	373
	17.8.2.3 Western Blot Analysis .....	375
17.9	Generation of Transgenic Offspring from Double-Knockout ES Cells .....	377
17.9.1	Procedure 1. Selection of C57BL/6J Estrous Females.....	377
17.9.2	Procedure 2. Preparation of a Bank of Sterile Males by Vasectomy.....	378
17.9.3	Procedure 3. Pairing of Estrous Females and Sterile Males.....	378
17.9.4	Procedure 4. Preparation of Blastocyst-Stage Embryos from Pseudopregnant Mice .....	378
17.9.5	Procedure 5. Preparation of Micromanipulation Apparatus .....	378
17.9.6	Procedure 6. Injection of ES Cells into Blastocysts.....	378
17.9.7	Procedure 7. Reimplantation of Injected Blastocysts into the Uterus of Recipient Females ....	378
17.10	Characterization of Mutant Mice .....	379
	References .....	379

<b>Chapter 18</b>	<b>Large-Scale Expression and Purification of Recombinant Proteins in Cultured Cells .....</b>	<b>381</b>
18.1	Introduction .....	381
18.2	Expression and Purification of Proteins in Prokaryotic Systems .....	382
	18.2.1 Design and Selection of Bacterial Expression Vectors.....	382
	18.2.2 Cloning of cDNA Inserts into Vectors .....	384
	18.2.3 Expression of Proteins of Interest in Bacteria.....	386
	18.2.3.1 Protocol A. Transformation of <i>E. coli</i> BL21 (DE3) with Vector Shown in Figure 18.1 Using CaCl <sub>2</sub> Method.....	386

18.2.3.2	Protocol B. Induction of Protein Expression with IPTG .....	386
18.2.3.3	Protocol C. Transformation of <i>E. coli</i> Strains HB101, JM109, TOP10, or DH5 $\alpha$ F' Using Vector Type Shown in Figure 18.2 .....	387
18.2.3.4	Protocol D. Induction of Protein Expression by Heat Shock .....	388
18.2.4	Purification and Cleavage of Expressed Proteins .....	388
18.2.4.1	Analysis of Cellular Proteins by SDS-PAGE, Dot Blot, or Western Blotting .....	388
18.2.4.2	Extraction of Total Proteins for Purification .....	389
18.2.4.3	Rapid Purification of Expressed Proteins with His-Tag Affinity Column Chromatography .....	390
18.2.4.4	Protease Cleavage of His-Tag .....	392
18.3	Overexpression of Specific Proteins in Eukaryotic Systems .....	395
18.3.1	Cloning of a cDNA to Be Expressed into Expression Vectors .....	398
18.3.2	Transformation of Yeast <i>Pichia</i> with Expression DNA Constructs .....	399
18.3.2.1	Protocol A. Linearization of Plasmid DNA .....	399
18.3.2.2	Protocol B. Transformation of <i>Pichia</i> by Electroporation .....	400
18.3.2.3	Protocol C. Preparation of Spheroplasts for Transformation .....	402
18.3.2.4	Protocol D. Transformation of Spheroplasts with Linearized DNA .....	405
18.3.3	Screening and Isolation of His <sup>+</sup> Mut <sup>+</sup> and His <sup>+</sup> Mut <sup>s</sup> Phenotype .....	407
18.3.4	Identification of Transformants Containing cDNA to Be Expressed .....	409
18.3.5	Expression of Proteins in Transformants .....	410
18.3.5.1	Determination of Optimum Conditions for Protein Expression .....	410
18.3.5.2	Large-Scale Expression of Proteins .....	411
18.3.5.3	Extraction of Total Proteins for Purification .....	412
18.3.6	Carry Out Fusion Protein Purification and Cleavage .....	412
	References .....	412

<b>Chapter 19</b>	Quantitative Analysis of Functional Genome by Real-Time RT-PCR .....	415
19.1	Introduction .....	415
19.2	Isolation of Total RNA from Tissues or Organs of Interest .....	417
19.3	Isolation of Total RNA from Cultured Cells .....	418
19.4	Preparation of RNA Pool .....	419
19.5	Designing Primers and Probes .....	420
19.6	Real-Time RT-PCR.....	421
19.6.1	Assembly of Reactions .....	421
19.6.2	Programming and Performance of Real-Time RT-PCR .....	422
19.6.3	Analysis of Data .....	423
19.6.4	Validation .....	426
	References .....	427
<b>Chapter 20</b>	High-Throughput Analysis of Gene Expression by Cutting-Edge Technology—DNA Microarrays (Gene Chips).....	429
20.1	Introduction .....	429
20.2	Isolation of Total RNA from Cells or Tissues .....	430
20.3	Preparation of Fluorescent Probes from mRNA .....	431
20.4	Generation of DNA Microarrays or Chips .....	433
20.5	Prehybridization of Gene Chips or Arrays.....	433
20.6	Hybridization.....	434
20.7	Washing .....	434
20.8	Scanning of Gene Chips Using GenePix 4000a Microarray Scanner.....	435
	References .....	437
<b>Chapter 21</b>	Construction and Screening of Human Antibody Libraries Using Phage Display Technology.....	439
21.1	Introduction .....	439
21.2	Preparation of White Blood Cells (WBCs) or Lymphocytes for RNA Isolation .....	441
21.2.1	Preparation of WBCs from Blood.....	441
21.2.2	Preparation of Lymphocytes from Tissues.....	442
21.3	Isolation of Total RNA from Lymphocytes.....	442
21.4	Synthesis of cDNAs.....	442
21.4.1	Synthesis of First Strand cDNAs from mRNAs .....	442
21.4.2	Synthesis of Double-Stranded cDNAs from Subtracted cDNAs.....	445
21.5	Design of Primers for Construction of Antibody V Gene Repertoire .....	446

21.6 PCR Amplification of Heavy- and Light-Chain Variable Regions (VH, VL), Linker, and Assembly of Recombinant Single-Chain DNA via PCR ..... 449

21.7 Generation of Recombinant DNA Constructs for Expressing Recombinant Antibodies on Surface of Phage ... 451

21.8 Expression, Biopanning, and Characterization of Phage Produces Monoclonal Antibodies on Its Tip ..... 451

    21.8.1 Infection of Bacteria Carrying Recombinant DNA Constructs and Rescuing Phagemid Libraries ..... 452

    21.8.2 Selection of Phage–Antibody Particles by Biopanning ..... 455

References ..... 456

**Chapter 22** Down-Regulation of Gene Expression in Mammalian Systems via siRNA Technology ..... 457

    22.1 Introduction ..... 457

    22.2 Design of Oligonucleotides for Hairpin siRNA ..... 458

        22.2.1 Selection of siRNA Target Site ..... 458

        22.2.2 Selection of Oligomer Size and Orientation for siRNAs ..... 459

        22.2.3 Synthesis of Hairpin siRNA-Encoding Oligonucleotides ..... 459

    22.3 Preparation of Double-Stranded Oligonucleotide Fragment for Cloning ..... 459

    22.4 Cloning Hairpin siRNA Oligo Insert into Appropriate Vectors ..... 460

    22.5 Purification of Plasmid DNA Carrying Hairpin siRNA Insert ..... 462

    22.6 Transient Transfection of Cells of Interest with Purified Plasmid DNA to Express siRNAs for Inhibiting Target mRNA ..... 463

    22.7 Isolation of Total RNA from Transfected Cells ..... 465

    22.8 Analysis of Inhibition of Specific mRNA via siRNAs by Northern Blotting ..... 466

    22.9 Extraction of Proteins for Proteomic and/or Reporter Gene Analysis ..... 466

        22.9.1 Isolation of Proteins for Western Blotting ..... 466

        22.9.2 Extraction of Proteins for Reporter Activity Assays ..... 467

    22.10 Analysis of siRNA-Mediated Inhibition of Gene Expression at Proteomic Level by Western Blotting ..... 467

    22.11 Reporter Gene Assays of Down-Regulation of Gene Expression via siRNAs ..... 467

References ..... 468

<b>Chapter 23</b>	Strategies for Gene Cloning, Expression, and Identification of Protein–Protein Interaction .....	471
23.1	Introduction .....	471
23.2	Rapid and High-Efficiency PCR-TA Cloning without DNA Ligase .....	471
23.2.1	Selection of Cloning Vector .....	472
23.2.2	PCR Primer Design.....	473
23.2.3	Performance of PCR Reactions.....	473
23.2.4	TA Cloning.....	474
23.2.5	Transformation of Chemically Treated <i>E. coli</i> One-Shot TOP10 Competent Cells.....	474
23.2.6	Confirmation of DNA Sequences of Colonies .....	475
23.3	Transfection of Eukaryotic Cells for Expression of Proteins of Interest.....	475
23.3.1	Use of FuGene 6 Reagent .....	475
23.3.2	Use of Lipofectamine 2000.....	476
23.4	Protein Extraction.....	476
23.5	Coimmunoprecipitation.....	477
23.6	Analysis and Identification of Binding Proteins.....	477
23.7	Different Strategies for Cloning, Identification, Mapping, and Characterization of Protein–Protein Interaction .....	479
23.7.1	Use of Fluorescent Protein as a Fusion Tag and Analysis by Fluorescent Microscopy .....	479
23.7.2	Cloning and Expression of Proteins of Interest with a Detection Minitag.....	479
23.7.3	How to Design, Clone, and Map Binding Regions of Proteins of Interest .....	480
23.8	Exploring the Biology or Potential Mechanisms of the Interactive Proteins.....	481
	References .....	481
<b>Chapter 24</b>	Conditional Gene Knockout.....	483
24.1	Introduction .....	483
24.2	Generation of Cre– <i>loxP</i> DNA Constructs .....	484
24.2.1	Selection of Gene or Exon(s) of Interest to Be Targeted.....	484
24.2.1.1	Rapid Isolation of Total RNAs Using Trizol Reagent™.....	485
24.2.1.2	Design of Primers for RT-PCR Using mRNA as Template.....	486
24.2.1.3	Performance of RT-PCR.....	486
24.2.2	Selection of Cloning Vector(s).....	487
24.2.3	Selection of Promoter for Expression of Cre.....	487
24.2.4	Cloning .....	487

24.3 Generation of Transgenic Mouse Line Containing *loxP* Cassette, Cre Cassette, or Both ..... 488

24.3.1 Method 1. Production of Transgenic Mice from Stably Transfected or Microinjected ES Cells ..... 489

24.3.1.1 Selection of C57BL/6J Estrous Females ..... 489

24.3.1.2 Preparation of a Bank of Sterile Males by Vasectomy ..... 490

24.3.1.3 Pairing of Estrous Females and Sterile Males ..... 491

24.3.1.4 Preparation of Blastocyst-Stage Embryos from Pseudopregnant Mice ..... 491

24.3.1.5 Preparation of Micromanipulation Apparatus ..... 492

24.3.1.6 Injection of Stably Transfected ES Cells into Blastocysts ..... 493

24.3.1.7 Reimplantation of Injected Blastocysts into the Uterus of Recipient Females ..... 494

24.3.2 Method 2. Production of Transgenic Mice from Oocytes Injected with DNA Constructs ..... 494

24.3.2.1 Preparation of Oocytes ..... 494

24.3.2.2 Microinjection of DNA Constructs into Oocytes ..... 496

24.3.2.3 Reimplantation of Injected Eggs into Recipient Female Mice and Generation of Founder Mice ..... 496

24.4 Generation and Characterization of Stable Transgenic Mouse Lines A and B ..... 497

24.5 Generation and Characterization of Transgenic Mouse Line C ..... 497

24.5.1 Genotypic Analysis ..... 498

24.5.2 Functional Genome Analysis ..... 498

24.5.3 Reporter Gene ..... 499

24.5.4 Immunostaining ..... 499

24.5.5 Functional and Phenotypic Analyses ..... 499

References ..... 499

**Chapter 25** How to Write a Research Manuscript for Publication in an English Journal ..... 501

25.1 Introduction ..... 501

25.2 Title ..... 503

25.3 Authors and Affiliation ..... 503

25.4 Materials and Methods ..... 504

25.5 Results ..... 505

25.6 Abstract (Summary in Some Journals) ..... 506



25.7	Introduction .....	506
25.8	Discussion.....	507
25.9	Acknowledgments .....	508
25.10	References.....	508
25.11	Adjustment of Format of Manuscript .....	508
25.12	Fine-Tuning and Submission of Manuscript.....	509
25.13	Some Observations on to Which Journal to Submit Your Manuscript.....	509
25.14	Waiting for Reviewers' Comments, Revision of Manuscript Based on Reviewers' Critique, and Resubmission of Manuscript .....	509
	References .....	510
<b>Chapter 26</b>	<b>How to Protect Your Discovery and Invention: <i>Patent 101</i> .....</b>	<b>511</b>
26.1	Introduction .....	511
26.2	Research Discoveries vs. IPs, Invention.....	511
26.3	IP or Invention Documentation .....	512
26.4	Technology Disclosure .....	512
26.5	Provisional Application for Patent.....	513
26.6	Full-Length or Complete Patent Application .....	514
26.6.1	Title .....	514
26.6.2	Inventor(s).....	514
26.6.3	Assignee .....	515
26.6.4	Abstract .....	515
26.6.5	Background of Invention.....	515
26.6.6	Summary of Invention.....	516
26.6.7	Brief Description of Drawings and Figures .....	516
26.6.8	Description of Illustrative Embodiments .....	516
26.6.9	References .....	518
26.6.10	Claims of Invention .....	518
	References .....	519
<b>Chapter 27</b>	<b>Determination of Transgene Copy Numbers and Practical Biocalculation.....</b>	<b>521</b>
27.1	Introduction .....	521
27.2	Determination of Gene Copy Numbers in Transgenic Animals .....	521
27.3	Molecular Weight .....	524
27.4	Calculation of Molecular Weight of Oligonucleotides .....	524
27.5	Amino Acids.....	525
27.6	Spectrophotometric Conversions.....	525
27.7	DNA Molar Conversions .....	525
27.8	Protein Molar Conversions.....	526
27.9	DNA–Protein Conversions .....	526

27.10 Molarity ..... 526

    27.10.1 Definition of Mole ..... 526

    27.10.2 How to Convert Solution or Buffer Density into  
        Moles or Molar Concentration ..... 526

    27.10.3 How to Convert a Specific Volume of a Specific  
        Concentration (100 mM) of a Solution or Buffer  
        into Weight ..... 527

    27.10.4 Common Buffer or Solution Volume Conversions... 527

    27.10.5 Example of Preparation of a Primer Solution ..... 527

    27.10.6 Example of Preparation of a Peptide Solution ..... 527

27.11 Calculation of Mean ..... 528

27.12 Variance and SD ..... 529

References ..... 530

**Index** ..... 531

---

# Preface

We are living in an era of biotechnology revolution. To many molecular and cellular biologists, the flood of information on human genome and new methodologies is particularly overwhelming because biotechnology is forging ahead and bringing rapid changes every day. Because every single organism depends on molecular actions for survival, molecular biology research has become more and more dominant in multiple disciplines. In fact, there is a general trend for the U.S. National Institutes of Health (NIH) and other funding agencies to award grants with high priority to those research proposals using molecular biology approaches. How can one catch up with new biotechnologies, and use the most recent, proven techniques for novel research? One of the aims of this book is to provide investigators with the tools needed for modern molecular and cellular biology research.

Another aim of this book is to guide graduate students in their thesis research. In our experience, good graduate training mandates independent performance with minimal advice from one's mentor. How do you select a novel research project for your thesis? What are your hypotheses, objectives, and experimental designs? How can you grasp technical problems and master current techniques? Where do you begin and what are the predicted results? How do you write your thesis and research manuscripts for publications? It is apparent that a graduate student needs some help with these questions. This book will provide the clues.

This book covers a wide range of current biotechnologies and methods that have been developed and are widely used in molecular biology, biochemistry, cell biology, immunology, recombinant protein biochemistry, biopharmaceutics, etc. The methods and protocols described in the appropriate chapters include the following: approaches to novel research, rapid isolation of specific cDNAs or genes by PCR; construction and screening of cDNA and genomic DNA libraries; preparation of DNA constructs; nonisotopic and isotopic DNA or RNA sequencing; information superhighway and computer databases of nucleic acids and proteins; characterization of DNA, RNA, or proteins by Southern, northern, or western blot hybridization; fluorescent techniques; gene overexpression; gene underexpression; and gene knockout in mammalian systems; analysis of cellular DNA or abundance of mRNA by radioactivity *in situ* hybridization; localization of DNA or abundance mRNA by fluorescence *in situ* hybridization; *in situ* PCR hybridization of low copy genes and *in situ* RT-PCR detection of low abundance mRNAs; strategies for gene double knockout, large-scale expression, and purification of recombinant proteins in cultured cells; high-throughput analysis of gene expression by real-time RT-PCR; gene expression profiling via DNA microarray, phage display, and siRNA technology; protein-protein binding and proteomic interactions; conditional gene knockout; and determination of gene copy numbers. Each chapter covers the principle(s) underlying methods and techniques, detailed step-by-step descriptions of each protocol, notes, tips, and a troubleshooting guide. We have observed that many of the currently available books in molecular biology contain only protocol recipes. Unfortunately, many

fail to explain the principles and concepts behind the methods outlined or to inform the reader about the possible pitfalls in the methods described. We intend to fill these gaps.

More importantly, this technology book provides unique features: (1) how to write a research paper for publication in English journals, (2) how to protect research discoveries and inventions via patents, and (3) discussion on practical biocalculation. The authors believe that research paper publication, intellectual property (IP) protection via patent(s), and biocalculations are very important topics to graduate students, researchers, and university faculty members.

For the information of the reader, Chapter 1 was written by William Wu, Peter B. Kaufman, and Michael J. Welsh. Chapters 2, 3, 6, 7, 9, 10, 13–17, 19–22, 23, 25, and 26 were written by William Wu. Chapter 8 was written by William Wu and Michael J. Welsh. Chapter 5 was written by William Wu and Peter B. Kaufman. Chapters 4, 11, 12, 18, 24, and 27 were written by William Wu and Helen Zhang. Nonetheless, all four authors have worked as a team.

---

# Authors

**William Wu** has extensive experience in both academic and industrial settings. Throughout the years, Dr. Wu has held various positions in several organizations, including investigator and research assistant professor at the University of Michigan Medical School, Ann Arbor, Michigan; professor at the Hunan Normal University, Hunan, China; and senior scientist, team leader, and chief technology officer in several biomedical and pharmaceutical companies. He received his master's in biology from the Hunan Normal University, Hunan, China, in 1984. In 1992, he received his PhD in molecular and cellular biology at The Ohio University, Athens, Ohio, USA. This was followed by 3 years of postdoctoral training in molecular biology at the University of Michigan.

Dr. Wu is an internationally recognized expert in molecular biology, cell biology, protein biochemistry, immunology, and biotechnology. He has presented and published more than 35 research papers and abstracts at scientific meetings and in national and international journals. As a senior author, Dr. Wu has contributed 39 chapters on molecular and cellular biology methodologies in four books. He has an extensive knowledge and profound understanding of molecular biology, biotechnology, protein biochemistry, cellular biology, and molecular genetics. He is highly experienced and has extensive hands-on expertise in a variety of current molecular biology technologies in both academic and bioindustrial settings. As inventor and coinventor, Dr. Wu has five biomedical patents granted or in pending status.

**Helen H. Zhang** is a senior research associate at the University of Michigan Medical School, Ann Arbor, Michigan. In 1996, she received her MS in molecular and cellular biology at the Eastern Michigan University, Ypsilanti, Michigan.

Zhang has a strong background in molecular biology, microbiology, biochemistry, and immunology. She is highly experienced in DNA recombination, polymerase chain reaction (PCR) applications, cell transfection, and gene expression in bacterial and animal systems. Additionally, she has extensive experience in protein-peptide purification, enzymatic assays, and analysis of drug-protein binding as well as cell culture techniques. As a coauthor, she has published many research papers in internationally recognized journals.

**Michael J. Welsh** is a professor of cell biology in the Department of Cell and Developmental Biology at the University of Michigan Medical School, Ann Arbor, Michigan. He is also a professor of toxicology in the School of Public Health at the University of Michigan. Dr. Welsh received his PhD in 1977 from the University of Western Ontario, London, Ontario, Canada.

Dr. Welsh is an internationally recognized top scientist in molecular and cellular biology. He has published more than 120 research papers and has contributed chapters in several reference books. Dr. Welsh is a leading authority on mammalian heat shock protein (HSP27) and is a recipient of several major grants from the U.S.

National Institutes of Health; some of these projects utilized his expertise to examine the function and mechanisms of the HSP27 gene. He is also a fellow of the American Association for the Advancement of Science.

**Peter B. Kaufman** is a professor of biology in the Plant Cellular and Molecular Biology Program in the Department of Biology and a member of the faculty of the Bioengineering Program at the University of Michigan, Ann Arbor, Michigan. Dr. Kaufman received his PhD in 1954 in plant biology at the University of California, Davis, California.

Dr. Kaufman is an internationally recognized scholar in the field of molecular biology and physiology. He is a fellow of the American Association for the Advancement of Science and Secretary–Treasurer of the American Society for Gravitational and Space Biology. He has served on the editorial board of *Plant Physiology* for 10 years, has published more than 190 research papers and seven professional books. Dr. Kaufman teaches a popular course in plant biotechnology yearly at the University of Michigan. He has been awarded research grants from the National Science Foundation, the National Aeronautics and Space Administration, the U.S. Department of Agriculture, and Parke-Davis Pharmaceutical Research Laboratories in Ann Arbor, Michigan.

---

# 1 Strategies for Novel Research Projects and/or Research Grant Funding

## 1.1 INTRODUCTION

We are living in the era of biotechnology revolution. To many molecular biologists, the flood of new bioinformation is particularly overwhelming. How can one catch up, update new biotechnology, and use the most recent, proven techniques for a novel research? As indicated in the Preface, one of the aims of this book is to provide investigators with tools for molecular biology research. Perhaps because every single organism depends on molecular actions for survival, molecular biology research becomes more and more dominant in multiple disciplines.<sup>1-21</sup> In fact, it is a general tendency that the National Institutes of Health (NIH) and other funding agencies award grants with high priority to those research proposals that use molecular biology approaches. Given the fact that research funding resources are quite limited, that funding budget is decreasing and that the number of research proposals rapidly increases year after year, the fundamental question is how one can bring \$\$\$ to his research? One strategy is to write an excellent proposal using molecular biology tools. Nonetheless, what catches your eyes in view of research projects and funding resources? How does one grasp research problems and march toward a new direction? How does one write an important and scientifically sound research proposal with new ideas, comprehensive designs, and methodologies? What is your research plan and where do you start? These questions may be particularly obvious to an investigator who does not have much experience in molecular biology research. This chapter can provide some insights and ideas that may be helpful to your novel research projects and obtain potential funding.

Another aim of this chapter is to guide graduate students in their thesis research. In our experience, good graduate training mandates independent performance with minimum advice from a mentor. How does one select a novel research project for a thesis? What are the hypotheses and objectives? How to design and conduct experiments to test your hypotheses? How does one grasp technical problems and master current techniques? Where does one begin and what are the predicted results? How to interpret research data and decide on the next experiments? As a matter of fact, a graduate student needs some help with these questions. This chapter will provide the clues.

The major objective of this book is to help the reader pursue research in molecular biology. The present chapter serves as a tour of how to use the current strategies

and techniques in the book in order to approach novel research strategies. Several examples of 2- to 5-year research proposals with specific aims, strategic designs, and methods are illustrated below. It should be noted that the following examples are not the real proposal format. It is hoped, however, that these examples will be a valuable guide for your novel research, proposal funding, and/or thesis research. The examples can also be adapted and applied to other appropriate novel research projects.

### **Proposal 1 Identification of a New Drug-Targeting Protein(s) and Isolation of Novel Gene(s)**

Drug discovery is one of the most interesting research projects to the public health and is certainly invaluable to pharmaceutical companies. Once a new drug is produced, it will open up broad areas for new research. The fundamental question is what its cure mechanism is. Many kinds of research can be conducted using the drug. In our view, the most promising research proposal is the identification of the drug-targeting protein(s) and isolation of novel gene(s). Because the molecular interaction is the basis for the cure of a disease with a new drug, it is reasonable to hypothesize that there may be one or more proteins or genes that are potentially targeted by the drug. Because the discovery of a new drug is of greatest concern to the public, this plan would most likely get funded by NIH, pharmaceutical companies, or other private sectors. Figure 1.1 illustrates the strategies, research design, and molecular biology methodologies that one can use, along with references to the appropriate chapters.


### **Proposal 2 Exploration of the Functions of the Gene Targeted by a New Drug**

Once a novel protein or gene targeted by a new drug or an important chemical has been identified, further research needs to be done. One logical and promising funding project is what the function of the targeted protein or gene is. The information from the research will provide crucial evidence for the cure mechanism of a disease by the drug. This involves sophisticated skills, including generation and use of transgenic mice as an animal model (Figure 1.2).


### **Proposal 3 Verification of Potential Function of a Specific Gene by the Gene Knockout Approach**

To verify the potential role of a novel, important gene, the best strategy is to knock out the expression of the gene. For example, if it is reasonable to believe that a gene plays a key role in heart development, a smart approach is to target the gene *in vivo* by knockout. If the gene becomes null, heart diseases such as failure of heart development would be predicted to occur based on the hypothesis. This is certainly a very sound proposal with promising funding for 3–4 years, assuming that no previous grants have been awarded for this type of proposal in other laboratories. The general approaches and methods are diagrammed in Figure 1.3.






**FIGURE 1.1** Research design for identification of novel gene(s) targeted by a new drug.



**FIGURE 1.2** Research approaches and technologies for exploration of potential functions of a new drug-targeting protein via cultured cells and animal models.



**FIGURE 1.3** Research approaches and methods for exploration of potential role(s) of a new drug-targeting protein via cultured cells and animal models.

#### **Proposal 4 Identification of the Functional Domain of a Protein by Site-Specific Mutagenesis**

Very often, the functions of a novel protein have been demonstrated but no one knows which specific fragment of the protein is the active domain or binding site. If the protein or enzyme is very important, there is a good reason to write a 2-year proposal on the identification of the functional domain of the novel protein or enzyme. The strategies for doing this are outlined in Figure 1.4.

#### **Proposal 5 Identification of Toxicant-Binding Protein(s) and Isolation of a Novel Gene That Is Related to the Toxicant and Heart Hypertrophy Using an Animal Model**


The heart is the first organ formed in animals, and heart diseases such as heart hypertrophy, heart attack, or failure are of great concern to the public. Additionally, toxicity mediated by toxicants becomes more and more of an environmental concern. If there is good reason to hypothesize that a toxicant (e.g., chemicals, proteins, drugs, carbohydrates) may be an inducer of heart hypertrophy, a 4- to 5-year proposal would be profound and promising for funding. This is a long-term research project that may need collaboration between laboratories. Specific aims, strategies, designs, expected results, and methodologies, as found in the appropriate chapters, are outlined in Figure 1.5.

#### **Proposal 6 Rescue of an Immune-Deficient System via Gene Therapy**


It is well known that immune deficiency, such as HIV, is the disease of greatest concern to the public at the present time. So many important proteins, such as the CD families, have been discovered to play a significant role in the deficient immune system. In order to increase the immune capabilities of patients, gene therapy has been established. Because of the great public interest in this type of therapy, research funding is virtually unlimited. Therefore, one may switch to this new avenue of research that involves several collaborators. In view of recent advances in molecular biology, a proposal regarding gene therapy will be a very good approach. Specifically, one may transfect human cells such as bone marrow stem cells with overexpression of sense cDNA constructs. Stably transfected cells that constitutively express proteins (e.g., CD4) can be directly injected into the immune system of the patient. An alternative way is to overexpress and purify a large amount of the proteins in bacteria or yeast, and then inject an appropriate dose of the protein molecules into the patient to activate the immune system using appropriate methodologies. Figure 1.6 illustrates the relevant research design strategies and methods that are covered in this book.

#### **Proposal 7 Discovery of IAA- or GA<sub>3</sub>-Binding Protein(s) and Isolation of Novel Gene(s) in Plants**


GA<sub>3</sub> and IAA are two well-known growth hormones in plants. They have been well studied in view of their actions on the physiology and biochemistry of plants. In spite of the fact that some laboratories have recently been working on the



**FIGURE 1.4** Design and methods for identification of functional domain(s) for a given protein by site-directed mutagenesis.



**FIGURE 1.5** Comprehensive project design and methods for identification of novel protein(s) and gene(s) in heart hypertrophy induced by a toxicant via an animal model.



**FIGURE 1.6** Research projects and methods for rescue of patients with immune deficiency by gene therapy.

molecular biology of these hormones, the mechanisms by which GA<sub>3</sub> and IAA can promote the growth of plants, especially in mutant phenotypes, are not really well understood. It appears that not much progress has been made so far. However, these two chemicals are very important hormones for normal plant development. From this point of view, and in order to promote new studies on the models of actions of these two hormones, one may launch a new proposal to the Department of Energy or the U.S. Department of Agriculture for the identification and isolation of GA<sub>3</sub>- and IAA-targeting proteins and novel genes, based on the hypothesis that the mechanisms of these hormones depend on hormone–protein interactions. This is an absolutely excellent research project for a PhD thesis, and is most likely to get funded. The suggested strategies and techniques for doing this are thus shown in Figure 1.7.

### **Proposal 8 Identification of Novel Proteins, cDNA, and Genes Induced or Repressed by a Specific Treatment**

It is reasonable to hypothesize that treatment of cultured cells or organisms with an important chemical, drug, alcohol, or hormone may induce or repress the expression of certain proteins. Therefore, a research proposal on the identification of these proteins and isolation of the cDNAs or genes coding for the proteins, especially the novel genes, would provide fundamental information about the action or mechanisms involved as a result of the treatment. Once a novel gene is isolated, it allows one to open a broad research area concerning the treatment, which has promise for funding. Meanwhile, this is an excellent research project for an MS or a PhD thesis. Figure 1.8 gives a guide for this type of research.


### **Proposal 9 Discovery of a Disease-Related New Protein(s) Via Protein–Protein Interaction**

It has been demonstrated that many proteins play critical role(s) in human diseases. More interestingly, numerous disease-related proteins are unknown. How to discover a new protein that is relevant to human health? How to explore the role(s) and mechanism(s) of the new protein in treatment of human diseases? One approach is protein–protein interaction. This is interesting and could be a well-funded research proposal.


Protein–protein interactions become an important research element of proteomics, functional genomics, and human disease treatment. Based on a known disease-related protein, one can design and execute protein–protein interaction experiments to identify new binding protein(s).

Having identified and mapped the binding or interacting regions between proteins of interest, it is highly recommended that one conduct research on the biological mechanisms of the proteins. For instance, if you hypothesize that protein X interacting with protein Y can result in inhibition of the formation and/or progression of brain tumors in patients, you should conduct experiments using animal models to obtain some preliminary data that are important for your publications and grant proposal application (Figure 1.9).






**FIGURE 1.7** Approaches of identification of novel gene(s) targeted by a hormone.




**FIGURE 1.8** Research outline for discovery of new proteins, cDNAs, and novel gene(s) induced by a chemical, toxicant, hormone, alcohol or, a drug.



**FIGURE 1.9** Diagram of procedures and specific proposal aims for cloning, identification, and characterization of human disease-related new protein(s) via protein–protein interaction strategies.

### **Proposal 10 Exploration of the Functions and Mechanism of Human Disease-Causing Gene via Conditional Gene Knockout**

Conditional gene knockout (CKO) is a relatively new technique that allows researchers to conditionally knockout the expression of the gene of interest in specific cell-, tissue-, or organ-type and/or at specific development stages, namely, “temporal and spatial knockout,” which is particularly important in investigating the biology of some lethal genes.<sup>22–24</sup> A lethal gene means that its expression during development can result in death of the animals bearing the gene. Therefore, CKO confers advantages over the conventional type in that genetically and conditionally modified mice are not only able to survive but also scientifically precise to genetically “turn on/off.” The general principle of CKO is the Cre–Lox recombination process. The CKO will alter the function of the protein of interest. As a result, the CKO mice will display unusual phenotypic changes. For instance, if you have isolated a gene and preliminary data showed that this gene could cause brain tumor development and that this gene had lethal effect to an animal, you could write a strong proposal for funding to explore the functions and mechanism of the gene using the CKO approach (Figure 1.10). Depending on the specific promoter used in the Cre DNA construct (i.e., brain specific) and the possible role of the targeted gene/protein of interest (i.e., tumor development), the successful CKO mouse could have bigger brain due to tumor



**FIGURE 1.10** Exploration of functions and mechanisms of gene X using conditional gene knockout approach.

development as compared to wild-type or the mouse line A or B. This indicated that the protein truncated in the targeted region could be a causal factor for brain tumor formation in mice.

## REFERENCES

1. Welsh, M. J., W. Wu, M. Parvinen, and R. R. Gilmont. 1996. Variation in expression of HSP27 messenger RNA during the cycle of the seminiferous epithelium and co-localization of HSP27 and microfilaments in Sertoli cells of the rat. *Biology of Reproduction* 55: 141–151.
2. Mehlen, P., X. Preville, P. Chareyron, J. Briolay, R. Klemenzenz, and A.-P. Arrigo. 1995. Constitutive expression of human hsp27, *Drosophila* hsp27, or human  $\alpha$ B-crystallin confers resistance to TNF- and oxidative stress-induced cytotoxicity in stably transfected murine L929 fibroblasts. *Journal of Immunology* 154: 363–374.
3. Iwaki, T., A. Iwaki, J. Tateishi, and J. E. Goldman. 1994. Sense and antisense modification of glial  $\alpha$ B-crystallin production results in alterations of stress fiber formation and thermoresistance. *Journal of Cell Biology* 15: 1385–1393.
4. Wu, W., and M. J. Welsh. 1996. Expression of HSP27 correlates with resistance to metal toxicity in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Applied Toxicology and Pharmacology* 141: 330–339.

5. Yang, N. S., J. Burkholder, B. Roberts, B. Martinell, and D. McCabe. 1990. *In vitro* and *in vivo* gene transfer to mammalian somatic cells by particle bombardment. *Proceedings of the National Academy of Sciences United States of America* 87: 9568.
6. Carmeliet, P., L. Schoonjans, L. Kiechens, B. Ream, J. Degen, R. Bronson, R. D. Vos, J. J. van den Oord, D. Collen, and R. C. Mulligan. 1994. Physiological consequences of loss of plasminogen activator gene function in mice. *Nature* 368: 419.
7. Johnston, S. A. 1990. Biolistic transformation: microbes to mice. *Nature* 346: 776.
8. Wu, W. 1995. Gene transfer and expression in animals. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. J. Cseke. Boca Raton, FL: CRC Press.
9. Capecchi, M. R. 1994. Targeted gene replacement. *Scientific American* 270: 52–59.
10. Capecchi, M. R. 1989. Altering the genome by homologous recombination. *Science* 244: 1288.
11. Mansour, S. L., K. R. Thomas, and M. R. Capecchi. 1988. Disruption of the proto-oncogene *int-2* in mouse embryo-derived stem cells: a general strategy for targeting mutations to non-selectable genes. *Nature* 336: 348.
12. Riele, H. T., E. R. Maandag, and A. Berns. 1992. Highly efficient gene targeting in embryonic stem cells through homologous recombination with isogenic DNA constructs. *Proceedings of the National Academy of Sciences of the United States of America* 89: 5128.
13. Schorle, H., T. Holtshcke, T. Hunig, A. Schimpl, and I. Horak. 1991. Development and function of T cells in mice rendered interleukin-2 deficient by gene targeting. *Nature* 352: 621.
14. Weinstock, P. H., C. L. Bisgaier, K. A. Setala, H. Badner, R. Ramakrishnan, S. L. Frank, A. D. Essenburg, R. Zechner, and J. L. Breslow. 1995. Severe hypertriglyceridemia, reduced high density lipoprotein, and neonatal death in lipoprotein lipase knockout mice. *Journal of Clinical Investigation* 96: 2555.
15. Michalska, A. E., and K. H. A. Choo. 1993. Targeting and germ-line transmission of a null mutation at the metallothionein I and II loci in mouse. *Proceedings of the National Academy of Sciences of the United States of America* 90: 8088.
16. Paul, E. L., M. L. Tremblay, and H. Westphal. 1992. Targeting of the T-cell receptor chain gene in embryonic stem cells: strategies for generating multiple mutations in a single gene. *Proceedings of the National Academy of Sciences of the United States of America* 89: 9929.
17. Robert, L. S., P. A. Donaldson, C. Ladaigue, I. Altosaar, P. G. Arnison, and S. Fabijanski. 1990. Antisense RNA inhibition of  $\beta$ -glucuronidase gene expression in transgenic tobacco can be transiently overcome using a heat-inducible  $\beta$ -glucuronidase gene construct. *Biotechnology* 8: 459.
18. Rezaian, M. A., K. G. M. Skene, and J. G. Ellis. 1988. Anti-sense RNAs of cucumber mosaic virus in transgenic plants assessed for control of the virus. *Plant Molecular Biology* 11: 463.
19. Hemenway, C., R.-X. Fang, W. K. Kaniewski, N.-H. Chua, and N. E. Tumer. 1988. Analysis of the mechanism of protection in transgenic plants expressing the potato virus X coat protein or its antisense RNA. *EMBO Journal* 7: 1273.
20. Dag, A. G., E. R. Bejarano, K. W. Buck, M. Burrell, and C. P. Lichtenstein. 1991. Expression of an antisense viral gene in transgenic tobacco confers resistance to the DNA virus tomato golden mosaic virus. *Proceedings of the National Academy of Sciences United States of America* 88: 6721.
21. Iwaki, T., A. Iwaki, J. Tateishi, and J. E. Goldman. 1994. Sense and antisense modification of glial  $\alpha$ B-crystallin production results in alterations of stress fiber formation and thermoresistance. *Journal of Cell Biology* 15: 1385–1393.
22. Sauer, B. 1987. Functional expression of the Cre–Lox site-specific recombination system in the yeast *Saccharomyces cerevisiae*. *Molecular and Cellular Biology* 7: 2087–2096.

23. Sauer, B., and N. Henderson. 1988. Site-specific DNA recombination in mammalian cells by the Cre recombinase of bacteriophage P1. *Proceedings of the National Academy of Sciences United States of America* 85: 5166–5170.
24. Wang, Y., J. Yang, H. Zheng, G. J. Tomasek, P. Zhang, P. E. McKeever, E. Y. Lee, and Y. Zhu, 2009. Expression of mutant p53 proteins implicates a lineage relationship between neural stem cells and malignant astrocytic glioma in a murine model. *Cancer Cell* 15: 514–526.

---

# 2 Rapid Isolation of Specific cDNAs or Genes by PCR

## 2.1 INTRODUCTION

Polymerase chain reaction (PCR) is a powerful method widely utilized to amplify specific DNA sequences *in vitro* using the appropriate primers.<sup>1-4</sup> It is a relatively rapid and sensitive procedure for amplification and cloning of the cDNA or genomic DNA of interest. In addition, it is valuable for analysis of RNA expression, genetic diagnosis, detection of mutations, and genetic engineering.<sup>2-11</sup> The principles of PCR starts from a pair of oligonucleotide primers that are specifically designed so that the forward or sense primer directs the synthesis of DNA toward the reverse or antisense primer and vice versa. During the PCR, *Taq* DNA polymerase, which is purified from *Thermus aquaticus*, is a heat-stable enzyme and catalyzes the synthesis of a new DNA strand that is complementary to a template DNA from 5'→3' direction by primer extension reaction, resulting in the production of the DNA region flanked by the two primers. Because the *Taq* DNA polymerase is high-temperature (95°C) stable, it is possible for target sequences to be amplified for many cycles using excess primers in a commercial thermocycler apparatus. Recently, high-quality *Taq* polymerases, such as recombinant polymerase *Tth*, long-span polymerase, and high fidelity PCR polymerase, have been developed. Because of their proofreading capability, these polymerases are considered more advanced enzymes compared with the traditional *Taq* DNA polymerase.

This chapter focuses on rapid amplification and isolation of specific cDNAs or genomic genes by PCR. Traditionally, cDNA or gene is isolated from cDNA or genomic DNA libraries, a process that involves the construction and screening of cDNA or genomic DNA libraries. The procedures are complicated, time-consuming, and costly. Moreover, it may be impossible to “fish” out the low copy cDNAs transcribed from rare mRNAs in cDNA libraries. In contrast, the rare cDNA can be rapidly amplified and isolated via reverse transcription (RT)-PCR. This chapter describes in detail protocols for fast isolation and purification of cDNAs or genes of interest. These protocols have been successfully used in our laboratories.

## 2.2 ISOLATION OF SPECIFIC FULL-LENGTH cDNAs BY RT-PCR METHOD

A full-length cDNA can be amplified via RT-PCR. To achieve this objective, a forward or sense primer and a reverse or antisense primer should be designed in the

5'-UTR (untranslation region) and the 3'-UTR regions of a known cDNA sequence or based on a known amino acid sequence.


### 2.2.1 ISOLATION OF RNAs

RNA isolation is described in Chapter 3.

### 2.2.2 DESIGN AND SYNTHESIS OF SPECIFIC FORWARD AND REVERSE PRIMERS


A pair of forward (sense, or upstream) primer and reverse (antisense or downstream) primer should be designed based on the 5'-UTR or 3'-UTR sequences of a known cDNA to be isolated (Figure 2.1). These sequences can be found in published cDNA data on the same species or possibly from different organisms. Specifically, the forward primer can be designed from the 5'-UTR in the 5'→3' direction with 20 to 30 bases, which should be complementary to the first or (–)strand of the cDNA template. The reverse primer is designed from the 3'-UTR region in the 5'→3' direction with 20 to 30 bases, which should be complementary to the second or (+)strand of the cDNA template.

Alternatively, forward and reverse primers can be designed based on the very N-terminal and C-terminal amino acid sequences in case the cDNA sequence is not available. As a result, if all goes well, a cDNA including the entire open reading frame (ORF) can be isolated with ease.<sup>2–4</sup> For example, assuming that the N-terminal and C-terminal amino acid sequences are NDPNG and DPCEW, respectively, the forward and reverse primers can be accordingly designed as 5'-AAC(T)GAT(C)CCIAA(C)TGGI-3' and 3'-GGTGAGCGTCCCTAG-5' (Figure 2.2). In case only the N-terminal amino acid sequence is available, a reverse primer may be designed as oligo(dT) (Figure 2.3).




**FIGURE 2.1** Diagram of isolation of full-length cDNA by RT-PCR.





**FIGURE 2.2** Diagram of isolation of full-length cDNA by RT-PCR using primers designed from known amino acid sequences.

It is very important that each pair of primers be carefully designed to anneal with two DNA strands. If two primers are annealed with the same DNA strand of the template, no PCR products will be produced. The primers should be analyzed by an appropriate computer program before they are used for PCR. We routinely use the Oligo Version 4.0 or CPrimer f program to check the quality of primers, including GC



**FIGURE 2.3** Diagram of isolation of full-length cDNA by RT-PCR using primers designed from known amino acid sequence and poly(A) tail. FP: forward primer.

contents,  $T_m$  value, potential formation of intraloops/dimers and interduplex of the primers, and potential annealing between the primers and the region flanked by the primers. In general, primers should be >17 bases with <60% GC contents. The first base at 5'- or 3'-end should be G or C followed by A or T for an efficient annealing. No more than four bases of introprimer or interprimer complementary are allowed.

The author recommends that two different restriction enzyme sites be designed at the 5'-end of the forward primer and the 3'-end of the reverse primer. This is invaluable in facilitating efficient subcloning of PCR products for characterization, such as DNA sequencing and *in vitro* transcription. The enzyme cutting site depends on the particular multiple cloning site (MCS) of an appropriate vector to be used for subcloning of PCR products. For example, 5'-GTGGATCCAACGATCCCAATGGTATTC-3' (forward primer containing *Bam*HI site) and 3'-GGTGAGCGTCCCTAGTTCGAATG-5' (reverse primer containing a *Hind*III site). After PCR amplification, the PCR products can be digested with *Bam*HI and *Hind*III and be subcloned at the *Bam*HI and *Hind*III sites of appropriate vectors that are digested with *Bam*HI and *Hind*III. The general procedures are outlined in Figures 2.1, 2.2, and 2.3.

### 2.2.3 AMPLIFICATION OF cDNA OF INTEREST BY RT-PCR

Target mRNA can be selectively transcribed to cDNA using a specific primer that anneals to the 3' portion near the target region of the mRNA. The author recommends that oligo(dT) primers be used to transcribe all the mRNA species into cDNAs. Oligo(dT) primers anneal to the 3' poly(A) tails of mRNA molecules and facilitate the synthesis of the first strand cDNAs. Avian myeloblastosis virus (AMV) reverse transcriptase and Moloney murine leukemia virus (MoMuLV) reverse transcriptase are commonly used RT reactions. RT kits are commercially available. A standard reaction volume is 25  $\mu$ l.

1. Perform synthesis of the first strand cDNAs from mRNA.
  - (a) Anneal 10  $\mu$ g of total RNA or 1  $\mu$ g of mRNA template with 1  $\mu$ g of oligo(dT) primers in a sterile RNase-free microcentrifuge tube. Add nuclease-free dd.H<sub>2</sub>O to a total volume of 15  $\mu$ l. Heat the reaction at 70°C for 5 min and allow it to slowly cool to room temperature to finish annealing. Briefly spin down the mixture to the bottom of the microcentrifuge tube.
  - (b) Add the following reagents to the annealed primer/template mixture in the order shown below:

First strand 5 $\times$ buffer	5 $\mu$ l
rRNasin ribonuclease inhibitor	50 units (25 units/ $\mu$ g mRNA)
40 mM sodium pyrophosphate	2.5 $\mu$ l
<u>AMV reverse transcriptase</u>	<u>30 units (15 units/<math>\mu</math>g mRNA)</u>
Add nuclease-free dd.H <sub>2</sub> O to a total volume of	25 $\mu$ l

- (c) Incubate the reaction at 42°C for 60 min. At this point, the synthesis of the first strand cDNAs is complete.

- (d) Stop the reaction by adding 2  $\mu$ l of 0.2 M EDTA to the mixture and place it on ice.
- (e) Precipitate the cDNAs by adding 2.5 volumes of chilled ( $-20^{\circ}\text{C}$ ) 100% ethanol to the tube. Gently mix and allow precipitation to occur at  $-20^{\circ}\text{C}$  for 2 h.
- (f) Centrifuge at the top speed for 5 min. Carefully remove the supernatant, briefly rinse the pellet with 1 ml of cold 70% ethanol, and gently drain away the ethanol.
- (g) Dry the cDNA pellet under vacuum for 10 min, and dissolve the cDNA pellet in 10  $\mu$ l of TE buffer. Take 2  $\mu$ l of the sample to measure the concentration of cDNAs before PCR. Store the sample at  $-20^{\circ}\text{C}$  until use.

### Reagents needed

- *10 $\times$  AMV or MoMuLV buffer*  
0.1 M Tris-HCl, pH 8.3  
0.5 M KCl  
25 mM  $\text{MgCl}_2$
  - *Stock dNTPs*  
10 mM dATP  
10 mM dTTP  
10 mM dATP  
10 mM dTTP
  - *Working dNTPs solution*  
10  $\mu$ l dATP (10 mM)  
10  $\mu$ l dTTP (10 mM)  
10  $\mu$ l dATP (10 mM)  
10  $\mu$ l dTTP (10 mM)
2. Carry out amplification of specific cDNAs by PCR in a 0.5-ml microcentrifuge tube.
    - (a) Prepare a PCR cocktail as follows:

Forward primer	5–8 pmol (30–40 ng) depending on the size of primer
(36–43-mer, 10–30 ng/ $\mu$ l)	
Reverse primer	5–8 pmol (30–40 ng) depending on the size of primer
(36–43-mer, 10–30 ng/ $\mu$ l)	
cDNAs	1–2 $\mu$ g
10 $\times$ amplification buffer	4 $\mu$ l
dNTPs (2.5 mM each)	4 $\mu$ l
<u>Taq or Tth DNA polymerase</u>	<u>5–10 units</u>
Add dd.H <sub>2</sub> O to a final volume of	40 $\mu$ l

Note: *The DNA polymerase should be high fidelity and long expand, which is commercially available.*

- (b) Overlay the mixture with 30  $\mu$ l of mineral oil to prevent evaporation of the samples during PCR amplification. Place the tubes in a thermal cycler and perform PCR.

Profile	Predenaturation	Cycling (30 Cycles)			Last
		Denaturation	Annealing	Extension	
Template (<4 kb) Primer is <24 bases or with <40% G-C content	94°C, 3 min	94°C, 1 min	60°C, 1 min	70°C, 1.5 min	4°C
Template is >4 kb Primer is >24mer or <24 bases with >50% G-C content	95°C, 3 min	95°C, 1 min	60°C, 1 min	72°C, 2 min	4°C

## 2.2.4 PURIFICATION OF PCR PRODUCTS BY HIGH-SPEED CENTRIFUGATION OF AGAROSE GEL SLICES

1. Load the amplified PCR mixture into a 1% to 1.4% agarose gel, depending on the sizes of the PCR products, and carry out electrophoresis.
2. When electrophoresis is complete, quickly locate the DNA band of interest by illuminating the gel on a long wavelength (>300 nm) UV transilluminator. Quickly slice out the band of interest using a sharp, clean razor blade.

Note: *To avoid potential damage to the DNA molecules, the UV light should be turned on as briefly as possible.*

3. To enhance the yield of DNA, trim away extra agarose gel outside the band and cut the gel slice into tiny pieces with a razor blade.
4. Transfer the fine slices into a 1.5-ml microcentrifuge tube (Eppendorf).

Notes:

(1) *If one does not need to elute DNA out of the gel slices, the slices do not need to be further sliced into tiny pieces. They can be directly placed in a tube.*

(2) *At this point, there are two options for eluting DNA from the agarose gel pieces. The first option is to immediately carry out high-speed centrifugation (step 5). The second option is to elute the DNA as high yield as possible (see below).*

5. Centrifuge at 12,000 to 14,000 g or at the highest speed using an Eppendorf centrifuge 5415C (Brinkmann Instruments, Inc.) for 15 min at room temperature.

Principles: *With high-speed centrifugation, the agarose matrix is compressed, and/or even partially destroyed, by the strong force of centrifugation. The DNA molecules contained in the matrix are released into the supernatant fluid.*

6. After centrifugation, carefully transfer the supernatant fluid containing DNA into a clean microcentrifuge tube. The DNA can be used directly for ligation, cloning, labeling, and restriction enzyme digestion without ethanol precipitation. Store the DNA solution at 4°C or -20°C until use.

Tips:

(1) *In order to confirm that the DNA is released from the gel pieces, the tube containing the fluid can be briefly illuminated with long wavelength UV light after centrifugation. An orange-red fluid color indicates the presence of DNA in the fluid.*


(2) *The supernatant fluid should be immediately transferred from the agarose pellet; within minutes, the temporarily compressed agarose pellet may swell, absorbing the supernatant fluid.*

High yield and cleaner elution of DNA:

1. Add 100 to 300  $\mu\text{l}$  of distilled deionized water (dd.H<sub>2</sub>O) or TE buffer (10 mM Tris-HCl, 1 mM EDTA, pH 8.0) to the gel pieces described in step 4.  
*Function: TE buffer or dd.H<sub>2</sub>O is added to the gel pieces to help elute the DNA and to simultaneously wash EtBr from the DNA during high-speed centrifugation.*
2. Centrifuge at 12,000 to 14,000 g at room temperature for 20 min. When centrifugation is complete, briefly visualize the eluted DNA in the fluid by illumination using a long wavelength UV light.
3. Immediately transfer the supernatant that contains the eluted DNA into a fresh tube.
4. To increase the recovery of DNA, extract the agarose pellet by resuspending the pellet in 100  $\mu\text{l}$  of dd.H<sub>2</sub>O or TE buffer followed by another cycle of centrifugation.
5. Pool the DNA supernatant and precipitate the DNA with ethanol. Dissolve DNA 10  $\mu\text{l}$  of dd.H<sub>2</sub>O or TE buffer. Store the DNA at 4°C or -20°C until use. Proceed to subcloning and characterization of the PCR products.

### 2.3 AMPLIFICATION AND ISOLATION OF cDNA ENDS BY 5'-RACE

5'-RACE stands for rapid amplification of 5'-cDNA ends and is widely utilized in amplifying and/or isolating partial-length cDNA transcribed from some rare mRNAs. As shown in Figure 2.4, the procedures and principles are quite similar to those described above except for the addition of oligo(dC) and the use of oligo(dG) as an anchor primer or forward primer. A reverse primer can be designed according to the known sequence in the 5'-portion of the cDNA to be amplified or the N-terminal amino acid of the protein of interest. Addition of oligo(dC) to the 3'-end of the first



**FIGURE 2.4** Diagram of 5'-RACE PCR.

strand cDNA can be facilitated using terminal deoxynucleotidyl transferase. The drawback of this approach is the potential nonspecific priming if the target cDNA sequence is GC-rich. Nonetheless, this strategy provides a powerful tool for analysis of the expression of rare messages. If the 5'-UTR sequence is available or the N-terminal amino acid sequence is known, the addition of oligo(dC) and synthesis of (dG) anchor primer is not necessary. A forward primer can be designed in the 5'-UTR sequence or N-terminal amino acid sequence.


## 2.4 AMPLIFICATION AND ISOLATION OF cDNA ENDS BY 3'-RACE

Similar to 5'-RACE, 3'-RACE or rapid amplification of 3'-cDNA ends is applied to amplify and isolate the 3'-portion of rare cDNAs made from rare mRNAs. It is simpler than 5'-RACE because there is no need for the addition of oligo(dC). A forward primer can be designed according to the 3'-portion of cDNA to be amplified or based on known C-terminal amino acid sequence. A reverse sequence may be universal primer or poly(T) primer. The procedure is outlined in Figure 2.5, which is quite similar to that described above.

## 2.5 ISOLATION OF GENE OF INTEREST BY PCR

### 2.5.1 ISOLATION OF GENOMIC DNA

1. For cultured cells, aspirate culture medium and briefly rinse the cells twice in PBS. Add 10 ml/60 mm culture plate (with approximately  $10^5$  cells) of DNA isolation buffer to the cells and allow cells to be lysed for 5 min at



**FIGURE 2.5** Diagram of isolation of 3'-RACE PCR.

room temperature with shaking at 60 rpm. For tissues, grind 1 g tissue in liquid N<sub>2</sub> to fine powder and transfer the powder into a tube containing 15 ml of DNA isolation buffer. Allow cells to be lysed for 10 min at room temperature with shaking at 60 rpm.

2. Incubate at 37°C for 5 h or overnight to degrade proteins, and extract genomic DNA.
3. Allow the lysate to cool to room temperature and add 3 volumes of 100% ethanol pre-cold at -20°C to the lysate. Gently mix it and allow DNA to precipitate at room temperature with slow shaking at 60 rpm. Precipitate DNA in appearance of white fibers should be visible in 20 min.
4. "Fish" out the DNA using a sterile glass hook or spin down the DNA. Rinse the DNA twice in 70% ethanol and partially dry the DNA for 40 to 60 min at room temperature to evaporate ethanol. The DNA can be directly subjected to restriction enzyme digestion without being dissolved in TE buffer or dd.H<sub>2</sub>O. We usually overlay the precipitated DNA with an appropriate volume of restriction enzyme digestion cocktail and incubate the mixture at an appropriate temperature for 12 to 24 h. The digested DNA is mixed with an appropriate volume of DNA loading buffer and is ready for agarose gel electrophoresis.

### Reagents needed

- *DNA isolation buffer*  
75 mM Tris-HCl, pH 6.8  
100 mM NaCl  
1 mg/ml protease K (freshly added)  
0.1% (w/v) *N*-lauroylsarcosine

## 2.5.2 PARTIAL DIGESTION OF GENOMIC DNA USING *Sau3AI*

It is necessary to partially cut the high molecular weight of genomic DNA with a four-base cutter, *Sau3AI*, to increase the efficiency of PCR.

### 2.5.2.1 Optimization of Partial Digestion of Genomic DNA with *Sau3AI*

To determine the amount of enzyme used to digest the high-molecular-weight DNA into 20- to 30-kb fragments, small-scale reactions, or pilot experiments, should be carried out.

(a) Prepare 1× *Sau3AI* buffer on ice:

10× <i>Sau3AI</i> buffer	0.2 ml
Add dd.H <sub>2</sub> O to a final volume of	2.0 ml

(b) Perform *Sau3AI* dilutions in 10 individual microcentrifuge tubes on ice:

Tube #	<i>Sau3AI</i> (3 u/μl) Dilution	Dilution Factors
1	2 μl <i>Sau3AI</i> + 28 μl 1× <i>Sau3AI</i> buffer	1/15
2	10 μl of 1/15 dilution + 90 μl 1× <i>Sau3AI</i> buffer	1/150
3	10 μl of 1/150 dilution + 10 μl 1× <i>Sau3AI</i> buffer	1/300
4	10 μl of 1/150 dilution + 30 μl 1× <i>Sau3AI</i> buffer	1/600
5	10 μl of 1/150 dilution + 50 μl 1× <i>Sau3AI</i> buffer	1/900
6	10 μl of 1/150 dilution + 70 μl 1× <i>Sau3AI</i> buffer	1/1200
7	10 μl of 1/150 dilution + 90 μl 1× <i>Sau3AI</i> buffer	1/1500
8	10 μl of 1/150 dilution + 110 μl 1× <i>Sau3AI</i> buffer	1/1800
9	10 μl of 1/150 dilution + 190 μl 1× <i>Sau3AI</i> buffer	1/3000
10	10 μl of 1/150 dilution + 290 μl 1× <i>Sau3AI</i> buffer	1/4500

(c) Perform 10 individual, small-scale digestion reactions on ice in the order listed below:

Components	Tube Number									
	1	2	3	4	5	6	7	8	9	10
Genomic DNA (1 μg/μl)	1 (μl)	1	1	1	1	1	1	1	1	1
10× <i>Sau3AI</i> buffer	5 (μl)	5	5	5	5	5	5	5	5	5
dd.H <sub>2</sub> O (μl)	39	39	39	39	39	39	39	39	39	39
<i>Sau3AI</i> dilution in the same order as in (b) above	5 (μl)	5	5	5	5	5	5	5	5	5
Final volume (μl)	50	50	50	50	50	50	50	50	50	50

*Note:* The final *Sau3AI* concentration used in tube nos. 1 to 10 should be 1, 0.1, 0.05, 0.025, 0.015, 0.0125, 0.01, 0.0085, 0.005, and 0.0035 unit/μg DNA, respectively.



- (d) Incubate the reactions at the same time at 37°C for 30 min. Place the tubes on ice and add 2 µl of 0.2 M EDTA buffer (pH 8.0) to each tube to stop the reaction.
- (e) During the reactions, prepare a large size of 0.4% agarose gel in 1× TBE buffer.
- (f) Add 10 µl of 5× DNA loading buffer to each of the 10 tubes containing the digested DNA prepared in step (d).
- (g) Load 30 µl of each sample to the wells in the order of 1 to 10. Load DNA markers (e.g., 1 µg DNA *Hind*III markers) to the left or the right well of the gel to estimate the sizes of digested DNA.
- (h) Carry out electrophoresis of the gel at 2 to 5 V/cm until the bromphenol blue reaches the bottom of the gel.
- (i) Photograph the gel under UV light and find the well that shows the maximum intensity of fluorescence in the desired DNA size range of 20 to 30 kb.

### 2.5.2.2 Large-Scale Preparation of Partially Digested Genomic DNA

- (a) Based on the optimal conditions established above, carry out a large-scale digestion of 50 µg of high-molecular-weight genomic DNA using half units of *Sau*3AI/µg DNA that produced the maximum intensity of fluorescence in the DNA size range of 20 to 30 kb. The DNA concentration, time, and temperature should exactly be the same as those used for the small-scale digestion. For instance, if tube no. 7 (0.01 unit of *Sau*3AI/µg DNA) in the small-scale digestion of the DNA shows a maximum intensity of fluorescence in the size range of 20 to 30 kb, the large-scale digestion of the same DNA can be carried out as follows.

Genomic DNA (1 µg/µl)	50µl
10× <i>Sau</i> 3AI buffer	250 µl
dd.H <sub>2</sub> O	1.95 ml
Diluted <i>Sau</i> 3AI (0.005 u/µg) prepared as step 1 (b), tube #9	250 µl
<hr/>	
Final volume of	2.5 ml

- (b) Incubate the reactions at 37°C in a water bath for 30 min. Stop the reaction by adding 20 µl of 0.2 M EDTA buffer (pH 8.0) and place the tube on ice until use.
- (c) Add 2 to 2.5 volumes of chilled 100% ethanol to precipitate the DNA at -70°C for 30 min.
- (d) Centrifuge at 12,000 *g* for 10 min at room temperature. Carefully decant the supernatant and briefly rinse the DNA pellet with 5 ml of 70% ethanol. Dry the pellet under vacuum for 8 min. Dissolve the DNA in 50 µl of TE buffer. Take 5 µl of the sample to measure the concentration at  $A_{260\text{ nm}}$  and store the DNA sample at -20°C before use.


## Reagents needed

- *10× Sau3AI buffer*  
0.1 M Tris-HCl, pH 7.5  
1 M NaCl  
70 mM MgCl<sub>2</sub>
- *5× Loading buffer*  
38% (w/v) sucrose  
0.1% bromphenol blue  
67 mM EDTA
- *5× TBE buffer*  
54 g Tris base  
27.5 g boric acid  
20 ml of 0.5M EDTA, pH 8.0
- *TE buffer*  
10 mM Tris-HCl, pH 8.0  
1 mM EDTA, pH 8.0  
Ethanol (100%, 70%)

## 2.5.3 DESIGN AND SYNTHESIS OF SPECIFIC FORWARD AND REVERSE PRIMERS

### 2.5.3.1 Amplification and Isolation of Exon and Intron Sequences

A pair of forward and reverse primers can be designed based on the 5'-UTR or 3'-UTR sequences of a known cDNA. The forward primer can be designed in the 5'-UTR region in the 5'→3' direction with 20 to 30 bases, which should be complementary to the first or (-)strand of cDNA template. The reverse primer is designed in the 3'-UTR region in the 5'→3' direction with 20 to 30 bases, which should be complementary to the second or (+)strand of cDNA template (Figure 2.6a). Alternatively, forward and



**FIGURE 2.6** Design of primers for amplification and isolation of exon and intron sequences. (a) Forward primer (FP) and reverse primer (RP) are designed from the 5'-UTR and 3'-UTR sequences of a known cDNA. (b) FP and RP are designed based on the very N-terminal or C-terminal amino acid sequence. E, exon; I, intron.

reverse primers can be designed based on the very N-terminal and C-terminal amino acid sequences if the cDNA sequence is not known (Figure 2.6b).


**2.5.3.2 Amplification and Isolation of Promoter Sequence**

To amplify the promoter sequence of interest, a reverse primer can be designed according to the 5'-end sequence of known cDNA or based on the N-terminal amino acid sequence. This primer will be employed to anneal with a DNA strand of the denatured genomic DNA fragments. The primer facilitates the synthesis of a new strand, which is complementary to the template and includes the promoter sequence. After addition of oligo(dC) to the 3'-end of the new strand, an oligo(dG) anchor primer or forward primer in the cloning site of the vector will facilitate the synthesis of the DNA strand that is complementary to the new strand. As a result, major PCR products including the promoter sequence will be obtained (Figure 2.7).

**2.5.4 AMPLIFICATION OF SPECIFIC DNA FRAGMENTS BY PCR**

1. Prepare a PCR cocktail in a 0.5-ml microcentrifuge tube.
 

Forward primer	5–8 pmol (30–40 ng) depending on the size of primer
(20- to 26-mer, 10–30 ng/μl)	
Reverse primer	5–8 pmol (30–40 ng) depending on the size of primer



**FIGURE 2.7** Diagram of amplification and isolation of promoter region of interest by PCR.

(20- to 26-mer, 10–30 ng/μl)	
Digested genomic DNA	2–3 μg
10× amplification buffer	4 μl
dNTPs (2.5 mM each)	4 μl
<i>Taq</i> or <i>Tth</i> DNA polymerase	5–10 units
Add dd.H <sub>2</sub> O to a final volume of	40 μl

Note: *The DNA polymerase should be of high fidelity and long expand.*

- Carefully overlay the mixture with 30 μl of mineral oil to prevent evaporation of the samples during PCR amplification. Place the tubes in a thermal cycler and perform PCR.

Predenaturation	Cycling (35 Cycles)			
	Denaturation	Annealing	Extension	Last
95°C, 3 min	95°C, 1 min	60°C, 1 min	72°C, 2 min	4°C

## 2.5.5 PURIFICATION OF PCR PRODUCTS BY AGAROSE GELS

Perform electrophoresis and elution of PCR products as described earlier in this chapter. Because of the different sizes of genomic DNA fragments, multiple PCR bands may be shown in agarose gels. These bands should be individually isolated for characterization.

## 2.6 SUBCLONING OF cDNA OR GENE OF INTEREST

Detailed protocols are described in Chapter 4.

## 2.7 CHARACTERIZATION OF PCR PRODUCTS

To verify whether the DNA of interest is obtained, PCR products should be characterized by Southern blotting using a specific probe (see Chapter 7) and by DNA sequencing (Chapter 5). The sequence can be compared with known or expected DNA sequences in GenBank databases (Chapter 6).

## REFERENCES

- Wu, W. 1995. PCR techniques and applications. In *Handbook of molecular and cellular methods in biology and medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke, 243–262. Boca Raton, FL: CRC Press.
- Ausubel, F. M., R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl. 1995. *Current protocols in molecular biology*. New York, NY: Greene Publishing Associates and Wiley-Interscience, John Wiley and Sons.
- Erllich, H. A. 1989. *PCR technology: Principles and applications for DNA amplification*. New York, NY: Stockton Press.
- Wu, L.-L., I. Song, N. Karupiah, and P. B. Kaufman. 1993. Kinetic induction of oat shoot pulvinus invertase mRNA by gravistimulation and partial cDNA cloning by the polymerase chain reaction. *Plant Molecular Biology* 21: 1175.

5. Innis, M. A., D. H. Gelfand, J. J. Sninsky, and T. J. White. 1989. *PCR protocols: A guide to methods and applications*. New York, NY: Academic Press.
6. Wang, A. M., M. V. Doyle, and D. F. Mark. 1989. Quantitation of mRNA by the polymerase chain reaction. *Proceedings of the National Academy of Sciences of the United States of America* 86: 9717.
7. Arnold, C., and I. J. Hodgson. 1991. Vectorette PCR: A novel approach to genomic walking. *PCR Methods and Applications* 1: 39–42.
8. Barany, F. 1991. Genetic disease detection and DNA amplification using cloned thermostable ligase. *Proceedings of the National Academy of Sciences of the United States of America* 88: 189.
9. Lu, W., D.-S. Han, J. Yuan, and J.-M. Andrieu. 1994. Multi-target PCR analysis by capillary electrophoresis and laser-induced fluorescence. *Nature* 368: 269.
10. Bloomquist, B. T., R. C. Johnson, and R. E. Mains. 1992. Rapid isolation of flanking genomic DNA using biotin-RAGE a variation of single-sided polymerase chain reaction. *DNA Cell Biology* 10: 791.
11. Edwards, J. B. D. M., J. Delort, and J. Mallet. 1991. Oligodeoxyribonucleotide ligation to single-stranded cDNAs: a new tool for cloning 5' ends of mRNAs and for constructing cDNA libraries by *in vitro* amplification. *Nucleic Acids Research* 19: 5227–5232.



---

# 3 Construction and Screening of Subtracted and Complete Expression cDNA Libraries


## 3.1 INTRODUCTION

Cloning of cDNAs plays an important role in current molecular biology.<sup>1-7</sup> Construction of a cDNA library is a highly sophisticated technology that involves a series of enzymatic reactions. The quality and integrity of the cDNA library greatly impact the success or failure in isolation of the cDNAs of interest.<sup>2</sup> The general principles begin with mRNA that is transcribed into the first-strand DNA, called a complementary DNA or cDNA, which is based on nucleotide bases complementary to the mRNA template. This step is catalyzed by AMV reverse transcriptase using oligo(dT) primers. The second strand DNA is copied from the first strand cDNA using DNA polymerase I, thus producing a double-stranded cDNA molecule. Subsequently, the double-stranded cDNA is ligated to an adapter and then to an appropriate vector via T4 DNA ligase. The recombinant vector-cDNA molecules are then packaged *in vitro* and cloned in a specific host, generating a cDNA library. Specific cDNA clones can be “fished” out by screening the library with a specific probe.<sup>1,4-10</sup>

cDNA cloning takes advantage of the 3' hairpins produced by AMV reverse transcriptase during the synthesis of the first strand cDNAs. The hairpins are used to prime the second strand cDNA that is catalyzed by Klenow DNA polymerase and reverse transcriptase. Hence, *SI* nuclease is needed to cleave the hairpin loops. However, the digestion is difficult and causes a low cloning efficiency and the loss of significant sequence information corresponding to the 5' end of the mRNA.<sup>2</sup> To solve this problem, 4 mM sodium pyrophosphate is utilized to suppress the formation of hairpins during the synthesis of the first-stranded cDNA. The second strand cDNA is then produced by RNase H to create nicks and gaps in the hybridized mRNA template, generating 3'-OH priming sites for DNA synthesis using DNA polymerase I. After treatment with T4 DNA polymerase to remove any remaining 3' protruding ends, the blunt-ended, double-stranded cDNAs are ready for ligation with adaptors or linkers. Therefore, *SI* digestion is eliminated and the cloning efficiency is much higher than that obtained with the classic method. Besides, the sequence information is optimally reserved.

cDNA cloning can be grouped into two classes: random cloning and orientation-specific cloning.<sup>1</sup> The random or classical cDNA cloning uses oligo(dT) as a primer and  $\lambda$ gt10 as cloning vectors (Figure 3.1a). The cDNA is cloned at the unique *EcoRI* site. Because of the single *EcoRI* site for cloning, the cDNAs are cloned in a random manner in both sense and antisense orientations. The constructed cDNA library can be screened using a DNA or RNA probe but not antibodies. In random cDNA cloning, if the expression vector  $\lambda$ gt11 (Figure 3.1b) is used for a cDNA library, the library can be screened using a specific antibody as well as a DNA or RNA probe. The disadvantage of using antibodies is that the possibility of obtaining the positive clones is at least 50% less than it actually is. This is because approximately 50% of cloned cDNAs are expressed as antisense RNA that can interfere with sense RNA by inhibiting the translation of the sense RNA to proteins. This shortcoming is eliminated in the orientation-specific or directional cDNA cloning using a primer-adaptor to prime the synthesis of the first strand cDNA and the use of  $\lambda$ gt11 as cloning vectors (see Section 3.3, “Construction and Screening of a Complete Expression cDNA Library”). The primer-adaptor consists of oligo(dT) adjacent to a unique restriction site (*XbaI* or *NotI*). The double-stranded cDNAs with *EcoRI* adaptors at the ends are digested with either *XbaI* or *NotI*. As a result, the digested cDNAs contain two incompatible termini: one *EcoRI* and one *XbaI* or *NotI*. In this way, self-ligation of adapter-cDNA molecules is substantially eliminated. These molecules are readily ligated with vectors containing the same restriction enzyme termini (see Figure 3.6 for detail). As compared with the random cloning method, the directional cDNA cloning is much more powerful and valuable. A factor of 2 is the likelihood of expressing the cDNA inserts as the correct polypeptides using  $\lambda$ gt11 *Sfi-NotI*. In theory, no antisense RNA interference will occur in the directional cDNA cloning approach.

More advanced lambda vectors are available, in which promoters of T7, T3, or SP6 RNA polymerase are included adjacent to the multiple cloning site (Figure 3.1c).



**FIGURE 3.1** Structural maps of vectors used for cDNA cloning.



All cDNAs can be cloned in the same direction downstream from T7, T3, or SP6 promoter. Sense or antisense RNA probes can be produced *in vitro*, which can be utilized as RNA probes for screening of a cDNA or genomic DNA library or for northern blot analysis.

Based on the author's experience, there are three critical steps for the success or failure in construction of a cDNA library. First is the purity and integrity of the mRNAs used for the synthesis of the first strand cDNAs. Any degradation or absence of specific mRNAs will result in partial-length cDNAs or complete loss of the specific cDNAs, especially for some rare mRNAs. The second important step is to obtain full-length cDNAs. If this procedure is not performed well, even if you have a very good mRNA source, the cDNA library is not so good. In that case, you may "fish" out only partial-length cDNAs or no positive clones at all. Once double-strand cDNAs are obtained, they are much more stable as compared with mRNAs. A third essential step in cDNA cloning is the ligation of cDNAs with adaptors to vectors. If the ligation fails or is of low efficiency, *in vitro* packaging of recombinant  $\lambda$ DNAs cannot be carried out effectively. As a result, the plaque-forming units (pfu) number or efficiency will be very low. In that case, a poor cDNA library is not recommended for screening of specific cDNA clones. To construct an excellent cDNA library, the following precautions should be taken. Elimination of RNase contamination must be carried out whenever possible. Procedures for creating an RNase-free laboratory environment for mRNA and cDNA synthesis include: (1) disposable plastic test tubes, micropipette tips, and microcentrifuge tubes should be sterilized; (2) gloves should be worn at all times and changed often to avoid finger derived RNase contamination; (3) all glassware and electrophoresis apparatus used for cDNA cloning should be separated from other labware; (4) glassware should be treated with 0.1% diethyl pyrocarbonate (DEPC) solution, autoclaved to remove the DEPC, and baked overnight at 250°C before being used; (5) solutions to be used with mRNA and cDNA synthesis should be treated with 0.1% DEPC (v/v) to inhibit RNase by acylation; (6) DEPC is recommended to be added to solutions with vigorous stirring for 20 min. The solutions should be autoclaved or by heating at 70°C for 1 h to remove the DEPC. It should be noted that because DEPC reacts with amines and sulfhydryl groups, reagents such as Tris and DTT cannot be treated directly with DEPC. These solutions can be made using DEPC-treated and sterile water. If solutions such as DTT cannot be autoclaved, the solution should be sterile-filtered.

Construction of a cDNA library is a highly sophisticated procedure. One should have a strong molecular biology background and intensive laboratory experience in molecular biology when working on a cDNA library. In spite of the fact that some commercial kits or cDNA libraries are available, often, a lot of laboratories need to construct a specific library with the mRNAs expressed in a specific cell/tissue type in the spatial and temporal manner. This chapter provides detailed and successful protocols for construction and screening of a cDNA library. Two major strategies are described. One is the subtracted cDNA library in which cDNAs are derived from mRNAs expressed in a specific cell or tissue type but not in another type. The cell/tissue type-specific cDNA clones are greatly enriched in the library, which allows one to readily isolate specific cDNAs copied from rare mRNAs. The other is the complete expression cDNA library that includes all cDNA clones from all mRNAs

in a specific cell or tissue type. The step-by-step protocols described in this chapter allow experienced workers as well as beginners to construct cDNA libraries.


### **3.2 CONSTRUCTION AND SCREENING OF A SUBTRACTED cDNA LIBRARY**

Construction of a subtracted cDNA library can allow one to identify specific cDNA clones corresponding to a specific mRNAs expressed in one cell or tissue type but not in another type. For instance, treatment of cultured cells or organisms with an important chemical, drug, alcohol, or hormone may induce or repress the expression of certain genes. In some cases, some novel genes encoding new mRNAs and proteins can be identified corresponding to a specific treatment, which may provide fundamental information about the action or mechanisms of the treatment. Once a novel gene is isolated, it allows one to open a broad research area concerning the treatment with promising results. In addition, a subtracted cDNA library consists of enriched cDNAs that provide the user with a powerful tool to isolate some rare cDNAs transcribed from rare mRNAs, which may be difficult to identify via screening of a complete cDNA library.<sup>1,2</sup>

The general procedures are outlined in Figure 3.2. The first step is to isolate total RNAs or mRNAs and to make the first strand cDNAs representing all of the mRNAs expressed in each of two cell/tissue types of interest. The single-stranded cDNAs in one cell or tissue type are subjected to hybridization with total mRNAs from another type. For example, in cell or tissue type A, any cDNAs that represent sequences expressed in type B will form DNA/mRNA hybrids with the corresponding mRNAs in cell- or tissue-type B, or vice versa. Therefore, the unhybridized cDNAs are specific in type A, but not in type B, or vice versa. Both single-stranded cDNAs and cDNA/mRNA hybrids can be separated by chromatography on hydroxyapatite (HAP) columns. The unhybridized cDNAs are then used to synthesize double-stranded (ds) cDNAs, which are then ligated to appropriate adaptors, vectors, and are utilized to construct a subtracted cDNA library in which the sequences specific to one cell or tissue type are greatly enriched. As compared with a complete cDNA library, a subtracted cDNA library contains an enriched set of cDNA clones, which simplifies the screening procedures using much smaller numbers of pfu in the primary screening. As a result, the purification process of the cDNA of interest can be speeded up.<sup>1</sup>

#### **3.2.1 ISOLATION OF TOTAL RNAs FROM CELL- OR TISSUE-TYPE A AND B OF INTEREST**

The quality and integrity of RNAs play a critical role in the success of construction of a cDNA library. Compared with DNA, RNAs are very mobile molecules due to their degradation by RNases. To obtain high yield and high quality of RNAs, four procedures should be handled properly and effectively: (1) optimal disruption of cells or tissues; (2) effective denaturation of nucleoprotein complexes; (3) maximum inhibition of exogenous RNases and endogenous RNases released from cells upon



**FIGURE 3.2** Scheme of construction and screening of a subtracted cDNA library.

cell disruption; (4) effective purification of RNA from DNA and proteins. The most difficult thing, however, is to inactivate RNase activity. In our experience, the following procedures are very effective in inactivation of RNases.

*To inactivate exogenous RNase.* Two common sources of RNase contamination are the user's hands and bacteria and fungi in airborne dust particles. Therefore, (1) gloves should be worn and changed frequently; (2) whenever possible, disposable plasticware should be autoclaved; (3) nondisposable glassware and plasticware should be treated with 0.1% DEPC in dd.H<sub>2</sub>O and be autoclaved before use; and (4) glassware should be baked at 250°C overnight. Disposable and sterile polypropylene centrifuge tubes are strongly recommended to be used in RNA isolation. Glass Corex tubes must be thoroughly cleaned, DEPC treated and autoclaved, followed by being baked at 250°C overnight before use.

*To inactivate endogenous RNase.* 4 M guanidine thiocyanate and  $\beta$ -mercaptoethanol are strongly recommended in the extraction buffer. These chemicals are strong inhibitors of RNases. Whenever possible, solutions should be treated with 0.05% DEPC at 37°C for 2 h or overnight at room temperature and then autoclaved for 20 min to remove any trace of DEPC. Tris buffers that cannot be treated with DEPC should be made from DEPC-treated dd.H<sub>2</sub>O.

### 3.2.1.1 Protocol A. Rapid Isolation of Total RNA by Acid Guanidinium Thiocyanate–Phenol–Chloroform Method

1. **From tissues:** Harvest the tissue of interest and immediately drop it in liquid nitrogen. Store at  $-80^{\circ}\text{C}$  until use. Grind 1 g tissue in a clean blender in liquid nitrogen. Keep adding liquid nitrogen while grinding the tissues until a fine powder is obtained. Warm the powder at room temperature for a few minutes and transfer the powder with a sterile spatula into a clean 14 or 50 ml polypropylene tube. Add 10 ml of solution B, mix, and keep the tube on ice. Proceed to step 2. Alternatively, homogenize the tissue in 10 ml of solution B in a sterile polypropylene tube on ice using a glass-Teflon homogenizer or an equivalent polytron at top speed for three 30-s bursts. Transfer the homogenate to a fresh polypropylene tube and proceed to step 2.

#### **From cultured cells grown in suspension culture or in a monolayer:**

Collect  $1-2 \times 10^8$  cells in a sterile 50-ml polypropylene tube by centrifugation at 400 g for 5 min at 4°C. Wash the cell pellet with 25 ml of ice cold, sterile 1 $\times$  PBS or serum-free medium [e.g., Dulbecco's modified Eagle medium (DMEM)], and centrifuge at 400 g for 5 min at 4°C. Repeat washing and centrifugation once more to remove all traces of serum that contains RNases. Aspirate the supernatant and resuspend the cells in 10 ml solution B. Keep the tube on ice and homogenize the cell suspension using a microtip on a polytron for two 0.5- to 1-min bursts at the top speed. Carefully transfer homogenate to a fresh tube. Proceed to step 2. Alternatively, wash and resuspend the cells as described above. Keep the suspension of cells on ice. In order to shear the DNA and lower the viscosity, sonicate the suspension of cells at the maximum power for a clean microtip (60%) using two 0.5- to 1-min bursts. A good sonicated solution should be thin enough to drop freely from the end of a Pasteur pipette. Proceed to step 2.

Note: *As long as the sample is in the solution B, RNase released from the tissue may be inhibited by guanidinium thiocyanate.*

Caution: *Guanidine thiocyanate is a potent chaotropic agent and irritant.*

2. Add the following components to the sample in the order given below:

1 ml of 2 M sodium acetate buffer (pH 4.0)

10 ml of water-saturated phenol

2 ml of chloroform/isoamyl alcohol

Cap the tube and mix by inversion after each addition. Vigorously shake the tube for 20 s to shear genomic DNA.

Caution: *Phenol is poisonous and can cause severe burns. Proper laboratory clothing including gloves and goggles should be worn when handling these reagents. If phenol contacts your skin, wash the area immediately with large volumes of water, but DO NOT RINSE WITH ETHANOL!*


3. Centrifuge at 12,000  $g$  for 20 min at 4°C using Corex tube or at 7000–8000 rev/min for 30 to 40 min at 4°C using 14 ml polypropylene tube in the swing-out rotor. Carefully transfer the top, aqueous phase to a fresh tube. Decant the phenol phase into a special container for disposal.
4. Add 10 ml of isopropanol, mix, and precipitate RNAs at –20°C for 2 h.
5. Centrifuge at 12,000  $g$  for 15 min at 4°C in a Corex tube or at 7000–8000 rev/min for 30 min at 4°C using a 14-ml polypropylene tube in the swing-out rotor. Resuspend the RNA pellet in 3 ml of solution B and add 3 ml of isopropanol. Mix and then place at –20°C for 2 h or overnight.
6. Centrifuge at 12,000  $\times g$  for 15 min at 4°C or at 7000–8000 rev/min for 30–40 min at 4°C using 14 ml polypropylene tube in the swing-out rotor. Briefly rinse the total RNA pellet with 4 ml of 75% ethanol. Dry the RNA pellet under vacuum for 15 min.
7. Dissolve the total RNAs in 100–150  $\mu$ l of 0.5% SDS solution. Take 5  $\mu$ l to measure the concentration with the spectrophotometer at 260 and 280 nm. Tips: *The ratio of  $A_{260}/A_{280}$  should be 1.8–2.0 to qualify as a good RNA preparation. The RNA isolated may be checked by 1% agarose, formaldehyde denaturing gel electrophoresis. Two strong rRNA bands should be visible with some smear through the well (Figure 3.3a). At this point, the RNA can be used for northern blot analysis, or dot blot hybridization or mRNA purification. The RNA sample may be stored at –20°C until use.*

### 3.2.1.2 Protocol B. Rapid Isolation of Total RNA Using Trizol Reagent™

1. **From tissue:** Harvest tissue and immediately drop it in liquid nitrogen. Store at –80°C until use. Homogenize 0.3 g tissue in 1 ml of Trizol reagent solution (Gibco TRL Life Technologies) using a polytron at the top speed for three 30-s bursts. Allow the cells to be lysed/solubilized for 5 min at room temperature. Proceed to step 2.

**From cultured cells grown in suspension culture or in a monolayer:**

Collect  $1 \times 10^7$  cells in a sterile 50 ml polypropylene tube by centrifugation at 400  $g$  for 5 min at 4°C. Wash the cell pellet with 25 ml of ice cold, sterile  $1 \times$  PBS or serum-free medium (e.g., DMEM), and centrifuge at 400  $g$  for 5 min at 4°C. Repeat washing and centrifugation once more to remove all



**FIGURE 3.3** Electrophoresis of total RNA.

traces of serum that contains RNases. Aspirate the supernatant and lyse the cells in 1 ml of Trizol reagent solution for 3–5 min at room temperature. Proceed to step 2.

*Note: Isolation of RNAs can be scaled up using 0.3 g tissue or  $1 \times 10^7$  cells per 1 ml of Trizol reagent.*

*Caution: Trizol reagent contains toxic phenol.*

2. Add 0.2 ml of chloroform per 1 ml of the Trizol reagent used. Cap the tube and vigorously shake the tube for 20 s to shear genomic DNA. Incubate at room temperature for 3 min for phase separation.
3. Centrifuge at 12,000 g for 20 min at 4°C in an Eppendorf tube or at 7000–8000 rev/min for 30–40 min at 4°C using a 14-ml polypropylene tube in a swing-out rotor. Carefully transfer the top, aqueous phase to a fresh tube. Decant the bottom, phenol phase into a special container for disposal.
4. Add 1 ml of isopropanol, mix, and precipitate RNAs at –20°C for 2 h.
5. Centrifuge at 12,000 g for 15 min at 4°C. Briefly rinse the total RNA pellet with 1 ml of 75% ethanol. Partially dry the RNA pellet at room temperature for 15 min.
6. Dissolve the total RNAs in 20–50  $\mu$ l of 0.5% SDS solution. Take 2  $\mu$ l to measure the concentration with the spectrophotometer at 260 and 280 nm.

### 3.2.1.3 Protocol C. Measurement of RNAs

1. Turn on an ultraviolet (UV) spectrophotometer and set the wavelength at 260 and 280 nm according to the manufacturer's instructions. Spectrophotometer (e.g., UV 160U, Shimadzu) has a computer unit that can automatically and simultaneously measure RNA at  $A_{260}$  and  $A_{280}$  nm, calculate and display RNA concentration together with the ratio of  $A_{260}/A_{280}$  reading numbers on the computer screen. If such spectrophotometer is not available, RNA concentration can be measured by other relatively simple UV-spectrophotometer such as Hitachi model 100-10 UV-visible spectrophotometer. The disadvantages, however, are that RNAs are first measured and recorded at 260 nm, and then switch to 280 nm and record the reading, and that RNA concentration and the ratio of  $A_{260}/A_{280}$  have to be calculated manually.

2. Set up a reference using blank solution, depending on the solution in which RNAs are dissolved. Add an appropriate volume (0.1 or 1 ml) of the solution (TE buffer, pH 8.0 or dd.H<sub>2</sub>O) to a clean cuvette. Insert the cuvette into cuvette holder in sample compartment with the optical (clear) sides of the cuvette facing the light path. Close the sample compartment cover and adjust the number to 0.000 either manually or by pressing Auto Zero button, depending on specific spectrophotometer.  
 Note: *Gloves should be worn when handling RNA measurement. Cuvettes should be rinsed with 95% ethanol followed by dd.H<sub>2</sub>O, and wipe dry the cuvettes using Kimwipe paper before reuse. Unclean cuvettes may contain contaminated materials that may affect readings between samples.*
3. Check for mismatching of cuvettes by filling cuvette(s) with blank solution and recording the absorbency (positive or negative number). Make appropriate additive (for negative number) or subtractive (for positive number) correction to future RNA sample readings. In most cases, however, this step is optional.
4. Make an appropriate dilution of RNA sample to be measured in blank solution in a total volume of 0.1 or 1 ml, depending on the size of cuvette. For example, if you take 2, 5, 10, 15, 20, or 25  $\mu$ l of the RNA sample, the blank solution should be 998, 995, 990, 985, 980, and 975  $\mu$ l, respectively, in a clean cuvette. Tightly cover the cuvette with a piece of Parafilm and mix well by inverting the cuvette two to three times. Alternatively, the sample can be mixed well using a pipette tip.
5. Insert sample cuvette in place and read the absorbency of the sample cuvette against the blank cuvette according to the instructions of spectrophotometer. If only one cell is available, remove the reference cuvette after adjusting the number to 0.000 and insert the sample cuvette in place.
6. After measurement of RNA sample(s) at  $A_{260}$  and  $A_{280}$  nm, respectively, calculate the ratio of  $A_{260}/A_{280}$  reading numbers and concentration for each RNA sample. Some spectrophotometers (e.g., UV 160U, Shimadzu) can automatically calculate, display, and print out the ratio and concentration for each RNA sample. A pure RNA should have a ratio of 1.85–2.0 of  $A_{260}/A_{280}$  readings. The concentration of a RNA sample can be manually calculated as follows:

$$\text{Total RNA } (\mu\text{g}/\mu\text{l}) = \text{OD at } A_{260} \times 40 \mu\text{g/ml} \times \text{dilution factor}$$

For example, if 20  $\mu$ l of RNA is diluted to 1000  $\mu$ l for measuring and its  $A_{260}$  reading number is 0.5000, then

$$\begin{aligned} \text{Total RNA}(\mu\text{g}/\mu\text{l}) &= A_{260} \text{ reading number} \times 40 \mu\text{g/ml} \times \text{dilution factor} \\ &= 0.5000 \times 40 \mu\text{g/ml} \times 1000/20 \\ &= 1000 \mu\text{g/ml} \\ &= 1 \mu\text{g/l} \end{aligned}$$

## Reagents needed

### Solution A

4 M guanidinium thiocyanate

25 mM sodium citrate, pH 7.0

0.5% sarcosyl

Sterile-filtered and store in a light-tight bottle at room temperature up to 3 months

### Solution B

100 ml Solution A

0.72 ml  $\beta$ -mercaptoethanol

Store at room temperature up to 1 month

### Sodium acetate buffer (pH 4.0)

2 M sodium acetate

Adjust pH to 4.0 with 2 N acetic acid; autoclave

### Sodium acetate solution

3 M sodium acetate

Autoclave

### Water saturated phenol

Thaw crystals of phenol at 65°C in a water bath and mix 1 part of phenol and 1 part of sterile dd.H<sub>2</sub>O. Mix well and allow two phases to separate.

Store at 4°C.

Caution: *Phenol is a dangerous reagent; gloves should be worn and the process should be done in a fume hood.*

### Chloroform/isoamyl alcohol (49:1)

98 ml chloroform

2 ml isoamyl alcohol

Mix and store at 4°C

### Ethanol

70%: 70 ml of 100% ethanol and 30 ml dd.H<sub>2</sub>O

75%: 75 ml of 100% ethanol and 25 ml dd.H<sub>2</sub>O

100%: store at -20°C

### 20% SDS

20 g SDS (sodium dodecyl sulfate) in 100 ml dd.H<sub>2</sub>O

## 3.2.2 PURIFICATION OF mRNAs FROM TOTAL RNAs

### 3.2.2.1 Protocol A. Purification of Poly(A)<sup>+</sup>RNAs Using Oligo(dT)-Cellulose Column

1. Add 4 ml of binding buffer in a clean tube containing 0.5 g of oligo(dT)-cellulose type 7 (Collaborative Research) and mix well. Transfer the slurry into a 10-ml poly-prep chromatography column (Bio-Rad) or equivalent. Vertically fix the column in a holder with a clamp and place the column at 4°C for 2 h to equilibrate the cellulose resin before use.



2. Transfer the column to room temperature and wash it with 2 ml of 0.1 N NaOH solution through the top of the resin. Drain away the fluid by gravity and repeat washing the column 5 times with 2 ml of 0.1 N NaOH solution per washing.  
Note: *The color of the resin changes from white to yellow.*
3. Neutralize the column by adding 4 ml of binding buffer to top of the resin followed by draining away the binding buffer. Repeat this step five times and store at 4°C until use.  
Note: *The color of the resin returns to white.*
4. Add 1 volume of loading buffer to the total RNA sample and heat the mixture for 10 min to 65°C to denature the secondary structure of RNA. Cool the sample to room temperature.  
Note: *The concentration of SDS in the loading buffer should never be >0.5%; otherwise, the SDS will precipitate and block the column. In our experience, 0.2% SDS in the binding buffer works well.*
5. Carefully load the total RNA sample to the top of the column capped at the bottom and allow the sample to run through the column by gravity. Gently loosen the resin in the column using a clean needle and let the column stand for 5 min. Drain away the fluid from the bottom of the column and collect the fluid containing some unbound mRNA. Reload the fluid onto the column to allow the unbound mRNA to bind to the oligo(dT)-cellulose column. Collect the elute and repeat this procedure twice.
6. Wash the column with 2 ml of washing buffer and drain away the buffer. Repeat washing three to four times.
7. Cap the bottom of the column and add 1 ml of elution buffer to the column to elute the bound poly(A)+RNA. Gently loosen the resin using a clean needle and allow elution to proceed for 4 min at room temperature. Remove the bottom cap and collect the eluate in a sterile tube. Elute the column twice with 1 ml of elution buffer and pool the eluate.
8. To the pooled eluates, add 0.15 volume of 3 M sodium acetate and 2.5 volumes of 100% chilled ethanol to precipitate the mRNA. Mix and place at -80°C for 1 h or at -20°C for 2 h or overnight.
9. Centrifuge at 12,000 g for 15 min at 4°C. Aspirate the supernatant and briefly wash the mRNA pellet with 2 ml of 70% ethanol. Dry the pellet under vacuum for 15 min and dissolve the mRNA in 20–40 µl of TE buffer. Store the sample at -80°C until use.
10. Take 2–4 µl of the sample to measure the concentration of the mRNA as described above.  
Notes: (1) *At this point, the sample should have a  $A_{260}/A_{280}$  ratio of 1.9–2.0. If the ratio is <1.75, the sample is not recommended for synthesis of cDNAs.* (2) *The quality of the purified mRNA may be checked by 1% agarose, formaldehyde denaturing gel electrophoresis. A broad range of smear should be visible from the top to the bottom of the well with or without two weak rRNA bands (Figure 3.3b).* (3) *The yield of poly(A) + RNA may be expected to be approximately 6% of total RNA. The calculation is as follows:*

$$\text{Poly(A)+RNA } (\mu\text{g}/\mu\text{l}) = A_{260} \text{ reading number} \times 42 \mu\text{g/ml} \times \text{dilution factor}$$

For example, if 20  $\mu\text{l}$  of mRNA is diluted to 1000  $\mu\text{l}$  for measuring and its  $A_{260}$  reading number is 0.4000, then

$$\begin{aligned} \text{Poly(A) + RNA}(\mu\text{g}/\mu\text{l}) &= A_{260} \text{ reading number} \times 42 \mu\text{g/ml} \times \text{dilution factor} \\ &= 0.4000 \times 42 \mu\text{g/ml} \times 1000/20 \\ &= 840 \mu\text{g/ml} \\ &= 0.84 \mu\text{g/l} \end{aligned}$$

### 3.2.2.2 Protocol B. Minipurification of mRNAs Using Oligo(dT) Cellulose Resin

1. Add 1 ml of binding buffer to 0.3 g of oligo(dT)-cellulose type 7 (Collaborative Research) in an Eppendorf tube and mix well. Place the tube at 4°C for 30 min.
2. Wash the resin with 1 ml of 0.1 N NaOH solution and centrifuge at 1500 g for 2 min. Carefully aspirate the supernatant and repeat this step eight times.  
Note: *Centrifugation greater than 1500 g may cause damage to the oligo(dT) beads.*
3. Neutralize the resin with 1 ml of binding buffer and centrifuge at 1500 g for 2 min. Carefully decant the supernatant and repeat this step eight times. Resuspend the resin in 1 ml of binding buffer.
4. Add 1 volume of loading buffer to the total RNA sample (maximum 100  $\mu\text{l}$ , about 2  $\mu\text{g}/\mu\text{l}$ ). Heat the mixture for 10 min at 65°C and cool it to room temperature.
5. Add the total RNA sample to the 1 ml slurry of oligo(dT)-cellulose prepared at step 3. Gently mix and place at room temperature for 15 min to allow the RNA to bind to the resin.
6. Centrifuge at 1500 g for 5 min and carefully aspirate the supernatant.
7. Add 0.5 ml of wash buffer to the resin and centrifuge at 1500 g for 2 min. Carefully aspirate the supernatant. Repeat this step three times.
8. Add 0.2 ml of elution buffer to the resin and gently shake for 5 min. Centrifuge at 1500 g for 5 min and transfer the supernatant containing mRNAs to a fresh tube. Repeat this step twice.
9. Pool the supernatant and add 0.1 volume 3 M sodium acetate and 2.5 volumes of 100% chilled ethanol to precipitate the mRNA as described above.

#### Reagents needed

- Ethanol  
70%: 70 ml of 100% ethanol and 30 ml dd.H<sub>2</sub>O.  
75%: 75 ml of 100% ethanol and 25 ml dd.H<sub>2</sub>O.  
100%: store at -20°C.

- 0.1 N NaOH  
4 g NaCl in 100 ml dd.H<sub>2</sub>O
- RNA buffer  
10 mM Tris-HCl, pH 7.5  
1 mM EDTA, pH 8.0  
0.2% SDS  
Sterile-filtered
- Binding buffer  
10 mM Tris-HCl, pH 7.5  
0.5 M NaCl  
1 mM EDTA  
0.5% SDS  
Sterile-filtered
- Loading buffer  
20 mM Tris-HCl, pH 7.5  
1 M NaCl  
2 mM EDTA  
0.2% SDS  
Sterile-filtered
- Wash buffer  
10 mM Tris-HCl, pH 7.5  
100 mM NaCl  
1 mM EDTA  
Sterile-filtered
- Elution buffer  
10 mM Tris-HCl, pH 7.5  
1 mM EDTA
- TE buffer  
10 mM Tris-HCl, pH 8.0  
1 mM EDTA

### 3.2.3 SYNTHESIS OF FIRST STRAND cDNAs FROM CELL/TISSUE TYPE A OR B

#### 3.2.3.1 Protocol A. Synthesis of First Strand cDNAs from mRNAs

It is recommended that one set up two reactions in two microcentrifuge tubes that will be carried out separately all the way to the end. The purpose is that if one reaction is somehow stopped by an accident during the experiments, the other reaction can be used as a backup—because, otherwise, one must start all over again, thus wasting time and money. A standard reaction is a total of 25  $\mu$ l using 0.2–2  $\mu$ g mRNA or 5–10  $\mu$ g total RNA. For each additional 1  $\mu$ g mRNA, increase the reaction volume by 10  $\mu$ l. A control reaction is recommended to be carried out whenever possible under the same conditions.

1. Anneal 2  $\mu$ g of mRNAs as templates with 1  $\mu$ g of primer of oligo(dT), or with 0.7  $\mu$ g of primer-adaptor of oligo(dT)-*NotI/XbaI* in 1.5 ml of sterile, RNase-free microcentrifuge tube. Add nuclease-free dd.H<sub>2</sub>O to 15  $\mu$ l. Heat

the tube at 70°C for 5 min to denature the secondary structures of mRNAs and allow it to slowly cool to room temperature to complete the annealing. Briefly spin down the mixture.

- To the annealed primer/template, add the following in the order listed. To prevent precipitation of sodium pyrophosphate when adding it to the reaction, the buffer should be preheated at 40–42°C for 4 min before the addition of sodium pyrophosphate and AMV reverse transcriptase. Gently mix well after each addition.

First strand 5× buffer	5 µl
rRNasin ribonuclease inhibitor	50 units (25 units/µg mRNA)
40 mM sodium pyrophosphate	2.5 µl
<u>AMV reverse transcriptase</u>	<u>30 units (15 units/µg mRNA)</u>
Add nuclease-free dd.H <sub>2</sub> O to a final	25 µl

Function of components: *The 5× reaction buffer contains components for the synthesis of cDNAs. Ribonuclease inhibitor serves to inhibit RNase activity and to protect the mRNA templates. Sodium pyrophosphate suppresses the formation of hairpins that are commonly generated in traditional cloning methods, thus avoiding the S1 digestion step that is difficult to carry out. AMV reverse transcriptase catalyzes the synthesis of the first strand cDNAs from mRNA templates according to the rule of complementary base pairing.*

- Transfer 5 µl of the mixture to a fresh tube, as a tracer reaction, which contains 1 µl of 4 µCi of [ $\alpha$ -<sup>32</sup>P]dCTP (>400 Ci/mmol, less than 1 week old). The synthesis of the first strand cDNAs will be measured by trichloroacetic acid (TCA) precipitation and alkaline agarose gel electrophoresis using the tracer reaction.

Caution: [ $\alpha$ -<sup>32</sup>P]dCTP is a toxic isotope. Gloves should be worn when carrying out the tracer reaction, TCA assay, and gel electrophoresis. Waste materials such as contaminated gloves, pipette tips, solutions, and filter papers should be put in special containers for disposal of waste radioactive materials.

- Incubate both reactions at 42°C for 1–1.5 h and then place the tubes on ice. At this point, the synthesis of the first strand cDNAs has been completed. To the tracer reaction mixture, add 50 mM EDTA solution up to a total volume of 100 µl and store on ice until use for TCA incorporation assays and analysis by alkaline agarose gel electrophoresis.
- To completely remove RNAs, add RNase A (DNase-free) to a final concentration of 20 µg/ml or 1 µl of RNase (Boehringer Mannheim, 500 µg/ml) per 10 µl of reaction mixture. Incubate at 37°C for 30 min.
- Extract the cDNAs from the unlabeled reaction mixture with 1 volume of TE-saturated phenol/chloroform. Mix well and centrifuge at 11,000 g for 5 min at room temperature.
- Carefully transfer the top, aqueous phase to a fresh tube. Do not take any white materials at the interphase between the two phases. To the supernatant,

add 0.5 volume of 7.5 M ammonium acetate or 0.15 volume of 3 M sodium acetate (pH 5.2), mix well, and add 2.5 volumes of chilled (at  $-20^{\circ}\text{C}$ ) 100% ethanol. Gently mix and precipitate cDNAs at  $-20^{\circ}\text{C}$  for 2 h.

8. Centrifuge in a microcentrifuge at 12,000 g for 5 min. Carefully remove the supernatant, briefly rinse the pellet with 1 ml of cold 70% ethanol. Centrifuge for 4 min and carefully aspirate the ethanol.
9. Dry the cDNAs under vacuum for 15 min. Dissolve the cDNA pellet in 15–25  $\mu\text{l}$  of TE buffer. Take 2  $\mu\text{l}$  of the sample to measure the concentration of cDNAs before the next reaction. Store the sample at  $-20^{\circ}\text{C}$  until use.

### 3.2.3.2 Protocol B. TCA Assay and Calculation of cDNA Yield

1. Place 4  $\mu\text{l}$  of the first strand cDNA tracer reaction mixture on glass fiber filters and air dry. These will be used to obtain the total counts per minute (cpm) in the sample.
2. Add another 4  $\mu\text{l}$  of the same reaction mixture to a tube containing 100  $\mu\text{l}$  of carrier DNA solution (1 mg/ml) and mix well. Add 0.5 ml of 5% TCA and mix by vortexing and precipitate the DNA on ice for 30 min.
3. Filter the precipitated cDNA through glass fiber filters and wash the filters four times with 6 ml cold 5% TCA. Rinse the filters once with 6 ml of acetone or ethanol and air dry. This sample represents incorporated cpm in the reactions.
4. Place the filters at steps 1 and 3 in individual vials and add 10–15 ml of scintillation fluid to cover each filter. Count both total and incorporated cpm samples according to the instructions of an appropriate scintillation counter. The cpm can also be counted by Cerenkov radiation (without scintillant).
5. Calculate the yield of first strand cDNA as follows:

$$\text{Percentage incorporated} = \frac{\text{incorporated cpm}}{\text{total cpm}} \times 100$$

$$\text{dNTP incorporated (nmol)} = 4 \text{ nmol dNTP/ml} \times \text{reaction vol. (ml)} \times \frac{\% \text{ incorporation}}{100}$$

$$\text{cDNA synthesized (nmol)} = \text{nmol dNTP incorporated} \times 330 \text{ ng/mol}$$

$$\% \text{ mRNA converted to cDNA} = \frac{\text{ng cDNA synthesized}}{\text{ng mRNA in reaction}}$$


### 3.2.3.3 Protocol C. Analysis of cDNAs by Alkaline Agarose Gel Electrophoresis

The quality and the size range of the synthesized cDNAs in the first strand cDNA reactions should be checked by 1.4% alkaline agarose gel electrophoresis using the tracer reaction samples.

1. Label  $\lambda$ HindIII fragments with  $^{32}\text{P}$  in a fill-in reaction that will be used as DNA markers to estimate the sizes of cDNAs. Add the following components into a sterile Eppendorf tube in the order shown below.

<i>Hind</i> III 10 $\times$ buffer	2 $\mu\text{l}$
dGTP	0.2 mM
dATP	0.2 mM
$[\alpha\text{-}^{32}\text{P}]\text{dCTP}$	2 $\mu\text{Ci}$
$\lambda$ HindIII markers	1 $\mu\text{g}$
<u>Klenow DNA polymerase</u>	<u>1 unit</u>
Add dd.H <sub>2</sub> O to a final volume of	20 $\mu\text{l}$

2. Mix well after each addition and incubate the reaction for 15 min at room temperature. Add 2  $\mu\text{l}$  of 0.2 M EDTA to stop the reaction. Transfer 6  $\mu\text{l}$  of the sample directly to 6  $\mu\text{l}$  of 2 $\times$  alkaline buffer and store the remainder at  $-20^\circ\text{C}$ .
3. Dissolve 1.4% (w/v) agarose in 50 mM NaCl, 1 mM EDTA solution and melt it in a microwave for a few min. Allow the gel mixture to cool to  $50^\circ\text{C}$  and pour the gel into a minielectrophoresis apparatus. Allow the gel to harden and equilibrate the gel in alkaline gel running buffer for 1 h before electrophoresis.
4. Transfer the same amount of each sample (50,000 cpm) to separate tubes and add an equal volume of TE buffer to each tube. Add 1 volume of 2 $\times$  alkaline buffer to each tube.
5. Carefully load the samples into appropriate wells and immediately run the gel at 7 V/cm until the dye has migrated to about 2 cm from the end.
6. When electrophoresis is complete, soak the gel in 5 volumes of 7% TCA at room temperature until the dye changes from blue to yellow. Dry the gel on a piece of Whatman 3MM paper in a gel dryer or under a weighted stack of paper towels for 6 h. The use of 7% TCA used here is to neutralize the denatured gel.
7. Wrap the gel with a piece of Saran Wrap and expose to x-ray film at room temperature or at  $-70^\circ\text{C}$  with an intensifying screen for 1 to 4 h.



**FIGURE 3.4** Analysis of first strand cDNAs using agarose electrophoresis.

Note: A successful synthesis of cDNAs should have a signal range from 0.15 to 10 kb with a sharp size range of 1.5–4 kb (Figure 3.4).

### Materials needed

- [ $\alpha$ - $^{32}$ P]dCTP (>400 Ci/mmol)
- 50 mM EDTA
- 7.5 M ammonium acetate
- Ethanol (100% and 70%)
- Chloroform/isoamyl alcohol (24:1)
- 2 M NaCl
- 0.2 M EDTA
- 1 mg/ml carrier DNA (e.g., salmon sperm)
- TCA (5% and 7%)
- First strand 5 $\times$  buffer
  - 250 mM Tris-HCl, pH 8.3 (at 42°C)
  - 250 mM KCl
  - 2.5 mM spermidine
  - 50 mM MgCl<sub>2</sub>
  - 50 mM DTT
  - 5 mM each of dATP, dCTP, dGTP, and dTTP
- TE buffer
  - 10 mM Tris-HCl, pH 8.0
  - 1 mM EDTA
- TE-saturated phenol/chloroform
  - Thaw phenol crystals at 65°C and mix an equal part of phenol and TE buffer. Mix well and allow the phases to separate at room temperature for 30 min. Take 1 part of the lower, phenol phase to a clean beaker or bottle and mix with 1 part of chloroform/isoamyl alcohol (24:1). Mix well and allow phases to be separated, and store at 4°C until use.
- Alkaline gel running buffer (fresh)
  - 30 mM NaOH
  - 1 mM EDTA
- 2 $\times$  alkaline buffer
  - 20 mM NaOH
  - 20% glycerol
  - 0.025% bromophenol blue (use fresh each time).

### 3.2.4 HYBRIDIZATION OF cDNAs FROM CELL/TISSUE TYPE A OR B WITH mRNAs FROM CELL/TISSUE TYPE B OR A, OR VICE VERSA

1. Perform a hybridization reaction in a microcentrifuge tube as follows:

4–6 $\mu$ g the first strand cDNAs from tissue or cell type A	
15 $\mu$ l of 2 $\times$ hybridization buffer	
5–15 $\mu$ g poly(A) <sup>+</sup> RNA or mRNAs from tissue or cell type B	
Add dd.H <sub>2</sub> O to a final volume of	30 $\mu$ l

or

4–6 $\mu$ g the first strand cDNAs from tissue or cell type B	
15 $\mu$ l of 2 $\times$ hybridization buffer	
<u>5–15 <math>\mu</math>g mRNAs from tissue or cell type A</u>	
Add dd.H <sub>2</sub> O to a final volume of	30 $\mu$ l

2. Cap the tubes to prevent evaporation and incubate at 65–68°C overnight to 16 h.

### 3.2.5 SEPARATION OF cDNA/mRNA HYBRIDS FROM SINGLE-STRANDED cDNAs BY HAP CHROMATOGRAPHY

1. Preparation of an HAP column. Add 1g of HAP (DNA Grade Bio-Gel, BioRad, Cat. # 130-0520) in 0.1 M phosphate buffer (PB), pH 6.8, for 5 ml of slurry and mix well. Heat the mixture in boiling water for 5 min. Place a 5-ml plastic syringe closed at the bottom in a water bath to equilibrate at 60°C. Place some sterile glasswool at the bottom of the syringe and slowly add 0.5–1 ml HAP slurry to the bottom-closed column and allow it to set down for 5 min before opening the column. Wash the column twice with 5 volumes of 0.1 M PB (60°C).
2. Dilute the hybridized sample 10-fold in prewarmed (60°C) 0.1 M PB containing 0.15 M NaCl. Gently load the sample onto the prepared HAP column with the bottom closed. Gently loosen the mixture in the column with a needle (avoid bubbles) and allow it to set for 10 min.
3. Open the column from the bottom and collect the effluent containing the single strand cDNAs. Wash the column twice with 0.5 ml of 0.1 M PB containing 0.15 M NaCl and collect the effluent. The cDNA/mRNA hybrids in the column are then eluted with 0.5 M PB.
4. Pool the effluent together and load onto a fresh HAP column as in steps 3–4 to maximally obtain any cDNA/mRNA hybrids that potentially remain in the effluent.
5. Pool the effluent together and dialyze against 500 ml dd.H<sub>2</sub>O overnight to remove the PB salts.
6. Add 0.15 volume of 3 M sodium acetate buffer (pH 5.2) and 2.5 volumes of chilled 100% ethanol to the dialyzed sample and place at –80°C for 30 min.
7. Centrifuge at 12,000 *g* for 5 min and briefly rinse the cDNA pellet with 1 ml of 70% cold ethanol. Dry the pellet under vacuum for 15 min and dissolve the cDNAs in 20–25  $\mu$ l TE buffer. Take 2  $\mu$ l of the sample to measure the concentration of cDNA. Store the sample at –20°C until use.

### 3.2.6 SYNTHESIS OF DOUBLE-STRANDED cDNAs FROM SUBTRACTED cDNAs

1. Set up the following reaction:

Subtracted first strand cDNAs	1 $\mu$ g
Second strand 10 $\times$ buffer	50 $\mu$ l
Poly(A) <sub>12–20</sub> primers	0.2 $\mu$ g



<i>Escherichia coli</i> DNA polymerase I	20 units
Nuclease-free dd.H <sub>2</sub> O to a final volume	50 $\mu$ l

2. Set up a tracer reaction for the second strand DNA by transferring 5  $\mu$ l of the mixture to a fresh tube containing 1  $\mu$ l 4  $\mu$ Ci [ $\alpha$ -<sup>32</sup>P]JdCTP (>400 Ci/mmol). The tracer reaction will be used for TCA assay and alkaline agarose gel electrophoresis to monitor the quantity and quality of the synthesis of the second strand DNA, as described above.
3. Incubate both reactions at 14°C for 3.5 h and then add 95  $\mu$ l of 50 mM EDTA to the 5  $\mu$ l tracer reaction.
4. Heat the unlabeled (nontracer portion) double strand DNAs sample at 70°C for 10 min to stop the reaction. At this point, the double strand DNAs should be produced. Briefly spin down to collect the contents at the bottom of the tube and place on ice until use.
5. Add 4 units of T4 DNA polymerase (2 u/ $\mu$ g input cDNA) to the mixture and incubate at 37°C for 10 min. This step functions to make the blunt-end, double-stranded cDNAs by T4 polymerase. The blunt ends are required for later adapter ligations.
6. Stop the T4 polymerase reaction by adding 3  $\mu$ l of 0.2 M EDTA and place on ice.
7. Extract the cDNAs with 1 volume of TE-saturated phenol/chloroform. Mix well and centrifuge at 11,000 g for 4 min at room temperature.
8. Carefully transfer the top aqueous phase to a fresh tube and add 0.5 volume of 7.5 M ammonium acetate or 0.15 volume of 3 M sodium acetate (pH 5.2). Mix well and add 2.5 volumes of chilled (-20°C) 100% ethanol. Gently mix and precipitate the cDNAs at -20°C for 2 h.
9. Centrifuge at 12,000 g for 5 min and carefully remove the supernatant. Briefly rinse the pellet with 1 ml of cold 70% ethanol, centrifuge at 12,000 g for 5 min and aspirate the ethanol.
10. Dry the cDNA pellet under vacuum for 15 min. Dissolve the cDNA pellet in 20  $\mu$ l of TE buffer. Measure the concentration of the cDNAs as described above. Store the sample at -20°C until use.

*Note: Before adapter ligation, it is strongly recommended that the quantity and quality of the double-stranded cDNAs be checked by TCA precipitation and gel electrophoresis as described previously.*

### Materials needed

- [ $\alpha$ -<sup>32</sup>P]dCTP (>400 Ci/mmol)
- 50 mM EDTA
- 3 M sodium acetate buffer, pH 5.2
- Ethanol (100% and 70%)
- Chloroform/isoamyl alcohol (24:1)
- 0.2 M EDTA
- TCA (5% and 7%)
- Hybridization buffer (2 $\times$ )
  - 40 mM Tris-HCl, pH 7.7
  - 1.2 M NaCl

- 4 mM EDTA
- 0.4% SDS
- 1  $\mu\text{g}/\mu\text{l}$  carrier yeast tRNA (optional)
- Phosphate buffer (stock)
  - 0.5 M monobasic sodium phosphate
  - Adjust the pH to 6.8 with 0.5 M dibasic sodium phosphate

### 3.2.7 LIGATION OF cDNAs TO LAMBDA GT10 OR APPROPRIATE VECTORS

#### 3.2.7.1 Ligation of *EcoRI* Linkers/Adapters to Double-Stranded, Blunt-End cDNAs

The *EcoRI* linker or *EcoRI* adapter ligation system is designed to generate *EcoRI* sites at the termini of blunt-ended cDNA, which are commercially available. If *EcoRI* linkers are used, digestion with *EcoRI* is required after ligation. However, there is no need to digest with *EcoRI* if one uses the *EcoRI* adapters if each adapter has one sticky end. The ligation of *EcoRI* linker or adapter allows cDNAs to be cloned at the unique *EcoRI* sites of vectors  $\lambda\text{gt}10$  or  $\lambda\text{gt}11$ . If cDNAs are synthesized with an *XbaI* or *NotI* primer-adaptor, they can be directionally cloned between the *EcoRI* and *XbaI* or *NotI* sites of  $\lambda\text{gt}11$  *Sfi-NotI* vector or other vectors such as  $\lambda\text{GEM-2}$  and  $\lambda\text{GEM-4}$ .

##### 3.2.7.1.1 Carry Out Size Fractionation of Double-Stranded cDNAs with an Appropriate Column (e.g., Sephacryl S-400 Spin Columns (Promega Corporation))

Note: It is strongly recommended that cDNA samples be size-fractionated before ligation with linkers to eliminate <200 bp cDNAs.

- (a) Add approximately 1.2 ml of Sephacryl S-400 slurry to a vertical column and drain the buffer completely. Repeat addition of the slurry until the final height of the gel bed reaches the neck of the column at the lower “ring” marking. Rehydrate the column with buffer, cap the top, and seal the bottom. Store the column at 4°C until use.
- (b) Before use, drain away the buffer and place the column in a collecting tube provided or a microcentrifuge tube. Briefly centrifuge in a swinging bucket for 4 min at 800 g to remove excess buffer.
- (c) Place the column in a fresh collecting tube and slowly load the cDNA samples (30–60  $\mu\text{l}$ ), dropwise, to the center of the gel bed. Centrifuge in a swinging bucket at 800 g for 5 min and collect the eluate. The eluted cDNAs can be directly used or precipitated with ethanol and dissolved in TE buffer.

##### 3.2.7.1.2 Protection of Internal *EcoRI* Sites of cDNAs by Methylation

- (a) Set up the *EcoRI* methylation reaction as follows:

1 mM S-adenosyl-L-methionine	2 $\mu\text{l}$
<i>EcoRI</i> methylase 10 $\times$ buffer	2 $\mu\text{l}$
DNA (1 $\mu\text{g}/\mu\text{l}$ )	2 $\mu\text{l}$

<u>EcoRI methylase</u>	<u>20 units</u>
Add dd.H <sub>2</sub> O to a final volume of	20 $\mu$ l

- (b) Incubate the reaction at 37°C for 20 min and inactivate the enzyme at 70°C for 10 min.
- (c) Extract the enzyme with 20  $\mu$ l of TE-saturated phenol/chloroform, mix well by vortexing, and centrifuge at 11,000 *g* for 4 min.
- (d) Carefully transfer the top, aqueous phase to a fresh tube and add an equal volume of chloroform/isoamyl alcohol (24:1). Vortex to mix and centrifuge as above.
- (e) Carefully transfer the top, aqueous phase to a fresh tube. Do not take any white materials. To the supernatant, add 0.15 volume of 3 M sodium acetate buffer, pH 5.2, and 2.5 volumes of chilled 100% ethanol. Precipitate the DNA at -70°C for 30 min or at -20°C for 2 h.
- (f) Perform centrifugation and dissolving the DNA as described previously.

### 3.2.7.1.3 Ligation of EcoRI Linkers to Methylated cDNAs

- (a) Set up the reaction as follows:

cDNA	0.2 $\mu$ g (0.1 $\mu$ g/ $\mu$ l)
Ligase 10 $\times$ buffer	2 $\mu$ l
Phosphorylated <i>EcoRI</i> linkers (diluted stock linkers, 0.001 A <sub>260</sub> unit of the linker = 10 pmol)	60-fold molar excess
<u>T4 DNA ligase (Weiss units)</u>	<u>5 units</u>
Add dd.H <sub>2</sub> O to a final volume of	20 $\mu$ l

- (b) Incubate the reaction at 15°C overnight and stop the reaction at 70°C for 10 min.
- (c) Cool the tube on ice for 2 min and carry out *EcoRI* digestion as follows:

Ligated cDNAs	20 $\mu$ l
<i>EcoRI</i> 10 $\times$ buffer	5 $\mu$ l
<u><i>EcoRI</i></u>	<u>1 unit/pmol of linker used in step (a)</u>
Add dd.H <sub>2</sub> O to a final volume of	50 $\mu$ l

- (d) Incubate the reaction at 37°C for 2 h and add 4  $\mu$ l of 0.2 M EDTA to stop the reaction.
- (e) Extract enzymes and precipitate DNA as described above.
- (f) Set up the *XbaI* or *NotI* digestion reaction as follows:

cDNAs from step	40 $\mu$ l
<i>XbaI</i> or <i>NotI</i> 10 $\times$ buffer	8 $\mu$ l
<u><i>XbaI</i> or <i>NotI</i></u>	<u>1 unit/pmol of linker used in step (a)</u>
Add dd.H <sub>2</sub> O to a final volume of	80 $\mu$ l

Incubate the reaction at 37°C for 2 h and add 8 ml of 0.2 M EDTA to stop the reaction. Extraction of DNA as described above.

Note: The following steps are designed for directional cloning of cDNAs that are synthesized with an *XbaI* or *NotI* primer-adapter. The ligated cDNAs with linkers must be digested with *XbaI* or *NotI* after the *EcoRI* digestion. Alternatively, a double enzyme digestion with *EcoRI* and *XbaI* or *NotI* can be executed in the same reaction using 10× digestion buffer for *XbaI* or *NotI* in the reaction. However, double digestions are usually of lower efficiency.

- (g) To check the efficiency of ligation, load 4  $\mu\text{l}$  (about 0.3  $\mu\text{g}$ ) of the ligated sample on a 0.8% agarose gel containing EtBr and an equal amount of the unligated, blunt-ended cDNAs next to the ligated sample as a control. After electrophoresis, take a photograph under UV light. An efficient ligation will cause a shift in the migration rate because of the ligation of linker concatamers that run more slowly than the unligated sample.

### Reagents needed

- 7.5 M ammonium acetate
- Ethanol (100% and 70%)
- Chloroform/isoamyl alcohol (24:1)
- 2 M NaCl
- 0.2 M EDTA
- *EcoRI* methylase 10× buffer:
  - 1 M Tris-HCl, pH 8.0
  - 0.1 M EDTA
- TE buffer
  - 10 mM Tris-HCl, pH 8.0
  - 1 mM EDTA
- Sample buffer
  - 50% glycerol
  - 0.2% SDS
  - 0.1% bromophenol blue
  - 10 mM EDTA
- Ligase 10× buffer
  - 0.3 M Tris-HCl, pH 7.5
  - 0.1 M DTT
  - 0.1 M  $\text{MgCl}_2$
  - 10 mM ATP
- *EcoRI* 10× buffer
  - 0.9 M Tris-HCl, pH 7.5
  - 0.5 M NaCl
  - 0.1 M  $\text{MgCl}_2$
- *NotI* or *XbaI* 10× buffer
  - 0.1 M Tris-HCl, pH 7.5
  - 1.5 M NaCl
  - 60 mM  $\text{MgCl}_2$
  - 10 mM DTT

### 3.2.7.1.4 Ligation of *EcoRI* Adaptors to cDNAs

An *EcoRI* adaptor is a duplex DNA molecule with one *EcoRI* sticky end and one blunt end for ligation to cDNA. Use of adaptors can eliminate the *EcoRI* methylation as described above. The adaptor-cDNA does not need to be digested with *EcoRI* after ligation, which is necessary for *EcoRI* linker ligation methodology. However, a phosphorylation reaction should be performed if the cloning vector is dephosphorylated.

- (a) Set up ligation of *EcoRI* adaptors to cDNAs in a microcentrifuge tube.

cDNA	0.2 µg
ligase 10× buffer	3 µl
<i>EcoRI</i> adaptors	25-fold molar excess
<u>T4 DNA ligase (Weiss units)</u>	<u>8 units</u>
Add dd.H <sub>2</sub> O to a final volume of	30 µl

- (b) Incubate the reaction at 15°C overnight and stop the reaction at 70°C for 10 min.  
 (c) Carry out a kinase reaction and *XbaI* or *NotI* digestion.

*Note: This reaction is necessary for the dephosphorylated vectors but is not required for the phosphorylated vectors. For directional cDNA cloning, XbaI or NotI digestion should be carried out. This can be done simultaneously with the kinase reaction using restriction enzyme 10× buffer instead of the kinase 10× buffer.*

Place the tube at step (b) on ice for 1 min and add the following in the order shown:

For kinase reaction only:

Kinase 10× buffer	5 µl
0.1 mM ATP (diluted from stock)	2.5 µl
<u>T4 polynucleotide kinase</u>	<u>10 units</u>
Add dd.H <sub>2</sub> O to a final volume of	50 µl

For both kinase reaction and *XbaI* or *NotI* digestion:

<i>XbaI</i> or <i>NotI</i> 10× buffer	5 µl
0.1 mM ATP (diluted from stock)	2.5 µl
T4 polynucleotide kinase	10 units
<u>Either <i>XbaI</i> or <i>NotI</i></u>	<u>8 units</u>
Add dd.H <sub>2</sub> O to a final volume of	50 µl

- (d) Incubate the reaction at 37°C for 60 min and extraction of DNA as described above.  
 (e) Remove unligated adaptors as follows:  
 Place a spin column in the collection tube and slowly load the supernatant onto the top center of the gel bed. Centrifuge in a swinging bucket at 800 g for 5 min and collect the eluate containing the cDNA adapter.

- (f) Add 0.5 volume of 7.5 M ammonium acetate to the eluate, mix, and add 2 volumes of chilled 100% ethanol. Precipitate DNA-linker/adaptor at  $-20^{\circ}\text{C}$  for 2 h.
- (g) Centrifuge at 12,000 g for 10 min and briefly rinse the pellet with 1 ml of cold 70% ethanol. Dry the cDNA-linker/adaptor under vacuum for 10 min and resuspend the pellet in 20  $\mu\text{l}$  of TE buffer. Store the sample at  $-20^{\circ}\text{C}$  until use.

### Reagents needed

- Ligase 10 $\times$  buffer  
300 mM Tris-HCl, pH 7.8  
0.1 M  $\text{MgCl}_2$   
0.1 M DTT  
10 mM ATP
- Kinase 10 $\times$  buffer  
0.7 M Tris-HCl, pH 7.5  
100 mM  $\text{MgCl}_2$   
50 mM DTT
- *Xba*I or *Not*I 10 $\times$  buffer  
300 mM Tris-HCl, pH 7.8  
100 mM  $\text{MgCl}_2$   
500 mM NaCl  
100 mM DTT
- 7.5 M ammonium acetate
- Ethanol (100% and 70%)

### 3.2.7.2 Restriction Enzyme Digestion of Vectors

If it is necessary, the vectors should be digested with appropriate restriction enzymes before being ligated with cDNA linkers or adaptors, as described above.

### 3.2.7.3 Ligation of cDNAs to Vectors

#### 3.2.7.3.1 Determination of the Optimal Ligation of Vectors with cDNA Inserts

Before a large-scale ligation, several ligations of vector arms and cDNA inserts should be carried out to determine the optimal molar ratio and ligation conditions. The molar concentration of the vectors should be constant while adjusting the amount of DNA inserts. The molar ratio range of 43 kb lambda arms to an average 1.4 kb cDNA inserts is usually from 1:1 to 1:0.5. Two control ligations should be carried out. One is the ligation of vectors and positive DNA inserts to check the efficiency, the other is ligation of the vector arms only to determine the background level of religated arms.

- (a) Set up the ligation reactions as follows and carry them out separately:  
*Sample ligations*

Components	Microcentrifuge Tubes			
	A	B	C	D
Ligase 10× buffer	0.5	0.5	0.5	0.5 (μl)
λDNA vectors (0.5 μg/μl; 1 μg = 0.04 pmol)	1	1	1	1 (μg)
Linker/adaptor-cDNA inserts (0.1 μg/μl; 10 ng = 0.01 pmol)	10	20	30	40 (ng)
T4 DNA ligase (Weiss unit)	2	2	2	2 (units)
Add dd.H <sub>2</sub> O to a final volume of	5	5	5	5 (μl)

*Control ligation 1*

Ligase 10× buffer	0.5 μl
λDNA vector (0.5 μg/μl)	1.0 μg
Positive control insert DNA	0.1 μg
<u>T4 DNA ligase (Weiss unit)</u>	<u>2.0 units</u>
Add dd.H <sub>2</sub> O to a final volume of	5 μl

*Control ligation 2*

Ligase 10× buffer	0.5 μl
λDNA vector (0.5 μg/μl)	1.0 μg
<u>T4 DNA ligase (Weiss unit)</u>	<u>2.0 units</u>
Add dd.H <sub>2</sub> O to a final volume of	5 μl

- (b) Incubate the reactions at room temperature (22–24°C) for 1–4 h.  
 (c) Check the efficiency of ligation by 0.8% agarose electrophoresis and determine the optimal conditions for a large-scale ligation.  
 (d) Carry out a large-scale ligation of vector arms and cDNA inserts using the optimal conditions determined above. Proceed to *in vitro* packaging.


### 3.2.8 GENERATION OF A SUBTRACTED cDNA LIBRARY

#### 3.2.8.1 *In Vitro* Packaging

Performance of packaging *in vitro* is to use a phage-infected *E. coli* cell extract to supply the mixture of proteins and precursors required for encapsulating the recombinant λDNA (vector-cDNA inserts). Packaging systems are commercially available with the specific bacterial strain host and control DNA.

1. Thaw a packaging extracts (50 μl/extract) on ice.

Note: Do not thaw the extract at room temperature or 37°C, and do not freeze the extract once it has thawed.



**FIGURE 3.5** Streaking of bacterial stock in a “zigzag” pattern on a Luria–Bertani (LB) plate. Fourteen hours later, well-isolated bacterial colonies are generated in the last streaking area in the plate.

2. Once the extracts have thawed, immediately add 5–10  $\mu\text{l}$  of the ligated mixture to the extract and mix gently.
3. Incubate at 22–24°C for 2–4 h and add 0.5 ml of phage buffer and 20  $\mu\text{l}$  of chloroform to the mixture. Gently mix well and allow the chloroform to settle to the bottom of the tube. Store the packaged phage at 4°C for up to 5 weeks, the titer may drop, though. Proceed to titrating of lambda phage.

### 3.2.8.2 Titration of Packaged Phage

1. Briefly thaw the specific bacterial strain such as *E. coli* DH5 $\alpha$ , *E. coli* 392, Y 1090, Y1089, and KW 251 on ice. The bacterial strain is usually kept in 20% glycerol and stored at –70°C until use. Pick up a small amount of the bacteria using a sterile wire transfer loop and immediately inoculate the bacteria on the surface of a Luria–Bertani (LB) plate (Figure 3.5). Invert the inoculated LB plate and incubate it in an incubator at 37°C overnight. Multiple bacterial colonies will be formed.

*Note: The LB plate should be freshly prepared and dried at room temperature for a couple of days before use.*

2. Prepare fresh bacterial culture by inoculating a single colony from the streaked LB plate using a sterile wire transfer loop in 5 ml of LB medium supplemented with 50 ml of 20% maltose and 50 ml of 1 M  $\text{MgSO}_4$  solution. Shake at 160 rev/min at 37°C for 6–9 h or until the  $\text{OD}_{600}$  has reached 0.6.
3. Dilute each of the packaged recombinant phage samples at 1000 $\times$ , 5000 $\times$ , 10,000 $\times$ , and 100,000 $\times$  in phage buffer.
4. Add 20  $\mu\text{l}$  of 1 M  $\text{MgSO}_4$  solution and 2.8 ml of melted top agar to 36 sterile glass tubes in a sterile laminar flow hood. Cap the tubes and immediately place the tubes in 50°C water bath for at least 30 min before use.
5. Mix 0.1 ml of the diluted phage with 0.1 ml of freshly cultured bacteria in a microcentrifuge tube. Cap the tube and allow the phage to adsorb the bacteria in an incubator at 37°C for 30 min.



6. Add the phage/bacterial mixture into a specified tube in the water bath. Vortex gently and immediately pour onto the center of LB plates, quickly overlay all over the surface of LB plate with the mixture by gently tilting the plate. Cover the plates and allow the top agar to harden for 10 min. Invert the plates and incubate them in an incubator at 37°C overnight or for 15 h.

Note: *The top agar mixture should be evenly distributed over the surface of the LB plate. Otherwise, the growth of bacteriophage will be affected by decreasing the pfu number.*

7. Count the number of plaques for each plate and calculate the titer of the phage (pfu).

Plaque forming units (pfu) per milliliter = no. of plaques/plate  $\times$  dilution times  $\times$  10

The last 10 of the calculation refers to the 0.1 ml, per milliliter basis, of the packaging extract used for one plate. For instance, if there are 100 plaques on a plate made from a 1/5,000 dilution, the pfu per milliliter of the original packaging extract =  $100 \times 5000 \times 10 = 5 \times 10^6$ .

### Reagents needed

- Ligase 10 $\times$  buffer
  - 300 mM Tris-HCl, pH 7.8
  - 0.1 M MgCl<sub>2</sub>
  - 0.1 M DTT
  - 10 mM ATP
- Phage buffer
  - 20 mM Tris-HCl, pH 7.4
  - 0.1 M NaCl
  - 10 mM MgSO<sub>4</sub>
- LB medium (per liter)
  - 10 g Bacto-tryptone
  - 5 g Bacto-yeast extract
  - 5 g NaCl
  - Adjust to pH 7.5 with 0.2 N NaOH and autoclave
  - 20% (v/v) maltose
  - 1 M MgSO<sub>4</sub>
- LB plates
  - Add 15 g of Bacto agar to 1 l of prepared LB medium and autoclave. Allow the mixture to cool to about 60°C and pour 30 ml/dish into 85- or 100-mm Petri dishes in a sterile laminar flow hood with filtered air flowing. Remove any bubbles with a pipette tip and let the plates cool for 5 min prior to their being covered. Allow the agar to harden for 1 h and store the plates at room temperature for up to 10 days or at 4°C in a bag for 1 month. The cold plates should be placed at room temperature for 1–2 h before use.

- TB top agar  
Add 3.0 g agar to 500 ml prepared LB medium and autoclave. Store at 4°C until use. For plating, melt the agar in a microwave. When the solution has cooled to 60°C, add 0.1 ml of 1 M MgSO<sub>4</sub> per 10 ml of the mixture. If color selection methodology is used to select recombinants in conjunction with bacterial host strain Y1090, 0.1 ml isopropyl-β-D-thiogalactoside (IPTG) (20 mg/ml in water, filter-sterilized) and 0.1 ml X-Gal (50 mg/ml in dimethylformamide) should be added to the cooled (55°C) 10 ml of the top agar mixture.
- S buffer  
Phage buffer + 2% (w/v) gelatin

### 3.2.8.3 Amplification of cDNA Library (Optional)

1. For each 50 ml of bacterial culture, add 10–15 μl of  $1 \times 10^5$  pfu of packaged bacteriophage or “total plaque eluate” into a microcentrifuge tube containing 240–235 μl of phage buffer. Mix with 0.25 ml of cultured bacteria and allow the bacteria and phage to adhere to each other by incubating at 37°C for 30 min.
2. Add the above mixture into a 250- or 500-ml sterile flask containing 50 ml of LB medium prewarmed at 37°C, which is supplemented with 1 ml of 1 M MgSO<sub>4</sub>. Incubate at 37°C with shaking at 260 rev/min until lysis occurs.  
*Tips: It usually takes 9 to 11 h for lysis to occur. The medium should be cloudy after several hours of culture and then be clear upon cell lysis. Cellular debris also becomes visible in the lysed culture. There is a density balance between bacteria and bacteriophage. If the bacteria density is much over that of bacteriophage, it takes longer for lysis to occur, or no lysis takes place at all. In contrast, if bacteriophage concentration is much over that of bacteria, lysis is too quick to be visible at the beginning of the incubation, and later on, no lysis will happen. The proper combination of bacteria and bacteriophage used in step 1 will assure success. In addition, careful observations should be made after 9 h of culture because the lysis is usually quite rapid after that time. Incubation of cultures should stop once lysis occurs. Otherwise, the bacteria grow continuously and the cultures become cloudy again. Once that happens, it will take a long time to see lysis, or no lysis takes place at all.*
3. Immediately centrifuge at 9000 g for 10 min at 4°C to spin down the cellular debris. Transfer the supernatant containing the amplified cDNA library in bacteriophage particles into a fresh tube. Aliquot the supernatant, add 20–40 μl of chloroform, and store at 4°C for up to 5 weeks.

## 3.2.9 ISOLATION OF SPECIFIC cDNA FROM THE SUBTRACTED cDNA LIBRARY

Details of the screening protocols are described in Section 3.3.

### 3.2.10 CHARACTERIZATION OF cDNA

DNA sequencing and sequence analysis are described in detail in Chapters 5 and 6.

### 3.3 CONSTRUCTION AND SCREENING OF A COMPLETE EXPRESSION cDNA LIBRARY

#### 3.3.1 GENERAL PRINCIPLES AND CONSIDERATIONS OF AN EXPRESSION cDNA LIBRARY

Unlike a subtracted cDNA library described above, a complete cDNA library theoretically contains all cDNA clones corresponding all mRNAs expressed in a cell or tissue type. An expression cDNA library refers to one in which all cDNAs are cloned in the sense orientation so that all the cDNA clones in the library can be induced to express their mRNAs and proteins. As a result, this cDNA library can be screened with specific antibodies against the expressed protein of interest or with a specific nucleic acid probe.

The general principles and procedures are similar to those of a subtracted cDNA library described above. Briefly, mRNAs are transcribed into the first stranded DNAs, or called complementary DNA (cDNA), based on nucleotide bases complementary to each other. This step is catalyzed by AMV reverse transcriptase using oligo(dT) adapter-primers. The second-stranded DNA is copied from the first stranded DNA using RNase H that creates nicks and gaps in the hybridized mRNA template, generating 3'-OH priming sites for DNA synthesis by DNA polymerase I. After treatment with T4 DNA polymerase to remove any remaining 3' protruding ends, the blunt-ended, double-stranded cDNAs are ready for the ligation with appropriate adapters or linkers. The resultants are then packaged *in vitro* and cloned in a specific host, generating a complete express cDNA library. In theory, this type of cDNA library preserves as much of the original cDNAs as possible, which can allow one to "fish" out any possible cDNA clones by screening the cDNA library as long as a specific probe or specific antibodies are available (Figure 3.6).

#### 3.3.2 ISOLATION OF TOTAL RNAS AND PURIFICATION OF MRNAs FROM CELLS OR TISSUES OF INTEREST

Detailed protocols are described in Section 3.2.

#### 3.3.3 SYNTHESIS OF cDNAs FROM MRNAs


See Subtracted cDNA Library (Section 3.2) for detailed protocols.

#### 3.3.4 LIGATION OF cDNAs TO $\lambda$ GT11 EXPRESSION VECTORS

$\lambda$ gt11 or equivalent vectors should be used for construction of an expression cDNA library. Restriction enzyme digestion of both cDNAs and vector arms and their ligation are described in detail in Section 3.2 (Construction and Screening of a Subtracted cDNA Library).

#### 3.3.5 GENERATION OF AN EXPRESSION cDNA LIBRARY

Packaging *in vitro* and generation of a library are the same as described in Section 3.2.



**FIGURE 3.6** Construction of a complete expression cDNA library using a directional cloning strategy.

### 3.3.6 SCREENING OF THE EXPRESSION LIBRARY AND ISOLATION OF THE cDNA OF INTEREST

#### 3.3.6.1 Method A. Immunoscreening of Expression cDNA Library Using Specific Antibodies

cDNAs cloned at the multiple cloning site (MCS) in the *lac Z* gene of vector  $\lambda$ gt11 *Sfi*-*Not*I can be expressed as a part of  $\beta$ -galactosidase fusion proteins. The expression cDNA library can be screened with specific antibodies of interest. The primary positive clones are then “fished” out from the library. After several rounds of reitering and rescreening of the primary positive clones, putative cDNA clones of interest will be isolated.

1. Prepare LB medium, pH 7.5, by adding 15 g of Bacto agar to 1 l of the LB medium followed by autoclaving. Allow the mixture to cool to about 55°C and add ampicillin (100  $\mu$ g/ml) or tetracycline (15  $\mu$ g/ml), depending on antibiotic resistant genes contained in the vectors. Mix well and pour 30 ml/dish of the mixture into 85- or 100-mm Petri dishes in a sterile laminar flow hood with filtered air flowing. Remove any bubbles with a pipette tip and allow the plates to cool for 5 min before being covered. Let the agar harden for 1 h and store the plates at room temperature for up to 10 days or at 4°C in a bag for 1 month. The cold plates should be placed at room temperature for 1–2 h before use.
2. Partially thaw a specific bacterial strain such as *E. coli* Y 1090 on ice. Pick up a tiny bit of the bacteria using a sterile wire transfer loop and immediately streak out *E. coli* Y1090 on an LB plate by gently drawing several lines on the surface of an LB plate (Figure 3.5). Invert the inoculated LB plate and incubate in an incubator at 37°C overnight. Multiple bacterial colonies will be generated.
3. Prepare fresh bacterial cultures by picking up a single colony from the streaked LB plate using a sterile wire loop and inoculate into a culture tube containing 50 ml of LB medium supplemented with 500  $\mu$ l of 20% maltose and 500  $\mu$ l of 1 M MgSO<sub>4</sub> solution. Shake at 160 rev/min at 37°C overnight or until the OD<sub>600</sub> has reached 0.6. Store the culture at 4°C until use.
4. Add 20  $\mu$ l of 1 M MgSO<sub>4</sub> solution and 2.8 ml of melted LB top agar to each of sterile glass test tubes in a sterile laminar flow hood. Cap the tubes and immediately place the tubes in 50°C water bath for at least 30 min before use.
5. According to the titration data, dilute the lambda cDNA library with phage buffer. Set up 20 to 25 plates for primary screening of the cDNA library. For each of the 100-mm plates, mix 0.1 ml of the diluted phage containing  $2 \times 10^5$  pfu of the library with 0.15 ml of fresh bacteria in a microcentrifuge tube. Cap the tube and allow the phage to adsorb the bacteria at 37°C for 30 min. Note: *The number of clones needed to detect a given probability that a low-abundance mRNA is converted into a cDNA in a library is as follows:*

$$N = \ln(1 - P) / \ln(1 - 1/n)$$

where *N* is the number of clones needed, *P* is the possibility given (0.99), *1/n* is the fractional portion of the total mRNA, which is represented by

*a single low-abundant mRNA molecule. For example, if  $P = 0.99$ ,  $1/n = 1/37,000$ ,  $N = 1.7 \times 10^5$ .*

6. Add the incubated phage/bacterial mixture to the tubes from the water bath. Vortex gently and quickly pour onto the center of an LB plate, quickly spread the mixture over the entire surface of an LB plate by tilting the plate. Cover the plates and allow the top agar to harden for 5–10 min in laminar flow hood. Invert the plates and incubate them in an incubator at 42°C for 4 h.

*Note: The top agar mixture should be evenly distributed over the surface of an LB plate. Otherwise, the growth of the bacteriophage may be affected.*

7. Saturate nitrocellulose filter disks in 10 mM IPTG in water for 30 min and air dry the filters at room temperature for 30 min.
8. Carefully overlay each plate with a dried nitrocellulose filter disk from one end and slowly lower it to the other end of the plate. Avoid any air bubbles underneath the filter. Quickly and carefully mark the top side and position of each filter in a triangle fashion by punching the filter through the bottom agar using a 20-gauge needle containing India ink. Cover the plates and incubate at 37°C for 4–6 h. If a duplicate is needed, a second filter may be overlaid on the plate and incubated for another 5 h at 37°C. However, the signal will be relatively weaker.

*Note: IPTG induces the expression of the cDNA library and the expressed proteins are transferred onto the facing side of the membrane filters.*


9. Place the plates at 4°C for 30 min to chill the top agar and to prevent the top agar from sticking onto the filters. Transfer the plates to room temperature and carefully remove the filters using forceps. Label and wrap each plate with Parafilm and store at 4°C until use. The filters can be rinsed briefly in TBST buffer to remove any agar.

*Tips: Due to the possible diffusion of proteins, the filters are strongly recommended to be processed according to the following steps. Storage at 4°C for a couple of days before processing may cause difficulty in the identification of the actual positive plaque in the plates. The filters must not be allowed to dry out during any of the subsequent steps that are carried out at room temperature. Based on our experience, high background and strange results may appear, even partial drying. If time is limited, the damp filters may be wrapped in Saran Wrap, then in aluminum foil, and stored at 4°C for up to 12 h. The filters are recommended to be processed individually during the following steps to obtain an optimal detection signal.*

10. Incubate a filter in 10 ml of TBST buffer containing 2–3% BSA or 1% gelatin or 5% nonfatty milk or 20% calf serum to block nonspecific protein binding sites on the filter. Treat the filters for 60 min with slow shaking at 60 rev/min.  
*Note: It is recommended that one use one dish for one filter only and that the facing side of the filter be down. Each filter is incubated with about 10 ml of blocking buffer. Less than 5 ml will cause the filter to dry but more than 15 ml for a 82 mm filter may prevent one from obtaining optimal results.*
11. Carefully transfer the filters to fresh dishes, each containing 10 ml of TBST buffer with primary antibody.

*Tip: The antibodies should be diluted at 200–10,000×, depending on the concentration of the antibody stock. The antibodies purified with an IgG*

- fraction or with an affinity column usually produce better signals. The diluted primary antibody can be reused several times if stored at 4°C.*
12. Wash each filter in 20 ml of TBST buffer containing 0.5% BSA for 10 min with shaking at 60 rev/min. Repeat washing twice.
  13. Transfer the filter to a fresh dish containing 10 ml of TBST buffer with the second antibody–alkaline phosphatase conjugate at 1:5000–10,000 dilution. Incubate for 40 min with shaking at 60 rev/min.
  14. Wash the filters as in step (12).
  15. Briefly damp dry the filter on a filter paper and place the filter in 10 ml of freshly prepared AP color development substrate solution. Allow the color to develop for 0.5–5 h or overnight. Positive clones should appear as purple circle spots on the white filter.
  16. Stop the color development when the color has developed to a desired intensity in 15 ml of stop solution. The filter can be stored in the solution or stored as dry. The color will fade after drying but can be restored in water.
  17. In order to locate the positive plaques, carefully match the filter to the original plate by placing the filter, facing side down, underneath the plate with the help of marks made previously. This can be done by placing a glass plate over a lamp and putting the matched filter and plate on the glass plate. Turn on the light so that the positive clones can easily be identified. Transfer individual positive plugs containing phage particles from the plate using a



**FIGURE 3.7** Diagram of rescreening and purification of positive clones from a cDNA library.

sterile pipette tip with the tip cut off. Expel the plug into a microcentrifuge tube containing 1 ml of elution buffer. Elute phage particles from the plug at room temperature for 4 h with occasional shaking.

18. Transfer the supernatant containing phage particles into a fresh tube and add 20  $\mu$ l of chloroform. Store at 4°C for up to 5 weeks.
19. Determine the pfu of the eluate, as described in Section 3.2. Replate the phage and repeat the screening procedure with the antibody probe several times until 100% of the plaques on the plate are positive (Figure 3.7).  
*Tips: During the rescreening process, the plaque number used for each plate should be gradually reduced. In my experience, the plaque density for one 100-mm plate in the rescreening procedure is 1000 to 500 to 300, and to 100.*
20. Amplify the putative cDNA clones and isolate the recombinant lambda DNAs by either plate or liquid methods.

### Reagents needed

- LB medium per liter  
10 g Bacto-tryptone  
5 g Bacto-yeast extract  
5 g NaCl  
Adjust pH to 7.5 with 0.2 N NaOH, then autoclave
- LB top agar (500 ml)  
Add 4 g agar to 500 ml of LB medium and autoclave
- Elution buffer  
10 mM Tris-HCl, pH 7.5  
10 mM MgCl<sub>2</sub>
- IPTG solution  
10 mM isopropyl  $\beta$ -D-thiogalactopyranoside in dd.H<sub>2</sub>O
- Phage buffer  
20 mM Tris-HCl, pH 7.4  
0.1 M NaCl  
10 mM MgSO<sub>4</sub>
- TBST buffer  
10 mM Tris-HCl, pH 8.0  
150 mM NaCl  
0.05% Tween 20
- Blocking solution  
3% BSA, or 1% gelatin, or 5% nonfatty milk in TBST buffer
- AP buffer  
0.1 M Tris-HCl, pH 9.5  
0.1 M NaCl  
5 mM MgCl<sub>2</sub>
- Color development substrate solution  
50 ml AP buffer.  
0.33 ml NBT (nitroblue tetrazolium) stock solution



0.165 ml BCIP (5-bromo-4-chloro-3-indolyl phosphate) stock solution. Mix well after each addition and protect the solution from strong light. Warm the substrate solution to room temperature to prevent precipitation.

- Stop solution  
20 mM Tris-HCl, pH 8.0  
5 mM EDTA

### 3.3.6.2 Method B. Screening a cDNA Library Using <sup>32</sup>P-Labeled DNA as a Probe

In addition to the Immunoscreening methodology described above, the cDNA library can also be screened with labeled DNA as a probe, which can be labeled by isotopic or nonisotopic methods (see Chapter 7 for detailed protocols). The library is screened by *in situ* plaque hybridization with the probe. Identification of cDNA clones of a potential multigene family can be obtained at relatively low stringency of hybridization. This will be achieved, based on our experience, by reducing the percentage of formamide (30–40%) in hybridization solution and washing temperature (room temperature followed by 50–55°C). Keep the temperature of hybridization being constant and the salt in the wash solution constant at 2× SSC in 0.1% SDS. To prevent nonspecific cross-linking hybridization, however, a high stringency condition should be applied. Positive plaques will then be isolated to homogeneity by successive rounds of phage titering and rescreening. The resulting phage lysates will be used in the large-scale preparation of phage DNAs.

The general procedures are the same as described for “Screening of Genomic DNA Library” in Chapter 15.

### 3.3.6.3 Method C. Screening a cDNA Library Using a Nonradioactive Probe

The general procedures are described in Chapter 19.

### 3.3.6.4 Method D. Isolation of λ Phage DNAs by the Liquid Method

1. For each 50 ml of the bacterial culture, add 10–15 μl of  $1 \times 10^5$  pfu of “plaque eluate” into a microcentrifuge tube containing 240–235 μl phage buffer. Mix with 0.25 ml of cultured bacteria and allow the bacteria and phage to adhere to each other by incubating at 37°C for 30 min.
2. Add the above mixture into a 250- or 500-ml sterile flask containing 50 ml of LB medium prewarmed at 37°C, which is supplemented with 1 ml of 1 M MgSO<sub>4</sub>. Incubate at 37°C with shaking at 260 rev/min until lysis occurs.  
*Tips: It usually takes 9 to 11 h for lysis to occur. The medium should be cloudy after several hours of culture and then be clear upon cell lysis. Cellular debris also becomes visible in the lysed culture. There is a density balance between bacteria and bacteriophage. If the bacteria density is much over that of bacteriophage, it takes longer for lysis to occur, or no lysis takes place at all. In contrast, if bacteriophage concentration is much over that of bacteria, lysis is too quick to be visible at the beginning of the incubation, and later on, no lysis will happen. The proper combination of*

*bacteria and bacteriophage used in step 1 will assure success. In addition, careful observations should be made after 9 h of culture because the lysis is usually quite rapid after that time. Incubation of cultures should stop once lysis occurs. Otherwise, the bacteria grow continuously and the cultures become cloudy again. Once that happens, it will take a long time to see lysis, or no lysis takes place at all.*

3. Immediately centrifuge at 9000 g for 10 min at 4°C to spin down the cellular debris. Transfer the supernatant containing the amplified cDNA library in bacteriophage particles into a fresh tube. Aliquot the supernatant, add 20–40 µl of chloroform, and store at 4°C for up to 5 weeks.
4. Add RNase A and DNase I to the lambda lysate supernatant, each to a final concentration of 2–4 µg/ml. Place at 37°C for 30–60 min.  
*Note: RNase A functions to hydrolyze the RNAs. DNase I will hydrolyze chromosomal DNA but not phage DNA that is packed.*
5. Precipitate the phage particles with 1 volume of phage precipitation buffer and incubate for at least 1 h on ice.
6. Centrifuge at 12,000 g for 15 min at 4°C and allow the pellet to dry at room temperature for 5–10 min.
7. Resuspend the phage particles with 1 ml of phage release buffer per 10 ml of initial phage lysate and mix by vortexing.
8. Centrifuge at 5000 g for 4 min at 4°C to remove debris and carefully transfer the supernatant into a fresh tube.
9. Extract the phage particle proteins using an equal volume of TE-saturated phenol/chloroform. Mix for 1 min and centrifuge at 10,000 g for 5 min.
10. Transfer the top, aqueous phase to a fresh tube and extract the supernatant one more time as in step 9.
11. Transfer the top, aqueous phase to a fresh tube and extract once with one volume of chloroform/isoamyl alcohol (24:1). Vortex and centrifuge as in step 9.
12. Carefully transfer the upper, aqueous phase containing λDNAs to a fresh tube and add one volume of isopropanol or 2 volumes of chilled 100% ethanol. Mix well and precipitate the DNAs at –80°C for 30 min or –20°C for 2 h.
13. Centrifuge at 12,000 g for 10 min at room temperature and aspirate the supernatant. Briefly wash the pellet with 2 ml of 70% ethanol and dry the pellet under vacuum for 10 min. Resuspend the DNA in 50–100 µl of TE buffer. Measure the DNA concentration (similar to RNA measurement described previously) and store at 4°C or –20°C until use.

### Reagents needed

- SM buffer (per liter)
  - 50 mM Tris–HCl, pH 7.5
  - 0.1 M NaCl
  - 8 mM MgSO<sub>4</sub>

- 0.01% gelatin (from 2% stock)  
Sterilize by autoclaving
- Phage buffer  
20 mM Tris-HCl, pH 7.4  
100 mM NaCl  
10 mM MgSO<sub>4</sub>
  - Release buffer  
10 mM Tris-HCl, pH 7.8  
10 mM EDTA
  - Phage precipitation solution  
30% (w/v) polyethylene glycol (MW 8000) in 2 M NaCl solution
  - TE buffer  
10 mM Tris-HCl, pH 8.0  
1 mM EDTA
  - TE-saturated phenol/chloroform  
Thaw crystals of phenol in a 65°C water bath and mix with an equal volume of TE buffer. Allow the phases to separate for about 10–20 min. Mix 1 part of the lower phenol phase with 1 part of chloroform/isoamyl alcohol (24:1). Allow the phases to separate and store at 4°C in a light-tight bottle.
  - DNase-free RNase A  
To make DNase-free RNase A, prepare a 10 mg/ml solution of RNase A in 10 mM Tris-HCl, pH 7.5 and 15 mM NaCl. Boil for 15 min and slowly cool to room temperature. Filter if necessary. Alternatively, RNase (DNase-free) from Boehringer Mannheim can be utilized.

### 3.3.7 CHARACTERIZATION OF cDNA

Isolated cDNA clones should be carefully characterized. For DNA sequencing and sequence analysis, detailed methods are described in Chapters 5 and 6.

#### Troubleshooting Guide

1. *Low yield of the first strand cDNAs.* The success of the synthesis of first and second strand cDNAs is extremely important and is considered to be halfway done in making a cDNA library. If the yield of the first strand cDNA conversion is less than 8%, and if the intensity of the different cDNA sizes shown on the x-ray film is very weak or if the size range is very small and of lower molecular weight, the potential causes for these problems are likely due to poor mRNA preparation and/or the failure of reverse transcriptase. The quality of the mRNA templates is the most important factor for a successful cDNA synthesis. If the poly(A) + RNA is degraded during isolation and/or purification procedures, the first strand cDNA synthesized from the template is only partial-length cDNA. To avoid this problem, it is important to check the quality of mRNA templates before the synthesis of first strand cDNAs. This can be done by analyzing 2 µg mRNAs in 1% agarose-formaldehyde denaturing gel containing ethidium bromide

(EtBr). After electrophoresis, take a photograph of the gel under UV light. If the smear range is from 0.65 up to 10 kb, the integrity of the mRNA is very good for the synthesis of cDNA. Another possible cause is that AMV reverse transcriptase for the synthesis of first strand cDNAs fails in the middle of the procedure. In that case, the cDNAs produced are likely to be only partial-length. Try to use positive mRNA templates as a control to check the activity of reverse transcriptase. If mRNA templates and reverse transcriptase are very good, then use control RNA to check for the presence of inhibitors such as SDS, EDTA, and salts.

2. *Low yield of the second strand cDNAs.* If the yield of the second strand DNA conversion is less than 40%, or the size range is very small and of abundant lower molecular weight, it may be due to either RNase H or DNA polymerase I that does not function well. To check the activity of RNase H, treat control mRNA with the enzyme and assayed by electrophoresis. If the RNase H works well, the mRNA is nicked into fragments. This will be indicated by gel electrophoresis as compared with untreated mRNA. On the other hand, if DNA polymerase I does not function well, the synthesis of second strand cDNAs or the repair of gaps will not be completed, thus generating partial-length cDNAs. In that case, set up another reaction using a control experiment, or use fresh DNA polymerase I. If low incorporation occurs even with the positive control, it is likely that the radioisotope used as a labeled probe is not good. Check the specificity and half-life of the isotope and use fresh [ $\alpha$ - $^{32}$ P]dCTP as a control.
3. *Plaques are small in one area and large in other areas.* This is due to uneven distribution of the top agar mixture. Make sure that the top agar mixture is spread evenly.
4. *Too many positive clones in the primary screening.* The specificity of the primary antibodies is low, or the concentration is too high, or the blocking efficiency is low. Try to use IgG or an affinity-column purified antibodies and carry out different dilutions of the antibodies, and/or increase the percentage of the blocking reagent in TBST buffer.
5. *Purple background on the filter.* Color development is too long. Try to stop the color reaction as soon as desired signals appear.
6. *Unexpected larger purple spots.* Air bubbles may be produced when one overlays the filters on the LB plates. Make sure that no air bubbles are generated underneath the filters.
7. *No signals appear at all in any of the primary screening plates.* The pfu numbers used for each plate may be too low. For rare proteins,  $2 \times 10^6$  pfu should be used in primary screening of the library.
8. *Signals are weak on the filters of subsequent screening.* The antibodies have a low activity or color development was stopped too soon. Try to use an immunoassay to check the quality of the antibodies, or allow color development to proceed for a longer period, and/or try to use high-quality nitro-cellulose filters.

## REFERENCES

1. Wu, L.-L., J. P. Mitchell, N. S. Cohn, and P. B. Kaufman. 1993. Gibberellin (GA<sub>3</sub>) enhances cell wall invertase activity and mRNA levels in elongating dwarf pea (*Pisum sativum*) shoots. *International Journal of Plant Sciences* 154: 280.
2. Wu, W., and M. J. Welsh. 1996. Expression of the 25-kDa heat-shock protein (HSP27) correlates with resistance to the toxicity of cadmium chloride, mercuric chloride, cis-platinum(II)-diammine dichloride, or sodium arsenite in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Toxicology and Applied Pharmacology* 141: 330–339.
3. Welsh, M. J., W. Wu, M. Parvinen, and R. R. Gilmont. 1996. Variation in expression of HSP27 messenger ribonucleic acid during the cycle of the seminiferous epithelium and co-localization of HSP27 and microfilaments in Sertoli cells of the rat. *Biology of Reproduction* 55: 141–151.
4. Wu, W. 1995. cDNA and Genomic DNA Libraries. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and C. Leland, 123–210. Boca Raton, FL: CRC Press.
5. Okayama, H., and P. Berg. 1982. High-efficiency cloning of full-length cDNA. *Molecular Cell Biology* 2: 161.
6. Wu, L.-L., I. Song, N. Karuppiah, and P. B. Kaufman. 1993. Kinetic induction of oat shoot pulvinus invertase mRNA by gravistimulation and partial cDNA cloning by the polymerase chain reaction. *Plant Molecular Biology* 21: 1175.
7. Mignery, G. A., C. S. Pikaard, D. J. Hannapel, and W. D. Park. 1984. Isolation and sequence analysis of cDNAs for the major tuber protein patatin. *Nucleic Acids Research* 12: 7987–8000.
8. Frohman, M. A., M. K. Dush, and G. R. Martin. 1988. Rapid production of full-length cDNAs from rare transcripts: amplification using a single gene-specific oligonucleotide primer. *Proceedings of the National Academy of Sciences of the United States of America* 85: 8998.
9. Sambrook, J., E. F. Fritsch, and T. Maniatis. 1989. *Molecular Cloning, A Laboratory Manual*, 2nd edn. Cold Spring Harbor, NY: Cold Spring Harbor Laboratory Press.
10. Chomczynski, P., and N. Sacchi. 1987. Single-step method of RNA isolation by acid guanidinium thiocyanate phenol–chloroform extraction. *Analytical Biochemistry* 162: 156.



---

# 4 Subcloning of Genes or DNA Fragments

## 4.1 INTRODUCTION

Subcloning or insertion of a gene or DNA fragment into an appropriate vector is an essential technique that is widely used in molecular biology today. Major advantages include: (1) DNA fragments of interest can be subcloned into a high copy number of plasmid vector and can be amplified up to 300-fold by plasmid replication in *Escherichia coli*; (2) vectors used for subcloning usually contain SP6, T7, or T3 promoters upstream from the polycloning sites, which allows one to prepare sense RNA or antisense RNA of the inserted cDNA as hybridization probes; (3) the SP6, T7, and T3 promoters enables an investigator to sequence the DNA insert on both strands in opposite directions; and (4) DNA constructs can be prepared by inserting a gene or cDNA of interest into an appropriate vector for gene transfer and expression in cultured cells and animals.


What is the principle involved and how can one insert a gene or DNA fragment of interest into the right place in a vector? The general procedures start with restriction enzyme digestion of both vector and insert DNA. After digestion, sticky or blunt ends are generated. Compatible sticky ends of both vectors and DNA inserts will be ligated together using T4 DNA ligase, forming recombinant constructs. In case of incompatible ends between vectors and inserts, the ends can be blunt-ended by 5'- or 3'-end filling. DNA constructs can be made by blunt-end ligation. The constructs are then transformed into an appropriate bacterial strain in which plasmids are replicated up to >300 copies/cell. Transformed bacterial colonies will be selected using appropriate antibiotics. This chapter describes the methods that have been well established and are routinely used in our laboratories.

## 4.2 RESTRICTION ENZYME DIGESTION OF VECTOR OR DNA INSERT FOR SUBCLONING


### 4.2.1 SELECTION OF RESTRICTION ENZYMES

Restriction enzymes or endonucleases recognize specific base sequences in DNA and make a cut on both strands. In general, these enzymes can be divided into two types. Type A refers to the endonucleases that can produce sticky ends after digestion. Type B enzymes generate blunt ends after digestion. There are hundreds of restriction enzymes that are commercially available. Typical type A enzymes include *Bam*HI,

*HindIII*, *EcoRI*, *KpnI*, *NotI*, *SacI*, *XhoI*, and *XbaI*. They can recognize and produce sticky ends as follows:



The common type B enzymes that generate blunt ends are as follows:



#### Tips:

(1) *Selection of restriction enzymes depends on particular restriction enzyme cutting site in vectors and on DNA to be inserted. To make the best choice, one needs to do some homework to find out which enzyme has a unique cut at the right place using a computer program such as GCG or Eugene (see Chapter 6). In my experience, several selections can be made. Choice A: Two incompatible, sticky ends in vector and the same sticky ends in DNA insert will be the best choice for high efficiency of ligation and transformation. For example, if the DNA insert has XhoI and HindIII sites at both ends of the DNA to be subcloned, and if the vector also has unique XhoI and HindIII sites at the multiple cloning site (MCS), this will be very fortunate. One can easily digest both vector and insert DNA with these two*



*enzymes. After purification of the digested DNA, vectors or inserts cannot undergo self-ligation because of the two incompatible, sticky ends produced by these two enzymes. During ligation, only insert and vector DNA can be combined together. In theory, any colonies after antibiotic selection will be positive transformants. If all goes well, putative constructs can be obtained in a few days starting from restriction enzyme digestion to verification of positive colonies.*

- (2) Choice B: If one cannot find two unique restriction enzyme sites at the right place, one unique site will be sufficient. For instance, if each of the vectors and inserts has a unique EcoRI site at the right site for cloning, both vector and insert can then be digested with EcoRI. The disadvantage, as compared with choice A, is that choice B will have less efficiency of ligation between vector and insert, and lower efficiency of transformation. Because the same single sticky end in both vector and DNA insert, the vector or insert will undergo a high percentage of self-ligation even though the vectors are treated with alkaline phosphatase. As a result, most of the colonies selected by antibiotics may be from self-ligation vectors, which makes it time-consuming and costly to verify the selected colonies. Nonetheless, single, sticky ends ligation will allow one to simultaneously make both sense and antisense orientations of DNA insert. In other words, the DNA of interest will be inserted into the vector in both directions, with a probability of 1:1. This is particularly useful if one wishes to make both sense and antisense constructs of cDNA to be expressed.*
- (3) If a unique enzyme site available at the right place is a blunt-end enzyme, one may have to use the blunt-end ligation approach. As compared with choices A and B, choice C has the lowest efficiency of ligation and transformation. It is known that blunt-end ligation is difficult to perform. A very small percentage of digested vectors and inserts can be ligated together at 4°C or 16°C. Even worse, a significant portion of the ligated DNA molecules is self-ligated DNA. It usually takes weeks or months to obtain putative DNA constructs. Obviously, this is not an effective method for cloning and may lead to frustration.*

#### **4.2.2 SELECTION OF CLONING VECTORS**

Plasmids such as pcDNA3, pcDNA 3.1, pMAMneo, pGEM series, and pBlue-script-SK II are commercially available for subcloning. Selection of particular vectors depends on individual investigators. In general, a standard plasmid for subcloning of a DNA fragment should contain the following necessary fragments: (1) a polycloning site for the insertion of the DNA of interest; (2) SP6, T7, or T3, or equivalent promoters upstream from the MCS in opposite directions in order to express the DNA insert for sense RNA, or antisense RNA, or for protein analysis; (3) the origin of replication for the duplication of the recombinant plasmid in the host cells; and (4) a selectable marker gene such as *Amp<sup>r</sup>* for antibiotic selection of transformants.

### 4.2.3 PROTOCOLS FOR RESTRICTION ENZYME DIGESTION

- For single restriction enzyme digestion, set up the following reaction on ice.
 

DNA (vector or insert DNA)	10–12 $\mu\text{g}$ in 6 $\mu\text{l}$
10 $\times$ appropriate restriction enzyme buffer	2.5 $\mu\text{l}$
<u>Appropriate restriction enzyme</u>	<u>3.3 units/<math>\mu\text{g}</math> DNA</u>
Add dd.H <sub>2</sub> O to a final volume of	25 $\mu\text{l}$

The following reaction is designed for two restriction enzymes digestion.

DNA (vector or insert DNA)	10–12 $\mu\text{g}$ 6 $\mu\text{l}$
10 $\times$ appropriate restriction enzyme buffer	3 $\mu\text{l}$
Appropriate restriction enzyme A	3 units/ $\mu\text{g}$ DNA
<u>Appropriate restriction enzyme B</u>	<u>3 units/<math>\mu\text{g}</math> DNA</u>
Add dd.H <sub>2</sub> O to a final volume of	30 $\mu\text{l}$

Notes:

- The restriction enzyme(s) used for vector and insert DNA digestions should be the same in order to ensure the optimal ligation. The digestions should be carried out in separate tubes for vector and insert DNA.*
  - For double restriction enzyme digestions, the appropriate 10 $\times$  buffer containing a higher NaCl concentration than the other buffer may be used for double-enzyme digestion.*
  - If two restriction enzymes require different reaction buffers, it is better to set up two consecutive single restriction digestion to ensure the DNA will be completely cut. Specifically, perform one enzyme digestion of the DNA and precipitated the DNA afterward. The DNA can be dissolved in dd.H<sub>2</sub>O and carry out the second enzyme digestion.*
- Incubate the reaction at an appropriate temperature (e.g., 37°C) for 2 h. For single enzyme digested DNA, proceed to step 3. For double-enzyme digested DNA, proceed to step 5.

Tips:

- To obtain an optimal ligation, the vector and insert DNA should be completely digested. The digestion efficiency may be checked by loading 1  $\mu\text{g}$  of the digested DNA with loading buffer in a 1% agarose mini-gel. Meanwhile, undigested vector and insert DNA (1  $\mu\text{g}$ ) and standard DNA markers should be loaded into the adjacent wells. After electrophoresis, the undigested plasmid DNA may display multiple bands because of different levels of supercoiled plasmids. However, one band should be visible for a complete, single enzyme digestion; one major band and one tiny band (<70 bp) may be visible after digestion with two different restriction enzyme digestion of vectors.*
  - After completion of restriction enzyme digestion, calf intestinal alkaline phosphatase (CIAP) treatment should be carried out for single*

*restriction enzyme digestion of vectors. This treatment serves to remove 5'-phosphate groups, thus preventing recircularization of the vector during ligation. Otherwise, the efficiency of ligation between vector and insert DNA will be very low. For vectors digested with double-restriction enzymes, the CIAP treatment is not necessary.*

3. Perform the CIAP treatment as follows:

10× CIAP buffer	5 $\mu$ l
Single enzyme digested DNA	25 $\mu$ l
CIAP diluted in 10× CIAP buffer	0.01 unit/pmole ends
Add dd.H <sub>2</sub> O to a final volume of	50 $\mu$ l

Notes:

- (1) CIAP and 10× CIAP should be kept at 4°C.  
 (2) Calculate pmole ends as follows:  
 For example, there is 9  $\mu$ g digested DNA left after using 1  $\mu$ g of 10  $\mu$ g digested DNA for analysis in an agarose gel. If the vector size is 3.2 kb, the pmole ends can be calculated by the formula below:

$$\begin{aligned} \text{pmole ends} &= \frac{\text{amount of DNA}}{(\text{base pairs} \times 660/\text{base pair})} \times 2 \\ &= \frac{9}{3.2 \times 1000 \times 660} \times 2 \\ &= 4.2 \times 10^{-6} \times 2 \\ &= 8.4 \times 10^{-6} \mu\text{M} \end{aligned}$$

$$8.4 \times 10^{-6} \times 10^6 = 8.4 \text{ pmol ends}$$

4. Incubate the reaction at 37°C for 1 h and add 2  $\mu$ l of 0.5 M EDTA buffer (pH 8.0) to terminate the reaction. At this point, two options are available. If the vector or insert DNA will be single fragment following restriction enzyme, the digested DNA can be purified by protein extraction and ethanol precipitation as described below. However, if restriction enzyme digestion results in more than one fragment or band, the fragment of interest should be purified by agarose gel electrophoresis as described in Section 4.3.
5. Add 1 volume of TE-saturated phenol/chloroform to the reaction. Mix well by vortexing the tube for 1 min and centrifuge at 11,000 g for 5 min at room temperature.
6. Carefully transfer the top, aqueous phase to a fresh tube and add 1 volume of chloroform/isoamyl alcohol (24:1) to the supernatant to further extract proteins. Mix well and centrifuge as described in step 5.
7. Carefully transfer the upper, aqueous phase to a fresh tube and add 0.1 volume of 3 M sodium acetate buffer (pH 5.2) or 0.5 volume of 7.5 M

ammonium acetate to the supernatant for efficient precipitation. Briefly mix and add 2 to 2.5 volumes of chilled 100% ethanol to the supernatant and precipitate the DNA at  $-80^{\circ}\text{C}$  for 1 h or at  $-20^{\circ}\text{C}$  for 2 h.

8. Centrifuge at 12,000  $g$  for 10 min and carefully decant the supernatant. Add 1 ml of 70% ethanol to the tube and centrifuge at 12,000  $g$  for 5 min. Dry the DNA pellet under vacuum for 20 min. Dissolve the DNA in 10  $\mu\text{l}$  dd.H<sub>2</sub>O. Take 1  $\mu\text{l}$  of the sample to measure the concentration of the DNA at  $A_{260\text{ nm}}$ . Store the sample at  $-20^{\circ}\text{C}$  prior to use. Proceed to DNA ligation.

## Reagents needed

- Appropriate enzymes
- 10 $\times$  appropriate restriction enzyme buffer
- 1% agarose minigel
- TE-saturated phenol/chloroform
- Chloroform/isoamyl alcohol (24:1)
- 7.5 M ammonium acetate
- 3 M sodium acetate buffer, pH 5.2
- Ethanol (100%, 70%)
- 0.5 M EDTA, pH 8.0
- CIAP
- TE buffer
- 10 $\times$  CIAP buffer
  - 0.5 M Tris-HCl, pH 9.0
  - 1 mM ZnCl<sub>2</sub>
  - 10 mM MgCl<sub>2</sub>
  - 10 mM spermidine

## 4.3 PURIFICATION OF DNA FRAGMENTS FROM AGAROSE GELS

### 4.3.1 ELUTION OF DNA BANDS BY HIGH-SPEED CENTRIFUGATION OF AGAROSE GEL SLICES

We have developed a rapid, simple method for eluting DNA bands from regular agarose gels by high-speed centrifugation. The agarose matrix containing DNA of interest will be compressed by the force of centrifugation, releasing DNA into the supernatant fluid. The method allows recovery of large as well as small DNA molecules. In addition to being rapid and simple, this method is inexpensive and does not require the use of phenol and chloroform in contrast to traditional methods. The eluted DNA is of high quality and suitable for restriction enzyme digestion, ligation, cloning, or labeling without further purification.<sup>1</sup> The protocol is described as follows:

1. Carry out electrophoresis as described in Chapter 7.
2. When electrophoresis is complete, quickly locate the DNA band of interest by illuminating the gel on a long wavelength ( $>300\text{ nm}$ ) UV transilluminator. Quickly slice out the band of interest using a sharp, clean razor blade.

Note: *To avoid potential damage to the DNA molecule, the UV light should be turned on as briefly as possible.*

3. To enhance the yield of DNA, trim away extra agarose gel outside the band and cut the gel slice into tiny pieces with the razor blade on a clean glass plate.
4. Transfer the fine slices into a 1.5-ml microcentrifuge tube (Eppendorf).

Notes:

- (1) *If one does not need to maximally elute DNA out of the gel slices, the slices do not need to be further sliced into tiny pieces. They can be directly placed in a tube.*
  - (2) *At this point, there are two options for eluting DNA from the agarose gel pieces. The first option is to immediately carry out high-speed centrifugation (step 5). The second option is to elute the DNA as high yield as possible (see below).*
5. Centrifuge at 12,000 to 14,000 g or at the highest speed using an Eppendorf Centrifuge 5415C (Brinkmann Instruments, Inc.) for 15 min at room temperature.

Principles: *With high-speed centrifugation, the agarose matrix is compressed and/or even partially destroyed by the strong force of centrifugation. The DNA molecules contained in the matrix are released into the supernatant fluid.*

6. After centrifugation, immediately and carefully transfer the supernatant fluid containing DNA into a clean microcentrifuge tube. The DNA can be directly used for ligation, cloning, labeling, and restriction enzyme digestion without ethanol precipitation. Store the DNA solution at 4°C or -20°C until use.

Tips:

- (1) *In order to confirm that the DNA is released from the gel pieces, the tube can be briefly illuminated with long wavelength UV light after centrifugation. An orange-red fluid color indicates the presence of DNA in the fluid.*
- (2) *The supernatant fluid should be immediately transferred from the agarose pellet; within minutes, the temporarily compressed agarose pellet may swell, absorbing the supernatant fluid.*

High yield and cleaner elution of DNA:

1. Add 100 to 300  $\mu$ l of distilled deionized water (dd.H<sub>2</sub>O) or TE buffer (10 mM Tris-HCl, 1 mM EDTA, pH 8.0) to the gel pieces described in step 4. Function: *TE buffer or dd.H<sub>2</sub>O is added to the gel pieces to help elute the DNA and to simultaneously wash EtBr from the DNA during high-speed centrifugation.*
2. Centrifuge at 12,000 to 14,000 g at room temperature for 20 min. When the centrifugation is complete, briefly visualize the eluted DNA by illumination using a long-wavelength UV light.
3. Immediately transfer the supernatant that contains the eluted DNA into a fresh tube.

4. To increase the recovery of DNA, extract the agarose pellet by resuspending the pellet in 100  $\mu$ l of dd.H<sub>2</sub>O or TE buffer followed by another cycle of centrifugation.
5. Pool the DNA supernatant and precipitate the DNA with ethanol. Dissolve DNA 10  $\mu$ l of dd.H<sub>2</sub>O or TE buffer. Store the DNA solution at 4°C or -20°C until use.

#### 4.3.2 ELUTION OF DNA FRAGMENT BY MELTING AND THAWING OF AGAROSE GEL SLICES

1. After restriction enzyme digestion, carry out electrophoresis as described in Southern blotting in Chapter 7, except that one should use 0.5% to 1% low melting temperature agarose instead of normal agarose.<sup>2-3</sup>
2. Transfer the gel to a long-wavelength UV transilluminator (305 to 327 nm) to visualize the DNA bands in the gel. Excise the band area of interest with a clean razor blade and transfer the slices into a microcentrifuge tube.

Notes:

(a) *The gel should not be placed on short-wavelength (e.g., <270 nm) UV transilluminator because this type of UV light may cause breakage inside the DNA fragment.*

(b) *The gel slices containing the DNA band of interest should be trimmed as much as possible in order to remove excess unstained gel areas.*

*Caution: UV light is harmful to the human body. Protective eye glasses, gloves, and a laboratory coat should be worn.*

3. Add 2 volumes of TE buffer to the gel slices and completely melt the gel in a 60 to 70°C water bath.

Note:

*The gel slices can be directly melted without adding TE buffer. The DNA concentration is usually higher, but the total yield of the DNA fragments is much lower than that if one adds TE buffer.*

4. Immediately chill the melted gel solution on dry ice or equivalent and leave the tube at -70°C for at least 20 min.
5. Thaw the gel mixture by vigorously tapping the tube. It takes 5 to 10 min to thaw the gel into a resuspension state.
6. Centrifuge at 12,000 g for 5 min at room temperature.
7. Carefully transfer the liquid phase containing the eluted DNA fragments into a fresh tube, which can be used directly for labeling except that the concentration is low.
8. Extract EtBr with 3 volumes of water-saturated *n*-butanol.
9. Precipitate the DNA by adding 0.1 volume of 3 M sodium acetate buffer (pH 5.2) and 2.5 volumes of chilled 100% ethanol to the DNA solution. Precipitate DNA at -70°C for 1 h and centrifuge at 12,000 g for 5 min at room temperature.
10. Discard the supernatant and briefly rinse the DNA pellet with 1 ml of 70% ethanol. Dry the DNA under vacuum for 15 min. The DNA can be dissolved in an appropriate volume of dd.H<sub>2</sub>O or TE buffer. Store at -20°C before use.

### 4.3.3 ELUTION OF DNA FRAGMENT USING NA45 DEAE MEMBRANE

1. Perform step 1 in Section 4.3.2 except that one uses 1% normal agarose.
2. Soak a piece of NA45 DEAE membrane (Scheicher and Schuell) in 10 mM EDTA buffer (pH 7.6) for 10 to 20 min at room temperature and in 0.5 N NaOH solution for 5 min. Wash the membrane with dd.H<sub>2</sub>O three to four times and store at 4°C before use.
3. During the electrophoresis, monitor the migration of the DNA bands stained with EtBr in the gel using a long-wavelength UV lamp. Turn off the power, make an incision in front of the DNA band of interest, and insert a piece of the prepared membrane into the incision in the gel.
4. Continue electrophoresis until the DNA fragments migrate onto the membrane by monitoring the migration of the stained band.
5. Remove the membrane strip from the gel and transfer it in a solution containing 20 mM Tris-HCl (pH 8.0), 0.15 M NaCl, and 0.1 mM EDTA. Rinse briefly the membrane to remove any agarose.
6. Transfer the strip into 0.2 to 0.3 ml of elution buffer containing 20 mM Tris-HCl (pH 8.0), 1 M NaCl, and 0.1 mM EDTA.
7. Incubate the strip at 55 to 68°C for 30 to 60 min with occasional agitation.
8. Briefly rinse the strip with 0.1 ml of elution buffer and extract EtBr with 3 volumes of water-saturated *n*-butanol.
9. Precipitate and dissolve the eluted DNA as described in Section 4.3.2.

### 4.3.4 ELUTION OF DNA FRAGMENTS IN AGAROSE GEL WELL

1. Carry out DNA electrophoresis as described in Section 4.3.2 except that one adds the running buffer up to the upper edges of the gel instead of covering the gel.
2. During electrophoresis, check the separation of DNA bands stained by EtBr in the gel using a long-wavelength UV lamp. Stop the electrophoresis and use a razor blade or a spatula to make a well in front of a specific band. Add 10 to 30  $\mu$ l of running buffer into the well.
3. Continue electrophoresis until the band migrates into the well by monitoring the band.
4. Stop electrophoresis and transfer the solution containing DNA of interest from the well to a fresh tube.
5. Extract EtBr with 3 volumes of water-saturated *n*-butanol, precipitate, and dissolve the DNA as described in Section 4.3.2.

## 4.4 LIGATION OF DNA FRAGMENTS

Once the digested vectors and insert DNA are ready, ligation can be carried out. To achieve an optimal ligation, the ratio of vector to insert DNA (1:1, 1:2, 1:3, and 3:1 molar ratios) should be optimized using a small-scale ligation. The following

reaction is standard for sticky ends ligation of a 3.2-kb plasmid vector and a 3.0-kb insert DNA.

1. Calculate the molar weights of vector and insert DNA:

$$1 \text{ M plasmid vector} = 3.2 \times 1000 \times 660 = 2.112 \times 10^6$$

$$1 \text{ M insert DNA} = 3 \times 1000 \times 660 = 1.98 \times 10^6$$

2. Calculate molar ratio of vector to insert DNA:

Vector DNA:Insert DNA	Amount of DNA	
	Vector	Insert
1:1	1 $\mu\text{g}$	0.792 $\mu\text{g}$
1:2	1 $\mu\text{g}$	1.584 $\mu\text{g}$
1:3	1 $\mu\text{g}$	2.376 $\mu\text{g}$
3:1	1 $\mu\text{g}$	0.264 $\mu\text{g}$

3. Set up the following ligation on ice:

Components	Ligation Reactions			
	1 (1:1)	2 (1:2)	3 (1:3)	4 (3:1)
Insert DNA	0.792 $\mu\text{g}$	1.584 $\mu\text{g}$	2.376 $\mu\text{g}$	0.244 $\mu\text{g}$
Vector DNA	1 $\mu\text{g}$	1 $\mu\text{g}$	1 $\mu\text{g}$	1 $\mu\text{g}$
10 $\times$ ligase buffer	1 $\mu\text{l}$	1 $\mu\text{l}$	1 $\mu\text{l}$	1 $\mu\text{l}$
T4 DNA ligase (Weiss units)	5 units	5 units	5 units	5 units
Add dd.H <sub>2</sub> O to	10 $\mu\text{l}$	10 $\mu\text{l}$	10 $\mu\text{l}$	10 $\mu\text{l}$

4. Incubate the reactions at 25°C or room temperature for 3 h sticky-end ligation, 16°C for 6 h to overnight, or 4°C 12 to 20 h for blunt-end ligation.
5. Determine the efficiency of the ligations by 1% agarose electrophoresis. When the electrophoresis is complete, take a picture of the gel stained with EtBr under UV light. As compared with unligated vector or insert DNA, high efficiency of ligation should visualize less than approximately 20% unligated vector and insert DNA by estimation of the intensity of fluorescence. Approximately 80% of the vector and insert DNA are ligated to each other and show strong band(s) with molecular weight shifts. By comparing the efficiency of ligations using different molar ratios, the optimal concentration of DNA can be used as a guide for large-scale ligation.
6. Carry out large-scale ligation of vector and insert DNA based on the optimal conditions determined by small-scale ligations. For example, if one




uses a 1:2 molar ratio of vector DNA/insert DNA as the optimal ligation condition, a large-scale ligation can be carried out as follows:

Vector DNA	3 $\mu$ g
Insert DNA	4.75 $\mu$ g
10 $\times$ ligase buffer	3 $\mu$ l
T4 DNA ligase (Weiss units)	15–50 units
<hr/>	
Add dd.H <sub>2</sub> O to a final volume of	30 $\mu$ l

Incubate the ligation as described in small-scale ligation. Proceed to transformation.

#### 4.5 SINGLE-STEP CLONING BY PCR

This strategy is particularly useful if there is no restriction enzyme site that can match both vector and insert DNA. Although the non-match sticky ends can be blunt ended followed by blunt-end ligation, the ligation efficiency will be extremely low, and so will be the efficiency of transformation. This is because blunt-end ligation is usually difficult to carry out, and that many of the ligated molecules are self-ligated. Therefore, a single-step cloning by polymerase chain reaction (PCR) can eliminate



**FIGURE 4.1** Diagram of single-step DNA cloning by PCR, transformation, selection, and verification of recombinant plasmid DNA by agarose gel electrophoresis.

this problem. There will be no ligase and ligation involved. The principles and procedures are outlined in Figure 4.1.

1. Design and synthesize a pair of forward (sense or upstream) primer and reverse (antisense or downstream) primer based on the known sequences at the cloning sites. Specifically, the forward primer is designed from 5'→3' direction and has approximately 36 to 43 bases that the first part of the primer (about 18- to 20-mer) matches the sequence at 3'-end of the first or (–)strand of vector DNA, and the rest of the sequence is the same as that of 5'-end of the first or (–)strand of insert DNA. On the other hand, a reverse primer is also designed from 5'→3' direction but its first part is the same as the sequence at the 3'-end sequence of the second or (+)strand of the vector DNA. The rest of the base sequence is the same as that of 5'-end of the second or (+)strand of the insert DNA.

2. Perform simultaneous amplification and ligation by PCR.

- (i) Prepare the following mixture in a 0.5-ml microcentrifuge tube on ice:

Forward primer (36- to 43-mer, 10–30 ng/μl)	5–8 pmol (30–40 ng) depending on the size of primer
Reverse primer (36- to 43-mer, 10–30 ng/μl)	5–8 pmol (30–40 ng) depending on the size of primer
DNA template (vector or insert) (0.4–7 kb, 10–100 ng/μl)	100–1000 ng depending on the size of the template
10× amplification buffer	4 μl
dNTPs (2.5 mM each)	4 μl
<u>Taq or Tth DNA polymerase</u>	<u>5–10 units</u>
Add dd.H <sub>2</sub> O to a final volume of	40 μl

Note: *The DNA polymerase should be high fidelity and long expand, which is commercially available.*

- (ii) Overlay the mixture in each tube with approximately 30 μl of mineral oil to prevent evaporation of the samples during the PCR amplification. Place the tubes in a thermal cycler and perform PCR.

Profile	Predenaturation	Cycling (4–12 Cycles)			Last
		Denaturation	Annealing	Extension	
Template (<4 kb) Primer is <24 bases or with <40% G-C content	94°C, 3 min	94°C, 1 min	60°C, 1 min	70°C, 1.5 min	4°C
Template is >4 kb Primer is >24-mer or <24 bases with >50% G-C content	95°C, 3 min	5°C, 1 min	60°C, 1 min	72°C, 2 min	4°C

3. When the PCR is complete, perform transformation of appropriate bacterial strain using 2 to 10  $\mu\text{l}$  of the amplified mixture as described above.
4. Selection and verification of recombinant plasmid DNA as described above.


## 4.6 TRANSFORMATION OF LIGATED DNA INTO BACTERIA

### 4.6.1 PROTOCOL 1. PREPARATION OF COMPETENT CELLS FOR TRANSFORMATION

#### 4.6.1.1 Competent Cells for $\text{CaCl}_2$ Transformation before Ligation

1. Prepare Luria–Bertani (LB) medium and LB plates. This should be done 2 to 3 days before ligation.
2. Streak an appropriate *E. coli* strain (DH5 $\alpha$ F', Top 10, or JM109) directly from small amount of frozen stock stored at  $-80^\circ\text{C}$  onto the surface of an LB plate in a “zigzag” pattern (Figure 4.2) using a sterile platinum wire loop. Invert the plate and incubate at  $37^\circ\text{C}$  for 12 to 16 h. Bacterial colonies will be formed. Note: *It is not necessary to completely thaw frozen bacteria at room temperature or at  $0^\circ\text{C}$ . A tiny bit of bacteria adhering to the wire loop is sufficient for inoculation.*
3. Inoculate a well-isolated colony from the plate at step 2 into 5 ml of LB medium. Incubate at  $37^\circ\text{C}$  overnight with shaking at 160 rev/min.
4. Add 0.5 ml of cells from step 3 to 100 ml of LB medium. Incubate at  $37^\circ\text{C}$  with shaking at 160 rev/min. Four hours later, take 1 ml of the culture and measure the  $\text{OD}_{600}$  or  $A_{600}$  every 20 to 30 min until the  $A_{600}$  reaches 0.5 to 0.6. This usually takes 5 to 8 h.

Tip: *Never allow bacteria to overgrow. If the density is higher than 0.65, the culture is too dense and transformation efficiency will be low.*



**FIGURE 4.2** Streaking of bacterial stock in a “zigzag” pattern on a Luria–Bertani (LB) plate. Fourteen hours later, well-isolated bacterial colonies will be generated in the last streaking area in the plate.

5. Chill the cells on ice for 20 min and centrifuge at 5000 g for 5 min at 4°C. Aspirate the medium.
6. Resuspend the cells in half of the original culture volume of sterile-filtered 0.1 M CaCl<sub>2</sub> (50 ml) on ice.
7. Incubate the cells on ice for 45 to 60 min.
8. Centrifuge at 5000 g for 10 min at 4°C and gently resuspend the cells in 20 ml (1/20 original volume) of ice-cold 0.1 M CaCl<sub>2</sub> solution.
9. Add sterile glycerol dropwise with gentle swirling to the cell solution to a final concentration of 15% (v/v). Aliquot the cells at 0.2 ml/tube, freeze and store at -80°C until use.
10. Take one aliquot to test the efficiency of transformation.

#### 4.6.1.2 Preparation of Competent Cells for Electroporation

1. Carry out steps 1 to 4 in Section 4.6.1.1.
2. Extensively wash the cells with 100 ml distilled water or low-salt buffer in order to reduce the ionic strength of the cell suspension.
3. Centrifuge at 5000 g for 10 min at 4°C and carefully decant the supernatant.
4. Repeat steps 2 to 3 twice.
5. Resuspend the cells in 20 ml of low-salt buffer or distilled water. Add glycerol dropwise with gentle swirling to 10% (v/v). Aliquot the cells at 0.2 ml/tube, freeze and store at -80°C until use.

#### Reagents needed

- *LB medium (per liter)*  
10 g Bacto-tryptone  
5 g Bacto-yeast extract  
5 g NaCl  
Adjust to pH 7.5 with 0.2 N NaOH and autoclave
- *LB plates*  
Add 15 g of Bacto-agar to 1 l of freshly prepared LB medium and autoclave. Allow the mixture to cool to about 55°C and add appropriate amount of antibiotic stock. Pour 25 to 30 ml of the mixture into each 100-mm Petri dishes in a sterile laminar flow hood with filtered air flowing. Remove any bubbles with a pipette tip and let the plates cool for 5 min before they are covered. Allow the agar to harden for 2 h and partially dry at room temperature for a couple of days. Store the plates at room temperature for up to 10 days or at 4°C in a bag for 1 month. Allow the cold plates to warm up at room temperature for 1 to 2 h before use.

#### 4.6.2 PROTOCOL 2. TRANSFORMATION OF CELLS BY CaCl<sub>2</sub> METHOD

1. Thaw an aliquot of 0.2 ml of frozen CaCl<sub>2</sub>-treated competent cells on ice.
2. Assembly transformation as follows:

Components	Tube # 1	Tube # 2	Tube # 3
Cells	50 $\mu$ l	50 $\mu$ l	50 $\mu$ l
DNA	50 ng in 5 $\mu$ l	200 ng in 5 $\mu$ l	500 ng in 5 $\mu$ l

Tip: Fifteen to twenty microliters of ligated mixture can be directly added into 50 to 60  $\mu$ l of competent cells.

3. Incubate on ice for 50 to 60 min.
4. Heat shock at 42°C for 1 to 1.5 min and quickly place the tubes on ice for 1 min.  
Tip: Heat shock and chilling on ice should not exceed the time indicated. Otherwise, the efficiency of transformation will decrease by 10- to 20-fold.
5. Transfer the cell suspension to sterile culture tubes containing 1 ml of LB medium without antibiotics. Incubate at 37°C for 1 to 2 h with shaking at 140 rev/min to recover the cells.
6. Transfer 50 to 150  $\mu$ l of the cultured cells per plate onto the center of LB plates containing 50  $\mu$ g/ml ampicillin (or 0.5 mM IPTG and 40  $\mu$ g/ml X-Gal for color selection). Immediately spread the cells over the entire surface of the LB plates using a sterile, bent glass rod.
7. Invert the plates and incubate at 37°C overnight. Selected colonies should be visible 14 h later.

#### 4.6.3 PROTOCOL 3. TRANSFORMATION BY ELECTROPORATION

1. Thaw an aliquot of 200  $\mu$ l of frozen, non-CaCl<sub>2</sub>-treated competent cells on ice.
2. Chill three disposable microelectroporation chambers (BRL) on ice.
3. Connect the power cable to a BRL-Porator pulse control + power supply apparatus, to BRL-Porator Voltage Booster, and between these two units.
4. Set a "pulse control" as follows:
 

Power:	Charge
Capacitance ( $\mu$ F):	330
High Ohm/low Ohm:	Low Ohm
Charge rate:	Fast

 Set up the "Voltage Booster" at 4 kV for *E. coli*.
5. Add ice water to "the chamber safe" up to 4/5 of the volume, and place "the chamber rack" in the chamber safe.
6. Thaw three aliquots (A, B, C) of 20  $\mu$ l of competent cells on ice. To aliquot A, add 3  $\mu$ l of DNA solution containing 1  $\mu$ g DNA. To aliquot B, add 3  $\mu$ l of DNA solution containing 2  $\mu$ g DNA. To aliquot C, add 3  $\mu$ l of DNA solution containing 4  $\mu$ g DNA. Gently mix and place on ice until use.  
Note: Try to avoid any air bubbles during mixing. The total volume of the transformation mixture should be  $\leq$ 25  $\mu$ l.

7. Use a pipette tip to transfer one aliquot and carefully place the mixture drop between the electrode poles in the microelectroporation chamber. Carefully cover the chamber.  
Note: *The liquid should not drop to the bottom of the chamber.*
8. Gently place the chamber into the cell in the safe-rack, cover the chamber, and turn the electric-shock pointer toward the cell containing the transformation chamber.
9. Connect the power from the “Voltage Booster” to the chamber safe, and turn on power for the “pulse control” and the “voltage booster.”
10. Press “charge button on the pulse control” up to 365. When the DC voltage drops down to 345 to 350 V, turn the button from “charge” to “arm.” Quickly push the “trigger” button for 1 to 2 s. The voltage goes down to <10 and kV number in the “voltage booster” should be 1.9 to 2.0.
11. Turn off the power and gently remove the chamber from the cell.  
Note: *The transformed cell suspension should still be between the positive and negative electrode poles. If the liquid drops to the bottom, this is not a good sign.*
12. Quickly transfer the transformed cell suspension into a test tube containing 0.5 ml LB medium without ampicillin as the cells are quite weak. Mix well and place at room temperature for not longer than 15 min.
13. Repeat above steps until all the samples are transformed.
14. Incubate at 37°C for 1 to 2 h with shaking at 150 rev/min to recover the cells.
15. Use a sterile, bent glass rod to spread 20, 50, 100, and 200  $\mu$ l of each of the three transformant cells over the entire surface of LB plates containing 50  $\mu$ g/ml ampicillin.
16. Invert all the plates prepared and incubate at 37°C for 12 to 16 h until colonies are visible.

## 4.7 ISOLATION AND PURIFICATION OF PLASMID DNA BY ALKALINE METHOD

### 4.7.1 PROTOCOL 1. MINIPREPARATION OF PLASMID DNA

Plasmids can be purified using the CsCl gradient method or miniprep method. Although we have found that the CsCl gradient method yields excellent results, it is time consuming and relatively expensive. The miniprep method, on the other hand, is simple, cheaper, and gives excellent sequencing results. The isolated DNA is suitable for restriction enzyme digestion, *in vitro* transcription, DNA subcloning, and DNA sequencing.

1. Inoculate a single colony or 10  $\mu$ l of previously frozen bacteria containing the plasmid DNA of interest in 5 ml LB medium and 50  $\mu$ g/ml of appropriate antibiotics (e.g., ampicillin), depending on the specific antibiotic-resistant gene carried by the specific plasmid. Culture the bacteria at 37°C overnight with shaking at 200 rev/min.
2. Transfer the overnight culture into microcentrifuge tubes (1.5 ml/tube) and centrifuge at 6000 rev/min for 4 min. Carefully aspirate the supernatant.

Note: *If the plasmid carried by bacteria is a high-copy number plasmid, 1.5 ml cell culture usually gives a yield of approximately 40 µg plasmid DNA using the present method. In this way, 10 tubes of preparation can generate about 400 µg plasmid DNA, which is equivalent to a large-scale preparation. Therefore, the volume of bacterial culture used for purification of plasmid DNA depends on a particular experiment.*

3. Add 0.1 ml of ice-cold lysis buffer to each tube and gently vortex for 1 min. Incubate at room temperature for 5 min.

Note: *The function of this step is to lyse the bacteria by hyperlytic osmosis, releasing DNA and other contents.*

4. Add 0.2 ml of a freshly prepared alkaline solution to each tube and mix by inversion. **Never vortex.** Place the tubes on ice for 5 min.

Note: *This step denatures chromosomal DNA and proteins.*

5. Add 0.15 ml of ice-cold potassium acetate solution to each tube. Mix by inversion for 10 s and incubate on ice for 5 min.

Note: *The purpose of this step is to selectively precipitate proteins, polysaccharides, and genomic DNA. Under these particular buffer conditions, plasmid DNA remains in the supernatant without being precipitated.*

6. Centrifuge at 12,000 g for 5 min and *carefully* transfer the supernatant to fresh tubes.

7. To degrade total RNAs from the sample, add RNase (DNase-free, Boehringer Mannheim) into the supernatant to at 1.5 µl/10 µl supernatant. Incubate the tubes at 37°C for 30 min.

Tips: *At this point, RNase and other remaining proteins can be removed by using either option A or option B. Option A is faster, cheaper, and more efficient than option B.*

- Option A: filtration using Probind filters (Millipore)

Transfer the RNase-treated supernatant into a minifilter cup (0.4 ml/cup) placed in an Eppendorf tube. Cap the tube and centrifuge at 12,000 g for 30 s. Remove the filter cup, and the collected supernatant in the Eppendorf tube is ready for DNA precipitation. Proceed to step 8.

Note: *The membrane filter at the bottom of the cup is specially designed to retain proteins and allow nucleic acids to pass through. One cup can be reused four to five times if one uses it for the same supernatant pool. However, it is not a wise idea to reuse it for different plasmid samples because of potential contamination. The author routinely utilizes this type of filter for plasmid DNA preparation. DNA obtained is pure and high yield with a  $A_{260}/A_{280}$  ratio of approximately 2.0.*

- Option B: phenol/chloroform extraction

- (a) Add an equal volume of TE-saturated phenol/chloroform to each tube and mix by vortexing for 1 min.
- (b) Centrifuge at 12,000 g for 5 min and transfer the upper, aqueous phase into fresh tubes.
- (c) Add an equal volume of chloroform/isoamyl alcohol (24:1) and mix by vortexing for 1 min and centrifuge as in step b.

- (d) Centrifuge at 12,000 *g* for 5 min and transfer the supernatant to fresh tubes. Proceed to step 8.
8. Add 2 to 2.5 volumes of 100% ethanol to each tube. Mix by inversion and allow the plasmid DNA to precipitate for 10 min at  $-80^{\circ}\text{C}$  or 30 min at  $-20^{\circ}\text{C}$ .
  9. Centrifuge at 12,000 *g* for 10 min. Carefully decant the supernatant, add 1 ml of prechilled 70% ethanol and centrifuge at 12,000 *g* for 5 min. Carefully aspirate the ethanol and dry the plasmid DNA in under vacuum for 15 min.
  10. Dissolve the plasmid DNA in 15  $\mu\text{l}$  of TE buffer or sterile deionized water. Take 1  $\mu\text{l}$  to measure the concentration and store the sample at  $-20^{\circ}\text{C}$  until use.

### Reagents needed

- *LB medium (per liter)*
  - 10 g Bacto-tryptone
  - 5 g Bacto-yeast extract
  - 5 g NaClAdjust pH to 7.5 with 2 N NaOH and autoclave. If needed, add antibiotics after the autoclaved solution has cooled to less than  $50^{\circ}\text{C}$ .
- *TE buffer*
  - 10 mM Tris-HCl, pH 8.0
  - 1 mM EDTA
- *Lysis buffer*
  - 25 mM Tris-HCl, pH 8.0
  - 10 mM EDTA
  - 50 mM glucose
- *Alkaline solution*
  - 0.2 N NaOH
  - 1% SDS
- *Potassium acetate solution (pH 4.8)*
  - Prepare 60 ml of 5 M potassium acetate. Add 11.5 ml of glacial acetic acid and 28.5 ml of  $\text{H}_2\text{O}$  to total volume of 100 ml. This solution is 3 M with respect to potassium and 5 M with respect to acetate. Store on ice before use.
- *RNase (DNase-free)*
  - Boehringer Mannheim, Cat. No: 119915, 500  $\mu\text{g/ml}$ .
- *TE-saturated phenol/chloroform*
  - Thaw crystals of phenol in  $65^{\circ}\text{C}$  water bath with occasional shaking. Mix equal parts of TE buffer and thawed phenol. Let it stand until the phases separate at room temperature. Mix an equal part of the lower, phenol phase with an equal part of chloroform/isoamyl alcohol (24:1).
- Chloroform/isoamyl alcohol (24:1)
- Ethanol: 100% and 70%



#### 4.7.2 PROTOCOL 2. LARGE-SCALE PREPARATION OF PLASMID DNA

The principles are the same as in the minipreparation method.

1. Inoculate a single colony or 50  $\mu$ l of previously frozen cells in 100 ml of LB medium containing 50  $\mu$ g/ml of appropriate antibiotics (e.g., ampicillin). Grow the bacteria at 37°C overnight with shaking at 160 rev/min.  
*Note: The volume of culture can be scaled up, depending on particular experiments, to a few liters and culture for 16 h with shaking at 240 rev/min.*
2. Centrifuge at 6000 g for 5 min at 4°C and completely aspirate the liquid.
3. Resuspend the pellet in an appropriate volume (1 ml/15 ml cell culture) of ice-cold lysis buffer and vortex for 2 min. Incubate the tubes for 5 to 10 min at room temperature.
4. Add an appropriate volume (2 ml/15 ml cell culture) of a freshly prepared alkaline denaturation solution and mix by inversion. Incubate the tubes on ice for 5 to 10 min.
5. Add an appropriate volume (1.5 ml/15 ml cell culture) of ice-cold potassium acetate solution, mix by inversion for 20 s and incubate on ice for 5 to 10 min.
6. Centrifuge at 12,000 g for 8 min at 4°C and *gently* transfer the supernatant to a fresh tube.
7. To degrade total RNAs from the sample, add RNase (DNase-free, Boehringer Mannheim) into the supernatant to at 10  $\mu$ l/ml supernatant. Incubate the tubes at 37°C for 30 to 50 min.

*Tips: At this point, RNase and other remaining proteins can be removed by the following two options.*

- Option A: filtration using Probind filters (Millipore)
  - (a) Add 2 to 2.5 volumes of 100% ethanol to the supernatant. Mix by inversion and allow the plasmid DNA to precipitate for 10 min at -80°C or 20 min at -20°C.
  - (b) Centrifuge at 12,000 g for 10 min. Carefully decant the supernatant and dry the plasmid DNA under vacuum for 10 min.
  - (c) Dissolve the plasmid DNA in 0.8 ml of TE buffer or sterile deionized water.

*Tip: The DNA sample contains RNase and other proteins, which can be readily removed by filtration. The volume (0.8 ml) is suitable for minifiltration using Probind-filter from Millipore.*

- (d) Transfer the DNA solution into a minifilter cup (0.4 ml/cup) placed in an Eppendorf tube. Cap the tube and centrifuge at 12,000 g for 40 s. Remove the filter cup and the supernatant collected in the Eppendorf tube is ready for DNA precipitation. Proceed to step 8.

*Note: The membrane filter fixed at the bottom of the cup is specially designed to retain proteins and allow nucleic acids to pass through. One cup can be reused for four to five times if one uses it for the same supernatant pool. However, it is not a wise idea to reuse it for*

*different plasmid samples because of potential contamination. The author routinely utilizes this type of filter for plasmid DNA preparation. DNA obtained is pure and high yield with a  $A_{260}/A_{280}$  ratio of approximately 2.0.*

- Option B: phenol/chloroform extraction  
Detailed protocol is described above

#### 4.7.3 PROTOCOL 3. PURIFICATION OF PLASMID DNA BY CsCl GRADIENT

This method, as compared with the protocol described above, is relatively complicated, time consuming, and costly. It usually needs a large-scale culture of bacteria. However, many investigators comment that the plasmid DNA purified by CsCl is pure and may be more suitable for DNA sequencing.

1. Inoculate a single colony or 50  $\mu$ l of previously frozen cells in 100 ml of LB medium containing 50  $\mu$ g/ml of appropriate antibiotics (e.g., ampicillin). Grow the bacteria at 37°C overnight with shaking at 160 rev/min.  
Note: *The volume of culture can be scaled up, depending on particular experiments, to a few liters and culture for 16 h with shaking at 240 rev/min.*
2. Centrifuge at 6000 g for 5 min at 4°C and completely aspirate the liquid.
3. Resuspend the pellet in an appropriate volume (1 ml/15 ml cell culture) of ice-cold lysis buffer and vortex for 2 min. Incubate the tubes for 5 to 10 min at room temperature.
4. Add an appropriate volume (2 ml/15 ml cell culture) of a freshly prepared alkaline denaturation solution and mix by inversion. Incubate the tubes on ice for 5 to 10 min.
5. Add an appropriate volume (1.5 ml/15 ml cell culture) of ice-cold potassium acetate solution, mix by inversion for 20 s, and incubate on ice for 5 to 10 min.
6. Centrifuge at 12,000 g for 8 min at 4°C and *gently* transfer the supernatant to a fresh tube.
7. Add 0.8 volumes of isopropanol to the supernatant, mix well, and allow the sample to precipitate for 15 min at room temperature.
8. Centrifuge at 12,000 g for 10 min at 4°C, aspirate the supernatant, and gently rinse the pellet with 6 ml of prechilled 70% ethanol. Dry the DNA under vacuum for 20 min.
9. Dissolve the DNA in 4 ml of TE buffer or sterile deionized water. Store at 4°C until use for CsCl gradient centrifugation.
10. Accurately measure the volume of the DNA sample and add 1 g/ml of solid CsCl. Warm the mixture at 30°C to dissolve the CsCl and gently mix well.
11. Add 0.35 ml of 10 mg/ml of ethidium bromide (EB) per 5 ml of the DNA/CsCl solution. Quickly and gently mix the solution.

*Caution: Ethidium bromide is a powerful mutagen; gloves should always be worn when working with the solutions. The used EtBr solution must be collected in a special container to gradually inactivate the chemical before*


*it is disposed under specific regulation. Stock solutions of EtBr should be stored in light-tight bottle at 4°C.*

12. Centrifuge at 8000 rev/min for 6 min at room temperature with a Sorvall SS34 rotor (or its equivalent).
13. Gently transfer the clear, reddish DNA–CsCl solution under the surface scum into “Quick-seal” ultracentrifuge tubes (Beckman) using a Pasteur pipette or a disposable syringe fitted with a large-gauge needle.  
*Tip: Fill the tubes right up to the neck of the tube, which is about 5.2 ml/tube. If the tube is overfilled, it will cause a problem when sealing the tube. On the other hand, if the tube is underfilled, large air bubbles may present after sealing the tube and may cause the tube to collapse. Carefully balance the tubes using CsCl balance solution.*
14. Turn on and warm the sealing machine for 5 min and place the tubes on a metal sealing plate. Cover each tube with an appropriate metal cap and place each tube, one at a time, right under the sealing rack. Push and hold the hot rack against the metal cap of the tube for 30 to 60 s. The neck of the tube will gradually melt until a sound is heard from the sealing machine. Immediately remove the tube from the melt rack and place the cap of the tube against a cold metal strip. Press and hold the strip against the cap for about 1 to 2 min to completely seal the tube and then take out the cap.
15. Attach a cap and a metal adapter to each sealed tube for ultracentrifugation and carefully balance again with a piece of Scotch tape if necessary. Symmetrically place the tubes into the Beckman vertical rotor and make sure to cover the tubes with their own caps and adapters.
16. Carry out centrifugation of the CsCl density gradients at 45,000 rev/min for 16 h (VTi65), 45,000 rev/min for 48 h (Ti50), 60,000 rev/min for 24 h (Ti65), or 60,000 rev/min for 24 h (Ti70.1) at 20°C.  
*Note: Never centrifuge at 4°C for this will cause the CsCl to precipitate out of solution, reducing the density of CsCl in the gradient.*
17. Stop centrifugation and slowly take out the tubes from the rotor and place them in a plastic rack. Use long-wavelength UV light (360 nm) to visualize the relaxed and supercoiled DNA bands.  
*Tips: Two bands of DNA are visible in the center of the gradient, which usually contains linear bacterial chromosomal DNA and nicked circular plasmid DNA. The lower band consists of circular plasmid DNA. The deep-red pellet on the bottom of the tube is ethidium bromide/RNA. The materials on the top surface are proteins.*
18. To remove the DNA, place the tube in a ringstand rack. Locate the DNA bands using 360 nm UV light. Wipe dry one side of the DNA band area using ethanol and place a piece of Scotch tape on the area. Carefully puncture through the tube with a needle and syringe (16- to 20-gauge) until the needle has penetrated into the closed circular plasmid DNA band area. Slowly withdraw a minimal volume of DNA sample and then remove the needle. Transfer the sample into a fresh tube. Discard the tubes containing the rest of the solution in a special container for disposal.

19. Extract ethidium bromide from the DNA sample by adding 1 volume of isopropanol. Gently invert the tube and allow the phases to separate by gravity. The EtBr usually partitions into the upper propanol phase and can be removed with a pipette. The lower aqueous phase contains DNA–CsCl with some EtBr, which should be reextracted for four to five times until no pink color is visible.
20. Transfer the lower phase into a fresh Corex tube and dilute the CsCl with 2 volumes of TE buffer. Add 2 volumes of chilled 100% ethanol into the diluted sample and precipitate the DNA at  $-20^{\circ}\text{C}$  for 2 h to overnight.  
Note: *Never place the tubes at  $-80^{\circ}\text{C}$  because this will cause the CsCl to precipitate.*
21. Centrifuge at 12,000 *g* for 15 min at  $4^{\circ}\text{C}$  and dry the DNA pellet under vacuum for 15 min. Resuspend the DNA in 100 to 200  $\mu\text{l}$  of TE buffer.
22. Repeat step 19 to further extract CsCl.
23. Centrifuge at 12,000 *g* for 15 min at  $4^{\circ}\text{C}$  and dry the DNA pellet under vacuum for 15 min. Resuspend the DNA in 100 to 200  $\mu\text{l}$  of TE buffer. Store the sample at  $-20^{\circ}\text{C}$  until use.

#### 4.8 VERIFICATION OF DNA INSERTION BY RESTRICTION ENZYME DIGESTION AND AGAROSE GEL ELECTROPHORESIS

This is a mandatory step to ascertain whether the insert DNA is cloned at the right site in the vector. Detail protocols for restriction enzyme digestion and agarose gel electrophoresis are given above. This section mainly focuses on analysis of restriction enzyme digestion pattern. For example, if a cDNA of interest is cloned between



**FIGURE 4.3** Diagram of DNA ligation, transformation, selection, and verification of recombinant plasmid DNA by agarose gel electrophoresis.

*NotI* and *XhoI* sites at the MCS of vector Bluescript SK(+), assuming that *NotI* and *XhoI* are unique in vector and insert. As shown in Figure 4.3, after ligation and transformation, plasmid DNA is isolated from selected colonies. After digestion of the plasmid DNA with the same restriction enzymes, *NotI* and *XhoI*, electrophoresis will be carried out. If all goes well, the pattern of DNA bands should be as expected, that is, two bands are the same sizes as the insert and vector used for ligation. If the insert size or vector size does not match the original size, it is likely that mutation may have occurred during ligation and/or transformation. In this case, the best way to solve the problem is to forget about the colony and start it all over again.

#### 4.9 VERIFICATION OF INSERTION SITE BY DNA SEQUENCING

The detailed protocols for DNA sequencing are described in Chapter 5. The major purpose of doing this is to design primers that can be used to specifically sequence the ligation sites to ensure that the sequence at the insertion site is not altered, including potential base missing, base addition, or base substitution.

##### Troubleshooting Guide

1. *After restriction enzyme digestion and electrophoresis, the number of bands are as expected but the sizes of one or more bands are not.* This is most likely due to inaccurate information on restriction enzyme sites in vector or insert DNA. Try to be careful in analyzing the restriction enzyme map, cutting site, and sizes of DNA fragments.
2. *Many unexpected bands show up after a single restriction enzyme digestion of vector or insert DNA.* It seems that the conditions set up for restriction enzyme digestion are not appropriate. As a result, the enzyme activity is not specific, but rather randomly cut DNA into pieces. Make sure that the reagents and temperature are optimal for the enzyme.
3. *Compared with undigested DNA, incomplete restriction enzyme digestion occurs.* The solution is to slightly increase the units of restriction enzyme(s) or increase digestion time for 1 more hour. In addition, try to use fresh enzyme.
4. *No colonies are observed after antibiotic selection.* This is a complicated situation. Most likely, no ligation occurred between vector and insert DNA. All the DNA molecules transformed into bacteria are linear DNA that are degraded rapidly in bacteria. Or, extremely high concentration of antibiotics such as ampicillin may be used in LB plates, which will kill all the bacteria including transformants. Try to increase the efficiency of ligation and make sure that an appropriate antibiotic is utilized in the LB plates.
5. *Large percentage of colonies are due to self-ligation.* This is a common problem when ligation occurs between single restriction enzyme digested vector and insert DNA. One effective solution is to increase the units of alkaline phosphatase to remove the 5' phosphate group from vector before being ligated with insert DNA. Whenever possible, try to choose two unique enzymes that can generate two incompatible sticky ends to eliminate self-ligation.

6. *The size and/or pattern of digested DNA do not match those of vector and insert used for ligation.* This may be due to mutation that occurred during transformation or replication of plasmid DNA in bacteria. If this happens, there is no effective way to solve the problem except for eliminating the bacterial colonies.

## REFERENCES

1. Wu, W., and M. J. Welsh. 1995. A method for purification of DNA species from agarose gels by high speed centrifugation. *Analytical Biochemistry* 229: 350–352.
2. Sambrook, J., E. F. Fritsch, and T. Maniatis. 1989. *Molecular Cloning: A Laboratory Manual*. Cold Spring Harbor, NY: Cold Spring Harbor University Press.
3. Wu, W. 1995. Gene transfer and expression in animals. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke. Boca Raton, FL: CRC Press.

---

# 5 Nonisotopic and Isotopic DNA or RNA Sequencing

## 5.1 INTRODUCTION

DNA and RNA sequencing is an essential technique mandated for DNA cloning, characterization, mutagenesis, DNA recombination, and gene expression.<sup>1-3</sup> Very recently, nucleic acid sequencing has become a rapid and powerful tool to identify novel gene(s) targeted by a novel drug or protein. To find out new target molecules, one may not need to use traditional gene or cDNA cloning methodologies; nor is the isolated gene or cDNA needed to be completely sequenced. Instead, as long as a portion of exon sequences is sequenced, a potentially novel DNA molecule can be identified by computer database searching. Nevertheless, nucleic acid sequencing is a crucial tool for one to fulfill such a task. How does one sequence the DNA of interest? How does one identify the existence of mRNA expression in a cell- or tissue-type of interest? Which methodology is the best selection for your purposes? This chapter summarizes the author's extensive experience and will help you achieve your goals.

Although automatic DNA and RNA sequencing services are commercially available, this chapter provides methods to researchers who are interested in their own hands-on experience. There are several well-established methods for nucleic acid sequencing. Based on the author's years of hands-on sequencing experience, this chapter describes in detail the protocols for DNA or RNA sequencing by either nonisotopic or isotopic sequencing approaches. Specific methodologies include nonisotopic and isotopic DNA sequencing by dideoxynucleotides chain termination,<sup>2,3</sup> formamide gel sequencing,<sup>3,4</sup> primer walking,<sup>5</sup> unidirectional deletions,<sup>6</sup> direct sequencing by polymerase chain reaction (PCR), and RNA sequencing<sup>2,7-9</sup> with modifications. These methods have been successfully employed in our laboratories. Automatic fluorescent sequencing is a very attractive methodology. However, because of the high cost of the DNA Sequencer, we do not consider this method to be within the scope of the present chapter, which is designed for regular nucleic acid sequencing in modestly equipped laboratories.

Since Sanger et al.<sup>2</sup> developed the dideoxynucleotides chain termination method of DNA sequencing, it has been extensively modified by the use of some superior enzymes and DNA cloning vectors. The general principles of the method include: (1) a synthesized oligonucleotide primer anneals to the 3'-end of the DNA template to be sequenced; (2) a DNA polymerase catalyzes the *in vitro* synthesis (5'→3') of a new DNA strand that is complementary to the template, starting from the primer site, using deoxynucleoside 5'-triphosphates (dNTPs). One of the dNTPs is either biotinylated dATP or dCTP used for nonisotopic sequencing, or  $\alpha$ -<sup>35</sup>SdATP or  $\alpha$ -<sup>35</sup>SdCTP

utilized for isotopic sequencing; and (3) after the synthesis of the new DNA strand, it is terminated by the incorporation of a nucleotide analog that is an appropriate 2',3'-dideoxynucleotide 5'-triphosphate (ddNTP). All four ddNTPs lack the 3'-OH group, which is required for DNA chain elongation. Based on the nucleotide bases of the DNA template, one of the four ddNTPs in each reaction is incorporated. The enzyme-catalyzed polymerization will then be stopped at each site where a ddNTP is incorporated, generating a population of chains of different sizes. Therefore, by setting up four separate reactions, each with a different ddNTP, complete nucleotide sequence information of the DNA strand will be revealed.

In DNA or RNA sequencing, different factors and strategies should be considered. The following factors greatly influence nucleic acid sequencing.

1. *Quality of template.* The purity and integrity of DNA or RNA to be sequenced are essential for obtaining an accurate and complete nucleotide sequence. Make sure that the DNA or RNA template is not degraded before sequencing. The DNA template can be single-stranded DNA (ssDNA) from M13 cloning vectors, double-stranded plasmid DNA or double-stranded bacteriophage DNA with appropriate pretreatment. An mRNA template is usually transcribed into cDNA followed by standard DNA sequencing.
2. *DNA polymerase.* United States Biochemical (USB) and Amersham Life Science produce excellent DNA polymerase for nucleic acid sequencing. These include Sequenase Version 2.0 DNA polymerase and AMV reverse transcriptase, which are routinely used in our laboratory with successful results. Sequenase Version 2.0 DNA polymerase is a superior enzyme that has no 3'→5' exonuclease activity. These enzymes should be kept at -20°C before use.
3. *Primers.* For sequencing the region of the DNA template close to the cloning site of the vector, the primers are complementary to the vector DNA strand(s) and are commercially available. For the sequence beyond 250 to 500 nucleotides from the cloning site, new primers should be designed based on the nucleotide sequence information obtained from the very last sequencing. The quality of primers is critical for the success of DNA or RNA sequencing. Primers can be designed using computer programs such as Oligo Version 4.0 or CPrimer f. We routinely check with the T<sub>m</sub> value, potential intrahairpin structures, potential interloop formation, and GC contents of the designed primers before employing them in sequencing.
4. *Nonisotopic or isotopic dNTP.* Biotinylated dATP or dCTP is commonly used for nonisotopic DNA or RNA sequencing. The drawback is potential background due to the high sensitivity. Nonetheless, the nonisotopic approach is faster and safer compared to radioactive sequencing. In the near future, traditional isotopic methods may be completely replaced by nonisotopic methodology. <sup>32</sup>P-labeled dNTP (dATP or dCTP) has a high energy level and a short half-life (usually 14 days). A major disadvantage of using <sup>32</sup>P is that it gives diffuse bands on autoradiographic x-ray film, limiting readable information of DNA sequences. However, [<sup>32</sup>S]dATP has a lower energy level and a longer half-life (usually 84 to 90 days). It greatly



improves autoradiographic resolution. Therefore, [<sup>32</sup>S]dATP is recommended for isotopic DNA or RNA sequencing. The activity and amount of labeled nucleotide plays a significant role in nucleic acid sequencing.

5. *Compressions.* Compressions represent a common problem in DNA sequencing, which is primarily due to dG–dC rich regions that may not be fully denatured during electrophoresis. As a result, interruption of the normal pattern of migration of DNA fragments becomes obvious. The bands are usually spaced closer than usual (compressed together) or occur further apart than usual, resulting in a significant loss of sequence information. In order to solve this problem, we use dITP or 7-deaza-dGTP (USB) to replace the nucleotide dGTP, which forms a weaker secondary structure that can be readily denatured during electrophoresis. In addition, a formamide gel is helpful in this compression situation. With these modifications, we have found that bands are sharper and compressions were eliminated by the use of dITP and formamide. In some cases, some bands appear weak using both dGTP and dITP. This limitation can be eliminated using pyrophosphatase (USB) in the presence of Mg<sup>2+</sup>, Mn<sup>2+</sup>, or both. The manganese can allow one to obtain sequence information close to the primer site.

## 5.2 NONISOTOPIC DNA SEQUENCING METHOD

The following protocols are adapted from Sanger et al.,<sup>2</sup> Sequenase Images<sup>TM</sup> nonisotopic sequencing (USB) and Sequenase Version 2.0 (USB) with some modifications.

### 5.2.1 PROTOCOL 1. PREPARATION OF DNA TEMPLATES FOR SEQUENCING

#### 5.2.1.1 Purification of Double-Stranded Plasmid DNA Using the Alkaline Method

After denaturation, double-stranded plasmids containing DNA inserts of interest can be directly sequenced. One can simultaneously sequence both strands of the DNA insert at opposite directions using forward or reverse primers. The primers are annealed to the appropriate sites at their 3' ends of the DNA insert, in two separate sequencing reactions. This simultaneous sequencing approach can speed up the sequencing procedure. It is especially useful for sequencing large DNA fragments. Double-stranded plasmids can be purified using the CsCl gradient method or the miniprep method. Although we have found that the CsCl gradient method yields excellent results, it is time-consuming and relatively expensive. The miniprep method, on the other hand, is simple, cheaper, and gives excellent sequencing results. The detailed protocol or isolation and purification of plasmid DNA is described below.

1. Inoculate a single colony or 10 µl of previously frozen bacteria containing the plasmid DNA of interest in 5 ml of Luria–Bertani (LB) medium and 50 µg/ml of appropriate antibiotics (e.g., ampicillin), depending on the specific antibiotic-resistant gene carried by the specific plasmid. Culture the bacteria at 37°C overnight with shaking at 200 rev/min.

2. Transfer the overnight culture into a microcentrifuge tube (1.5 ml/tube) and centrifuge at 6000 rev/min for 4 min. Carefully aspirate the supernatant.  
Note: *If the plasmid carried by bacteria is a high-copy number plasmid, 1.5 ml of cell culture usually gives a yield of approximately 40 µg plasmid DNA using the present method. In this way, 10 tubes of preparation can generate about 400 µg plasmid DNA, which is equivalent to a large-scale preparation. Therefore, the volume of bacterial culture used for purification of plasmid DNA depends on the particular experiment.*
3. Add 0.1 ml of ice-cold lysis buffer to each tube and gently vortex for 1 min. Incubate at room temperature for 5 min.  
Principle: *The function of this step is to lyse the bacteria by hyperlytic osmosis, releasing DNA and other contents.*
4. Add 0.2 ml of a freshly prepared alkaline solution to each tube and mix by inversion. **Never vortex.** Place the tubes on ice for 5 min.  
Principle: *This step denatures chromosomal DNA and proteins.*
5. Add 0.15 ml of ice-cold potassium acetate solution to each tube. Mix by inversion for 10 s and incubate on ice for 5 min.  
Principle: *This purpose of step is to selectively precipitate proteins, polysaccharides, and genomic DNA. Under these particular buffer conditions, plasmid DNA still remains in the supernatant without being precipitated.*
6. Centrifuge at 12,000 g for 5 min and *carefully* transfer the supernatant to fresh tubes.
7. Add RNase (DNase-free, Boehringer Mannheim) to the supernatant at 1.5 µl/0.1 ml supernatant. Incubate the tubes at 37°C for 30 min.  
Principle: *RNase degrades total RNAs from the sample.*
8. Remove RNase and other remaining proteins by the following two options (see below). Option A is faster, cheaper, and more efficient than option B.
  - Option A: filtration using a Probind-filter (Millipore)  
Transfer the RNase-treated supernatant into a minifilter cup (0.4 ml/cup) placed in a Eppendorf tube. Cap the tube and centrifuge at 12,000 g for 30 s. Remove the filter cup and the collected supernatant in the Eppendorf tube is ready for DNA precipitation. Proceed to step 9.  
Note: *The membrane filter attached at the bottom of the cup is specially designed to retain proteins and to allow nucleic acids to pass through. One cup can be reused for four to five times if one uses it for the same supernatant pool. However, it is not a wise idea to reuse it for different plasmid samples because of potential contamination. The author routinely uses this type of filter for plasmid DNA preparations. DNA obtained is pure and of high yield with a  $A_{260}/A_{280}$  ratio of approximately 2.0.*
  - Option B: phenol/chloroform extraction
    - (a) Add an equal volume of TE-saturated phenol/chloroform to each tube and mix by vortexing for 1 min.
    - (b) Centrifuge at 12,000 g for 4 min and transfer the upper, aqueous phase into fresh tubes.

- (c) Add an equal volume of chloroform/isoamyl alcohol (24:1) and mix by vortexing for 1 min and centrifuge as in step (b).
- (d) Centrifuge at 12,000 *g* for 4 min and transfer the supernatant to fresh tubes. Proceed to step 9.
9. Add 2 to 2.5 volumes of 100% ethanol to each tube. Mix by repeat inversions and allow the plasmid DNA to precipitate for 10 min at  $-80^{\circ}\text{C}$  or 30 min at  $-20^{\circ}\text{C}$ .
10. Centrifuge at 12,000 *g* for 10 min. Carefully decant the supernatant, add 1 ml of prechilled 70% ethanol, and centrifuge at 12,000 *g* for 5 min. Carefully aspirate the ethanol and dry the plasmid DNA under vacuum for 15 min.
11. Dissolve the plasmid DNA in 15  $\mu\text{l}$  of TE buffer or sterile deionized water. Take 1  $\mu\text{l}$  to measure the concentration and store the sample at  $-20^{\circ}\text{C}$  until use.

### Reagents needed

- *LB medium (per liter)*  
10 g Bacto-tryptone  
5 g Bacto-yeast extract  
5 g NaCl  
Adjust pH to 7.5 with 2 N NaOH and autoclave. If needed, add antibiotics after the autoclaved solution has cooled to less than  $50^{\circ}\text{C}$ .
- *TE buffer*  
10 mM Tris-HCl, pH 8.0  
1 mM EDTA
- *Lysis buffer*  
25 mM Tris-HCl, pH 8.0  
10 mM EDTA  
50 mM glucose
- *Alkaline solution*  
0.2 N NaOH  
1% SDS
- *Potassium acetate solution (pH 4.8)*  
Prepare 60 ml of 5 M potassium acetate. Add 11.5 ml of glacial acetic acid and 28.5 ml of  $\text{H}_2\text{O}$ . Total volume is 100 ml. This solution is 3 M with respect to potassium and 5 M with respect to acetate. Store on ice before use.
- *RNase (DNase-free)*  
Boehringer Mannheim, Cat. No: 119915, 500  $\mu\text{g/ml}$
- *TE-saturated phenol/chloroform*  
Thaw crystals of phenol in  $65^{\circ}\text{C}$  water bath with occasional shaking. Mix equal parts of TE buffer and thawed phenol. Let it stand until the phases separate at room temperature. Mix an equal part of the lower, phenol phase with an equal part of chloroform/isoamyl alcohol (24:1).
- Chloroform/isoamyl alcohol (24:1)
- Ethanol: 100% and 70%

### 5.2.1.2 Purification of ssDNA

ssDNA utilized as a template usually gives excellent sequencing results. The following protocol works quite well for purification of ssDNA from plasmid-phage (phagemid) vectors, which include M13mp9, M13mp12, M13mp13, M13mp18, and M13mp19.

1. Streak an appropriate *Escherichia coli* strain on an LB plate, which carries the putative phagemids containing the DNA insert of interest. Invert the plate and incubate at 37°C overnight in order to obtain individual colonies.
2. Inoculate a single colony in 3 ml of LB medium containing 50 µg/ml ampicillin and 12 µg/ml tetracycline or appropriate antibiotic. Incubate at 37°C overnight with shaking at 200 rev/min.
3. Add 0.3 ml of the cell culture to 3 ml of superbroth in a 50 ml conical tube. Incubate at 37°C with shaking at 200 rev/min for 2 to 3 h.
4. Add 8 ml of helper phage R408 (pfu =  $1 \times 10^{11}$ ; available from Stratagene) to the culture at step 3 and continue to culture for 8 to 10 h.
5. Centrifuge at 6000 rev/min for 4 min and carefully transfer the supernatant to a fresh tube.
6. Based on the volume of the supernatant, add 1/4 volume of polyethylene glycol (PEG) precipitation buffer containing 3.5 M ammonium acetate buffer (pH 7.5) and 20% (w/v) PEG to the tube. Vortex for 1 min and leave it at room temperature for 20 min.
7. Centrifuge at 12,000 g for 15 min and aspirate the supernatant completely.
8. Resuspend the PEG pellet in 1/4 volume (versus the volume of the supernatant at step 5) of TE buffer (pH 8.0) and extract it with one volume of TE-saturated phenol/chloroform/isoamyl alcohol (25:24:1). Mix by vortexing and centrifuge at 11,000 g for 5 min.
9. Carefully transfer the top, aqueous phase to a fresh tube and repeat extraction twice as in step 8.
10. Measure the volume of the supernatant and precipitate the ssDNA by adding 0.5 volume of 7.5 M ammonium acetate (pH 7.5) and 2.5 volumes of chilled 100% ethanol to the supernatant. Place at -70°C for 30 min.
11. Centrifuge at 12,000 g for 20 min at 4°C and aspirate the supernatant. Wash the DNA pellet by adding 5 to 10 ml of 70% ethanol and spin down at 12,000 g for 5 min. Carefully aspirate the ethanol and dry the pellet under vacuum for 20 min. Dissolve the DNA in 40 µl of TE buffer (pH 7.6). Take 2 µl to measure the concentration of ssDNA at  $A_{260 \text{ nm}}$  and  $A_{280 \text{ nm}}$ . Store the sample at -20°C until use.

### Reagents needed

- *Superbroth medium*

Bacto-tryptone 12 g

Bacto-yeast extract 24 g

0.4% (v/v) glycerol

Dissolve in a total of 900 ml in dd.H<sub>2</sub>O and autoclave. Cool to about 50°C and add 100 ml of phosphate buffer containing 170 mM KH<sub>2</sub>PO<sub>4</sub> and 720 mM K<sub>2</sub>HPO<sub>4</sub>. Autoclave again.

- *PEG precipitation buffer*  
3.5 M ammonium acetate, pH 7.5  
20% (w/v) polyethylene glycol (PEG) 8000

## 5.2.2 PROTOCOL 2. SEQUENCING REACTIONS

### 5.2.2.1 Method A. Sequencing Reactions for Double-Stranded Plasmid DNA

1. Denature double-stranded DNA as follows:

- (a) To denature plasmid DNA, the alkaline-denaturation method is recommended. Transfer an appropriate volume of purified plasmid DNA (approximate 1  $\mu\text{g}/\mu\text{l}$ ) to a microcentrifuge tube and add one volume of freshly prepared alkaline solution containing 0.4 M NaOH and 0.4 mM EDTA (pH 8.0). Incubate at 37°C for 35 min.

*Tip: The amount of DNA to be denatured should be in excess of the amount of DNA to be sequenced. For example, if one uses 3 to 5  $\mu\text{g}$  DNA for one primer sequencing reaction, the amount of DNA for two-primer sequencing reactions for both strands at opposite directions will be 6 to 7  $\mu\text{g}$ . If the yield of DNA after denaturation, neutralization, and precipitation is 80%, the amount of DNA used for denaturation should be 7.2 to 8.4  $\mu\text{g}$ . We routinely use double the amount of DNA for denaturation and measure the DNA concentration after it is precipitated. This ensures that one has a sufficient amount of DNA for sequencing.*

- (b) After denaturation, add 0.1 volume of 3 M sodium acetate buffer (pH 5.2) to the denatured sample to neutralize the mixture.
- (c) Add 2 to 5 volumes of 100% ethanol to the mixture and precipitate DNA at -70°C for 15 min.
- (d) Centrifuge at 12,000 g for 10 min and decant the supernatant. Wash away any remaining salt from the DNA pellet with 1 ml of chilled 70% ethanol and spin down at 12,000 g for 5 min. Dry the DNA under vacuum for 15 min.
- (e) Dissolve the DNA in 10  $\mu\text{l}$  dd.H<sub>2</sub>O and place the tube on ice. Quickly measure the concentration of DNA using 1 to 2  $\mu\text{l}$  of the sample at  $A_{260\text{nm}}$  and  $A_{280\text{nm}}$ . Immediately proceed to the primer annealing reaction.
2. Perform template–primer annealing as follows:
- (a) Transfer 1 to 2  $\mu\text{g}$  or 1 pmol of freshly denatured plasmid DNA to a microcentrifuge tube on ice and add dd.H<sub>2</sub>O to a total volume of 7  $\mu\text{l}$ . Add 2  $\mu\text{l}$  of reaction buffer and 1  $\mu\text{l}$  of 5'-biotinylated sequencing primer (2 to 3 pmol). This gives approximately 1:1 (template/primer) molar stoichiometry with a total volume of 10  $\mu\text{l}$ .

DNA + dd.H <sub>2</sub> O	7 $\mu\text{l}$
5 $\times$ reaction buffer	2 $\mu\text{l}$
5'-biotinylated primer	1 $\mu\text{l}$
Total	10 $\mu\text{l}$

- (b) Place the tube in a plastic rack or its equivalent and heat at 65°C for 2 to 3 min. Quickly transfer the rack together with the tube to a beaker or tray containing an appropriate volume of 60 to 63°C water and then let cool slowly to <30°C or room temperature over 20 to 30 min. If one uses a heating block, the tubes can be heated at 65°C for 2 min followed by slow cooling to room temperature by turning off the heat so that the heating block will slowly cool down. When the temperature drops to <30°C, the annealing is complete. The real annealing temperature is 50 to 52°C. Some laboratories prefer to anneal at 50 to 55°C for 15 to 30 min followed by slow cooling.
3. Preparation of labeling and termination.
- (a) While the annealing mixture is cooling, remove the necessary materials from a commercial sequencing kit that is usually stored at -20°C. Thaw the materials on ice.
- (b) Label four microcentrifuge tubes for each template-primer mixture, which are A, G, T, and C that represent ddATP, ddGTP, ddTTP, and ddCTP, respectively.
- (c) Transfer 2.5 µl of the termination mixture of ddATP, ddGTP, ddTTP, and ddCTP to the labeled tubes A, G, T, and C, respectively. Cap the tubes and keep at room temperature until use.
- (d) Dilute the labeling mixture 5-fold as a working concentration and store on ice before use. For example, 2 µl of labeling mixture is diluted to total 10 µl with dd.H<sub>2</sub>O.

*Tips: (1) Mix well the mixture in each stock tube by pipetting it up and down before removal of an appropriate amount of mixture from each tube. (2) There are two sets of labeling mixtures and termination mixtures in the sequencing kit (USB). For regular noncompression sequencing, the one labeled dGTP should be used. However, if compression appears due to G-C rich sequences, the other one labeled dITP is strongly recommended. dITP replaces the nucleotide analog dGTP. We have found that it significantly eliminates the compressed bands.*

- (e) Dilute Sequenase Version 2.0 T7 DNA polymerase (1:8 dilution) as follows:

Ice-cold enzyme dilution buffer	6.5 µl
Pyrophosphatase	0.5 µl
DNA polymerase stored at -20°C	1 µl

*Tips: The enzyme should not be diluted in glycerol enzyme dilution buffer if one uses TBE in the gel and in the running buffer. The diluted enzyme should be stored on ice and be used within 1 h.*

4. Carry out labeling reaction when the template-primer annealing is complete.
- (a) Briefly spin down the annealed mixture and store on ice until use.
- (b) Add the following to the tube containing 10 µl of annealed mixture in the order shown:

*For use of a biotinylated primer*

DTT (0.1 M)	1 $\mu$ l
dd.H <sub>2</sub> O	2.5 $\mu$ l
Diluted Sequenase DNA polymerase	2 $\mu$ l

*For use of a biotinylated nucleotide*

DTT (0.1 M)	1 $\mu$ l
diluted labeling mixture	2.5 $\mu$ l
Diluted Sequenase DNA polymerase	2 $\mu$ l

*Tip: Add 1  $\mu$ l of Mn buffer to enhance the band that is close to the primer.*

(c) Gently mix well to avoid any air bubbles. For use of a biotinylated nucleotide in a labeling reaction, incubate at room temperature for 3 to 5 min. Proceed to step 5.

5. Carry out the termination reactions as follows:

- Carefully and quickly transfer 3.5  $\mu$ l of the mixture to each of the termination tubes (A, G, T, C) prewarmed at 37°C for 1 min. Mix and continue to incubate the reaction at 37°C in a heating block for 4 to 5 min.
- Add 4  $\mu$ l of stopping solution to each tube, mix, and cap the tubes. Store at -20°C until use.

*Tip: The samples should be electrophoresed within 4 days even when stored at -20°C. Denature the sample at 75 to 80°C for 2 to 3 min before loading it into a sequencing gel.*

**Reagents needed**

- *5 $\times$  reaction buffer*  
0.2 M Tris-HCl, pH 7.5  
0.1 M MgCl<sub>2</sub>  
0.25 M NaCl
- *DTT solution*  
100 mM dithiothreitol
- *5 $\times$  Labeling solution for dGTP*  
7.5  $\mu$ M dGTP  
7.5  $\mu$ M dTTP  
7.5  $\mu$ M dCTP or dATP  
Biotinylated dATP or dCTP
- *5 $\times$  Labeling mixture for dITP*  
7.5  $\mu$ M dITP  
7.5  $\mu$ M dTTP  
7.5  $\mu$ M dCTP or dATP  
Biotinylated dATP or dCTP
- *ddATP termination mixture for dGTP*  
80  $\mu$ M dATP  
80  $\mu$ M dGTP  
80  $\mu$ M dCTP

- 80  $\mu\text{M}$  dTTP
- 8  $\mu\text{M}$  ddATP
- *ddGTP termination mixture for dGTP*
  - 80  $\mu\text{M}$  dATP
  - 80  $\mu\text{M}$  dGTP
  - 80  $\mu\text{M}$  dCTP
  - 80  $\mu\text{M}$  dTTP
  - 8  $\mu\text{M}$  ddGTP
- *ddCTP termination mixture for dGTP*
  - 80  $\mu\text{M}$  dATP
  - 80  $\mu\text{M}$  dGTP
  - 80  $\mu\text{M}$  dCTP
  - 80  $\mu\text{M}$  dTTP
  - 8  $\mu\text{M}$  ddCTP
- *ddTTP termination mixture for dGTP*
  - 80  $\mu\text{M}$  dATP
  - 80  $\mu\text{M}$  dGTP
  - 80  $\mu\text{M}$  dCTP
  - 80  $\mu\text{M}$  dTTP
  - 8  $\mu\text{M}$  ddTTP
- *ddATP termination mixture for dITP*
  - 80  $\mu\text{M}$  dATP
  - 80  $\mu\text{M}$  dITP
  - 80  $\mu\text{M}$  dCTP
  - 80  $\mu\text{M}$  dTTP
  - 8  $\mu\text{M}$  ddATP
- *ddGTP termination mixture for dITP*
  - 80  $\mu\text{M}$  dATP
  - 160  $\mu\text{M}$  dITP
  - 80  $\mu\text{M}$  dCTP
  - 80  $\mu\text{M}$  dTTP
  - 8  $\mu\text{M}$  ddGTP
- *ddCTP termination mixture for dITP*
  - 80  $\mu\text{M}$  dATP
  - 80  $\mu\text{M}$  dITP
  - 80  $\mu\text{M}$  dCTP
  - 80  $\mu\text{M}$  dTTP
  - 8  $\mu\text{M}$  ddCTP
- *ddTTP termination mixture for dITP*
  - 80  $\mu\text{M}$  dATP
  - 80  $\mu\text{M}$  dITP
  - 80  $\mu\text{M}$  dCTP
  - 80  $\mu\text{M}$  dTTP
  - 8  $\mu\text{M}$  ddTTP
- *Sequence extending mixture for dGTP*
  - 180  $\mu\text{M}$  dATP



- 180  $\mu$ M dGTP
- 180  $\mu$ M dCTP
- 180  $\mu$ M dTTP
- *Sequence extending mixture for dITP*
  - 180  $\mu$ M dATP
  - 360  $\mu$ M dITP
  - 180  $\mu$ M dCTP
  - 180  $\mu$ M dTTP
- *Mn buffer (only for dGTP)*
  - 150 mM sodium isocitrate
  - 100 mM MnCl<sub>2</sub>
- *Enzyme dilution buffer*
  - 10 mM Tris–HCl, pH 7.5
  - 5 mM DTT
  - 0.5 mg/ml BSA
- *Glycerol enzyme dilution buffer*
  - 20 mM Tris–HCl, pH 7.5
  - 2 mM DTT
  - 0.1 mM EDTA
  - 50% glycerol
- *Sequenase Version 2.0 T7 DNA polymerase*
  - 13 units/ $\mu$ l in
  - 20 mM KPO<sub>4</sub>, pH 7.4
  - 1 mM DTT
  - 0.1 mM EDTA, pH 7.4
  - 50% glycerol
- *Pyrophosphatase*
  - 5 units/ml in
  - 10 mM Tris–HCl, pH 7.5
  - 0.1 mM EDTA, pH 7.5
  - 50% glycerol
- *Stop solution*
  - 20 mM EDTA, pH 8.0
  - 95% (v/v) formamide
  - 0.05% Bromophenol blue
  - 0.05% Xylene cyanol FF

### 5.2.2.2 Method B. Sequencing Reactions for ssDNA

The procedures are similar to those described in method A (Section 5.2.2.1) except for the following:

- (a) No double-stranded DNA denaturation is mandated. Instead, the appropriate primer and template DNA can be directly annealed in an annealing reaction.
- (b) The temperature for primer–template annealing can be at 50 to 55°C in a heating block for 15 to 25 min followed by slow cooling by turning off the heat.

### 5.2.3 PROTOCOL 3. PREPARATION OF SEQUENCING GELS

Gel preparation is one of the most important steps for success in DNA sequencing. The DNA sequencing gel is very thin (0.2 to 0.4 mm thick) and its quality and integrity directly influence the resolution and maximum reading information of DNA sequences. There are two common problems that one may encounter when preparing a sequencing gel: (1) generation of air bubbles in the gel and (2) potential leaking of gel mixture from the bottom or the side edges of the gel apparatus. Either of these two problems can lead to failure or poor quality of DNA sequencing. In our experience, the detailed protocol given below can help solve these problems. The protocol is routinely and successfully used in our laboratory.

1. Prepare a gel mixture as follows:

- (a) Dissolve an appropriate amount of urea in distilled, deionized water (dd. H<sub>2</sub>O) in a clean beaker using a stir bar.

Components	Small size gel (50 ml)	Large size gel (100 ml)
<b>For use of "Long Ranger Gel Mixture" from AT Biochemicals</b>		
Ultrapure Urea (7 M)	21 g	42 g
dd.H <sub>2</sub> O	12 ml	24 ml
<b>For use of regular acrylamide gel</b>		
Ultrapure Urea (7–8.3 M)	21–25 g	42–50g
dd.H <sub>2</sub> O	12 ml	24 ml

- (b) Warm at approximately 40 to 50°C to dissolve the urea with stirring. Once the urea is dissolved, add the following to the mixture with stirring at room temperature.

Components	Small size of gel (50 ml)	Large size of gel (100 ml)
<b>Recipe for using "Long Ranger Gel Mixture" from AT Biochemicals</b>		
5× TBE	12 ml	24 ml
Long Ranger mixture	5 ml	10 ml
Add dd.H <sub>2</sub> O up to	50 ml	100 ml
<b>Recipe for regular 5% or 8% acrylamide gel using TBE buffer</b>		
5× TBE	10 ml	20 ml
5% Acrylamide/bis-acrylamide	2.37 g/0.13 g	4.75 g/0.25 g
8% Acrylamide/bis-acrylamide	3.8 g/0.2 g	7.6 g/0.4 g
Add dd.H <sub>2</sub> O up to	50 ml	100 ml

**Recipe for regular 5% or 8% acrylamide gel when using glycerol gel buffer (for Sequenase Version 2.0 DNA polymerase diluted with glycerol enzyme dilution buffer)**

10× TBE	5 ml	10 ml
5% Acrylamide/bis-acrylamide	2.37 g/0.13 g	4.75 g/0.25 g
8% Acrylamide/bis-acrylamide	3.8 g/0.2 g	7.6 g/0.4 g
Add dd.H <sub>2</sub> O up to	50 ml	100 ml

Caution: *The Long Ranger mixture and the acrylamide/bis-acrylamide are very toxic. Care should be taken when using these chemicals. Gloves should be worn when handling the gel mixture.*

- (c) Filter and degas the mixture under vacuum for 3 to 5 min (optional) and transfer the gel mixture to a plastic squeeze bottle or leave it in the beaker if one uses a syringe to fill a gel apparatus with the liquid.
2. While the gel mixture is cooling to 25 to 30°C with a stirring bar, one can start to clean glass plates. Gently place glass plates, one by one, in a sink and thoroughly clean the glass plates with detergent using a sponge. Wash away the soap residue with running tap water followed by distilled water. Spray (95% or 100%) ethanol onto the plates to thoroughly remove the soap and oily residues. Finally, wipe the plate dry using clean paper towels (e.g., bleached singlefold towels; James River Corporation, Norwalk, CT).
3. Carefully lay the glass plate down on the laboratory bench and coat its surface with 0.5 to 1.0 ml of either Sigmacoat (Sigma Chemicals) to form a thin film. This helps prevent the gel from sticking onto the glass plate when separating the glass plates from each other after electrophoresis. Mark the coated plate on the back with a marker pen for identification. The other plate should not be coated and served as the bottom plate when the plates are separated from each other.
4. Assemble a glass plate sandwich by placing a spacer (0.2 or 0.4 mm thick) on each of two side edges of the bottom glass plate and cover the plate with the top plate. There are different ways to assemble glass plates, depending on the manufacturer's instructions, and to pour the gel mixture into the sandwich.

### 5.2.3.1 Method A. Pouring the Gel Mixture Horizontally into the Sandwich

- (a) Place two Styrofoam supporters (about 5 to 10 cm thick, one for the top and the other for the bottom of the sandwich) or two plastic pipette-tip boxes with an even surface on a flat bench. Lay the glass sandwich horizontally on the two supports and check the flatness with a level. It is not necessary to seal the edges of the glass sandwich with a tape. Clamp the side edges of the plates with the manufacturer's clamps (optional).
- (b) Immediately before pouring the gel, add *N,N,N',N'*-tetramethylethylenediamine (TEMED) and freshly prepared 10% ammonium persulfate solution (APS) to the gel mixture (for 100 ml of gel mixture, the volume for TEMED and APS should be 48 µl and 0.49 ml, respectively). Quickly and gently mix the mixture by swirling the squeeze bottle to avoid generating air bubbles, and immediately begin to pour the gel mixture into the sandwich. Starting at the middle region between the plates, slowly and continuously squeeze

the bottle with one hand to cause flow outward of the mixture. One should simultaneously use a roll of Scotch masking tape (1 to 2 cm wide and 10 to 12 cm in diameter) to tap the top glass plate along the front of the flowing solution with the other hand until the sandwich is completely filled. The gel mixture becomes distributed into the sandwich by capillary suction and the tapping helps cause an even flow of the gel mixture. If squeezing of the bottle is stopped at any time, make sure to squeeze the bottle to remove any air bubbles before refilling the sandwich with gel mixture. It is strongly recommended that two people work together while pouring the gel in such a manner that one person can focus on squeezing the bottle to pour the gel, while the other is responsible for tapping the top glass plate to help flow and prevent occurrence of bubble formation. Alternatively, the gel mixture can also be loaded into the sandwich by the use of a syringe or a pipette depending on personal preference.

- (c) Immediately and carefully insert the comb (0.2 or 0.4 mm thick depending on the thickness of the spacer), upside down, into the gel mixture to make a straight, even front edge of the gel. Avoid producing any bubbles underneath the comb. To prevent the gel from polymerizing between the comb and the glass plates, clamp the comb in place together with the glass plates with two to three appropriately sized clamps. It is recommended that a 24-well comb be used for a small size gel and a 48- or 60-well comb be used for a large size of gel. The color of the comb should be off-white or white so that each well can be clearly visible when loading the DNA samples.
- (d) Allow the gel to polymerize for 0.5 to 1.5 h at room temperature. The gel can be subjected to electrophoresis directly by removing the comb and mounting the cassette onto the sequencing apparatus according to the manufacturer's instructions. For multiple loadings at approximately 2-h intervals, we recommend that the gel be poured late in the day or at night, and that electrophoresis be performed early the next morning. If this is the option taken, the polymerized gel should be covered at the top and bottom edges of the cassette with clean paper towels wetted with distilled water. Wrap the paper towels with Saran Wrap™ to keep the gel from drying. Leave it overnight so that the electrophoresis can be carried out the next day.

### 5.2.3.2 Method B. Pouring the Gel at an Angle

- (a) Carefully seal the two side edges of the sandwich using appropriate tape. Clamping both sides of the sandwich is optional.
- (b) Seal the bottom of the sandwich in two ways: (1) tightly seal the bottom edge with an appropriate tape; (2) leave the bottom unsealed and attach the special bottom tray (provided by the manufacturer) to the bottom of the sandwich. Some types of commercial apparatus have disposable bottom spacers available, which can be inserted into the sandwich at the bottom and may then be sealed by tape.
- (c) Pour the gel mixture into the sandwich. One option is to pre-seal the bottom first with some gel mixture to ensure no leaking. This can be done by

transferring approximately 3 ml of the gel mixture to a tray and adding 5  $\mu$ l of TEMED and 45  $\mu$ l of freshly prepared 10% APS. Mix well, hold the sandwich vertically, and immediately immerse the bottom of the sandwich in the gel mixture. The mixture containing a high concentration of APS can quickly polymerize and seal the bottom of the sandwich. After the bottom is sealed, the rest of the gel mixture can be poured into the sandwich.

- (d) Immediately before pouring the gel, add TEMED and freshly prepared 10% APS to the gel mixture contained in a clean squeeze bottle (for 100 ml of gel mixture, the volume for TEMED and APS should be 48  $\mu$ l and 0.49 ml, respectively). Quickly and carefully mix the mixture by swirling the squeeze bottle to avoid bubbles, and immediately start to pour the gel into the sandwich. Raise the top of the sandwich to about 45° angle with one hand. Using the other hand, slowly squeeze the bottle to cause flow of the gel mixture at the top corner along one side of the sandwich. The angle of the plate and the rate of flowing should be adjusted to avoid formation of air bubbles. When the sandwich is half-full, place the top end of the plate on a small box or support on the laboratory bench and the bottom end of the plate on the bench, forming an angle of 25° to 30°. Continuously fill the gel mixture into the sandwich and simultaneously use a roll of Scotch masking tape (1 to 2 cm thick and 10 to 12 cm diameter) or its equivalent to tap the top glass plate along the front of flowing gel with the other hand to prevent any air bubbles from forming until the sandwich is completely filled. On the other hand, the gel mixture can also be loaded into the sandwich with a syringe or pipette depending on personal preference.
- (e) Immediately and carefully insert a clean comb (0.2 or 0.4 mm thick depending on the thickness of the spacer), upside down, into the gel mixture to make a straight, even front edge of the gel. Avoid generating any air bubbles underneath the comb. Clamp the comb in place between the glass plates with two to three appropriate sized clamps.
- (f) Carefully lay the plates on a flat surface and allow the gel to polymerize for 0.5 to 1.5 h at room temperature. At this point, the gel can be directly subjected to electrophoresis by removing the comb and mounting the gel cassette onto the sequencing apparatus according to the manufacturer's instructions. For multiple loadings (e.g., four loadings at 2-h intervals), we recommend that the gel be poured late in the day or at night, and that the electrophoresis be carried out early the next morning. To leave the gel overnight, the polymerized gel should be covered at the top and bottom edges of the cassette with clean paper towels wetted with distilled water. Wrap the paper towels with Saran Wrap to keep the gel from drying.

### Materials needed

- 5 $\times$  TBE buffer
  - 27.5 g Boric acid
  - 54 g Tris base

20 ml 0.5 M EDTA buffer (pH 8.0)

Dissolve well after each addition in 600 ml dd.H<sub>2</sub>O. Add dd.H<sub>2</sub>O to a final volume of 1000 ml. Autoclave and then store at room temperature.

- *10× Glycerol tolerant gel buffer*  
108 g Tris base  
36 g Taurine  
4.65 g Na<sub>2</sub>EDTA·2H<sub>2</sub>O buffer (pH 8.0)  
Dissolve well after each addition in 600 ml dd.H<sub>2</sub>O. Add dd.H<sub>2</sub>O to a final volume of 1000 ml. Autoclave and then store at room temperature.
- *Urea*  
Ultrapure grade
- *Long Ranger Gel Mixture™*  
AT Biochem (Cat. # 211ISI).
- *10% Ammonium persulfate solution (APS)*  
0.1 g in 1.0 ml dd.H<sub>2</sub>O (fresh)
- *High power supply*  
It should have an upper limit of 2500 to 3000 V.

#### 5.2.4 PROTOCOL 4. ELECTROPHORESIS

1. Carefully remove the comb and insert the cassette into the gel apparatus according to the manufacturer's instructions.
2. Add sufficient volume of 0.6× TBE running buffer (diluted from 5× TBE stock buffer) to both top (cathode) and bottom (anode) chambers. Gently wash the top surface of the gel three times by pipetting the running buffer up and down.
3. Vertically hold the left and right sides of the comb using two hands and carefully insert the comb into the top of the sandwich to form the wells. The insertion of the comb should be done slowly and evenly until all the teeth just touch the surface of the gel. Remove any air bubbles trapped in the wells using a pipette.

*Tips: It is acceptable if the teeth of the comb penetrate a little bit into the gel (<0.5 mm from the surface of the gel). However, if one inserts the teeth too deep into the gel or repeatedly pulls and inserts the comb several times, the surface of the gel will be badly damaged and cause leaking when loading samples. This results in contamination of the wells and inaccurate sequence data.*

4. Calculate the volume of the gel (length × width × thickness of the spacer) and set the power supply. We strongly recommend that one set it at a constant power (Watts) using 1.0 to 1.1 W/cm<sup>3</sup>. If constant power is not available from the power supply, 0.5 to 0.8 mA/cm<sup>3</sup> constant current should be set up. Examples are as follows:

Gel volume	Constant wattage	Electrophoresis temperature
35 cm <sup>3</sup>	35–38.5	45–55°C
70 cm <sup>3</sup>	70–77	45–55°C

Caution: *If one sets the power supply at a nonconstant level (e.g., high voltage or high current), the gel may burn or melt during the electrophoresis due to the high amount of heat generated.*

5. Connect the power supply unit to the gel apparatus with the cathode at the top of the gel and anode at the bottom of the gel so that the negatively charged DNA will migrate downward.
6. Turn on the power and prerun the gel for 10 to 12 min.
7. After prerunning for 7 to 9 min, denature the labeled DNA samples at 75°C for 2.5 to 3 min before loading in wells. The tubes containing the samples should be capped tightly while heating in order to prevent evaporation of the samples.

Tip: *For heating, it is recommended that one places the tubes in a heating block in the order of A, T, G, C or A, G, T, C to prevent a potential mix-up when loading the samples into the gel.*

8. When pre-electrophoresis is complete, turn off the power supply unit, wash the wells briefly to remove urea, and then quickly and carefully load the samples into the appropriate wells (3.5 to 4  $\mu$ l/well).

Tips:

- (a) *No leaking is allowed between wells. Otherwise, the DNA samples will be contaminated and result in a mix-up of the nucleotide sequences.*
  - (b) *There are special pipette tips available for DNA sample loading. It is recommended that one not use one tip for loading multiple samples in order to prevent any contamination. If one uses a 0.4-mm spacer, the use of normal 100 to 200  $\mu$ l pipette tips works fine for loading. This is faster and no air bubbles develop, which is quite common when using the commercial sequencing loading tips with a long and flat tip.*
  - (c) *After taking a sample from each tube, the tubes should be capped immediately. All tubes should be briefly spun down and stored at 4°C or -20°C until the next loading.*
  - (d) *It is very important that the samples loaded into the wells be recorded in a notebook in the order of the DNA samples loaded (e.g., A, G, T, C or A, T, G, C depending on the particular loading sequence). This will help one read the DNA sequence after autoradiography.*
9. After all the samples are loaded, turn on the power supply and allow electrophoresis to occur at an appropriate constant voltage. The running time depends on the size of DNA. Generally, the run time for 250, 400 to 450, and >500 bp are 2, 4, and 6 to 8 h, respectively. For multiple loading (e.g., 2 to 5 times loading depending on the size of the gel and volume of the DNA sample), monitor the migration of the first blue dye (Bromophenol blue or BPB), which migrates at 40 bp. When the BPB reaches approximately 2 to 3 cm from the bottom, turn off the power supply and carry out the next loading so that there are overlapping sequences between the adjacent loads. This is very useful for the correct reading of DNA sequences after autoradiography.  
Tips: *The power supply must be turned off and the wells for sample loading should be washed to remove air bubbles with the running buffer using a pipette. DNA samples may be denatured again at 75°C for 2 min before*

*loading. The loading order of the samples should be the same as for the previous loading to avoid misreading of DNA sequences.*

10. When the electrophoresis is complete, disconnect the power supply and decant the upper chamber buffer. Lay the cassette containing the gel on a table or bench and allow to cool for 20 to 25 min before separating the glass plates. Mark and measure the area of the gel to be transferred.  
*Note: If the glass plates are separated immediately after electrophoresis, the gel may not be flat, or it may become broken, or it can cause difficulty in separating the glass plates.*
11. While the gel is cooling, wear clean gloves and cut one piece of nylon membrane and three pieces of 3MM Whatman paper. The size of membrane or filter paper should be slightly larger than the area of the gel to be transferred. Label one corner of the membrane for orientation using a pencil and prewet the membrane in dd.H<sub>2</sub>O for 5 to 10 min.
12. Remove the clamps from the glass plates. Starting at one corner of the spacer site, carefully insert a spatula into the sandwich and slowly lift the top glass plate (the Sigma coated plate) with one hand. Meanwhile, hold the bottom plate with the other hand until the top glass plate is completely separated from the gel. The gel should remain stuck onto the bottom plate.  
*Tip: Separation of glass plates is critical for the success of DNA sequencing. As long as the top plate is loosened, continue to lift it until it is completely separated from the other plate. Do not allow the top plate to come back in contact with the gel at any time during separation or it may cause trouble for the gel.*
13. Perform fixation. If one uses “Long Ranger Gel” mixture, the electrophoresed gel does not need to be fixed. However, if a regular acrylamide gel mixture is used, the gel should be fixed. Immerse the gel together with the bottom plate in a relatively large tray filled with a sufficient volume of fixing solution containing 15% to 20% of ethanol or methanol and 5% to 10% acetic acid for 15 to 20 min. Remove the gel together with the plate from the tray, drain off excess fixing solution, and gently place bleached, clean paper towels on the gel to remove excess solution.

### 5.2.5 PROTOCOL 5. TRANSFERRING OF DNA FROM GEL ONTO A NYLON MEMBRANE

1. Transfer the sequenced DNA from the gel onto the prewetted membrane in the order shown: wear clean gloves and lay the membrane on the area of the gel to be transferred with the marked corner facing the gel. Remove any air bubbles underneath the membrane by gently rolling a clean 25-ml pipette on the membrane. Carefully place three layers, one by one, of 3MM Whatman dry filter papers on the membrane. Place the other glass plate or its equivalent on top of the filter papers and then a weight on the top (e.g., a bottle or beaker containing 1000 ml water). Leave undisturbed for 1 to 1.5 h.



Note: Any bubbles generated will block local transfer of DNA bands from the gel to the membrane. Once this occurs, reading of DNA sequences will not be accurate. Virtually, one has to start all over again.

2. Remove the weight, top glass plate, and 3MM filters. Wear gloves and gently peel the membrane off the gel and place the membrane with DNA-side facing up on a sheet of clean 3MM Whatman paper. Allow the membrane to dry for 30 to 45 min at room temperature. The dried membrane may be stored at 4°C until use.

### 5.2.6 PROTOCOL 6. DETECTION

1. Block nonspecific binding sites on the membrane with 0.4 ml/cm<sup>2</sup> of blocking solution using an appropriate size of tray. Place the tray on an orbital shaker with shaking at 60 rev/min for 40 min.
2. Add streptavidin–alkaline phosphatase conjugate (SAAP) to the blocking solution (1:2000 to 1:5000 dilution) in the tray. Allow SAAP to hybridize with biotinylated primer or nucleotides on the membrane for 40 min with shaking at 60 rev/min.
3. Briefly rinse the membrane with dd.H<sub>2</sub>O and wash the membrane with 1 ml/cm<sup>2</sup> of 0.5× to 1.0× SSC containing 0.1% SDS by agitating for 10 min on a shaker at 60 rev/min. Repeat this step twice.
4. Briefly rinse the membrane with dd.H<sub>2</sub>O and wash the membrane once with 1 ml/cm<sup>2</sup> of 0.5× to 1.0× SSC without SDS for 5 min on a shaker at 60 rev/min. The membrane can be subjected to detection by the following methods.

#### 5.2.6.1 Method A. Chemiluminescent Detection

- (a) Place a piece of Saran Wrap film on a bench. According to the size of the membrane, add 10 µl/cm<sup>2</sup> of Lumi-Phos 530 (Boehringer Mannheim Corporation) to the center of the Saran Wrap.
- (b) Wear gloves and briefly dampen the membrane to remove excess washing solution and thoroughly wet the DNA binding side of the membrane by lifting and overlaying the membrane several times.
- (c) Wrap the membrane with Saran Wrap film, leaving two ends of the Saran Wrap film unfolded. Place the wrapped membrane on a paper towel and carefully press the wrapped membrane, using another piece of paper towel, to wipe off excess detection solution through the unfolded ends of the Saran Wrap film. Excess detection solution will most likely cause a high background.
- (d) Completely wrap the membrane and place it in an exposure cassette with DNA-side facing up. Tape the four corners of the wrapped membrane.
- (e) In a dark room with the safe light on, overlay the membrane with a sheet of Kodak XAR or XRP x-ray film and close the cassette. Allow exposure to proceed at room temperature for 20 s to 12 h, depending on the intensity of the detected signal.

- (f) In a dark room, develop and fix the film in an appropriate developer and fixer, respectively. If an x-ray processor is available, development, fixation, washing, and drying of the film can be completed in 2 min.

*Tips: Multiple films may be needed to be exposed and processed until the desired signals are obtained. Exposure for more than 4 h may generate a high black background. In our experience, a good hybridization and detection should display sharp bands within 1.5 h (Figure 5.1).*


- (g) Proceed to DNA sequence reading (Figure 5.2).

### 5.2.6.2 Method B. Colorimetric Detection

- (a) After washing, place the membrane in color developing solution (20  $\mu\text{l}/\text{cm}^2$ ) containing 0.08  $\mu\text{l}$  of NBT stock solution and 0.06  $\mu\text{l}$  of BCIP stock solution. NBT and BCIP stock solutions are commercially available.
- (b) Allow color to develop in a dark place for 15 to 120 min at room temperature or until a desired level of detection is obtained. Detected bands should appear as a blue/purple color on the membrane.

### Reagents needed

- 5 $\times$  TBE buffer
  - 600 ml dd.H<sub>2</sub>O
  - 27.5 g 0.45 M boric acid
  - 54 g 0.45 M Tris base



**FIGURE 5.1** Chemiluminescent detection of DNA sequences.




FIGURE 5.2 Reading of DNA sequences.

10 mM EDTA (20 ml 0.5 M EDTA, pH 8.0)

Dissolve well after each addition. Add dd.H<sub>2</sub>O to 1 l. Autoclave.

- *20× SSC solution (1 l)*  
175.3 g NaCl  
88.4 sodium citrate  
Adjust the pH to 7.5 with HCl
- *Blocking buffer*  
3% (w/v) nucleic acid blocking reagents or 5% (w/v) nonfat dry milk  
150 mM NaCl  
100 mM Tris-HCl, pH 7.5  
Dissolve well with stirring
- *Color developing buffer*  
0.1 M Tris-HCl, pH 9.5  
0.1 M NaCl  
50 mM MgCl<sub>2</sub>
- *NBT stock solution*  
75 mg/ml Nitroblue tetrazolium (NBT) salt in 70% (v/v) dimethylformamide
- *BCIP stock solution*  
50mg/ml 5-bromo-4-chloro-3-indolylphosphate (BCIP or X-phosphate),  
in 100% dimethylformamide
- SAAP
- Lumi-Phos 530

### 5.3 ISOTOPIC DNA SEQUENCING METHOD

Procedures for isotopic DNA sequencing are essentially the same as those described for the nonisotopic sequencing method except for the following differences.

The first difference is the labeling reaction in which [<sup>35</sup>S]dATP or [<sup>35</sup>S]dCTP (not a biotinylated nucleotide) is employed. Add the following components to the annealed primer–template mixture (10 µl).

DTT	1 µl
Diluted labeling mixture	2 µl
[ <sup>35</sup> S]dATP or [ <sup>35</sup> S]dCTP (1000–1500 Ci/mmol)	1 µl
Diluted Sequenase DNA polymerase	2 µl

The second difference is drying of the gel and autoradiography. There is no DNA transferring involved. Specific steps are described below.

1. Once the top glass plate is separated from the gel on the bottom plate, gently and slowly lay the precut 3MM Whatman paper on the gel from the bottom side or the upper side of the gel until it lays down on the entire gel. Gently and firmly press the paper thoroughly onto the gel surface with a Styrofoam block (approximately 50 cm long, 5 cm wide, and 5 cm thick). Then, starting from one corner, slowly peel the 3MM Whatman paper with the gel on it from the bottom plate. Place it on a flat surface with gel-side up and carefully cover the gel with Saran Wrap without any air bubbles or wrinkles generated between the Saran Wrap and the gel.
2. Assemble the gel on the drying apparatus according to the manufacturer's instructions and dry the gel at 70 to 80°C under vacuum for 30 to 55 min depending on the strength of the vacuum pump. Turn off the heat and allow to cool for another 20 to 30 min under vacuum. Proceed to autoradiography.

Tips:

- (a) *Place a water trap at a position lower than the gel dryer for effective suction of the water. If no freeze- or refrigerated trap is available, place a water-trap flask or bottle in a bucket with some dry ice and ethanol. Connect the trap to a vacuum pump and to the gel dryer. This works fine in our laboratory.*
  - (b) *If the gel is removed immediately after the heat is turned off, the gel may crack and/or become uneven on the surface. Hence, it is recommended that one allow it to cool down for a while under vacuum before taking the gel out of the gel dryer.*
3. Peel off the Saran Wrap from the gel and put the gel on an appropriate exposure cassette. In a dark room under a safe light, place an appropriately sized piece of x-ray film (Kodak XAR-film or Amersham x-ray film) on the surface of the gel and close the cassette. Allow exposure to take place at room temperature (for <sup>35</sup>S) by placing the cassette in a dark place for 1 to 4 days depending on the intensity of the signal. It is recommended that one should develop the film after exposure for 24 h and decide the length of further exposure.  
Caution: [<sup>35</sup>S] dATP or dCTP is dangerous. Care should be taken when using the nucleotides. Gloves should be worn and an appropriate Plexiglas protector ought to be used. Any used isotopic buffer should be collected in a special container for disposal.

## 5.4 USE OF FORMAMIDE GELS

Compression is a common phenomenon that usually causes unreadability on a developed sequencing film. The problem is primarily due to intramolecular base pairing or G-C rich in a primer extension. The local folded structures or hairpin loops migrate faster through the gel matrix than unfolded structures, and persist during the electrophoresis. As a result, bands run very close together with a gap or increased band spacing in the region. One way to solve this problem is to increase the denaturing conditions in the gel matrix using urea and formamide. The procedures for preparing a formamide gel, electrophoresis, and autoradiography are very similar to those described in earlier protocols except for the following steps.

### 1. The gel mixture

Components	Small size gel (50 ml)	Large size gel (100 ml)
<b>Use of "Long Ranger Gel Mixture" from AT Biochemicals</b>		
Ultrapure Urea	21 g	42 g
Long Ranger mixture	8 ml	16 ml
Ultrapure formamide	20 ml	40 ml
5× TBE	10 ml	20 ml
Add dd.H <sub>2</sub> O up to	50 ml	100 ml
<b>Use of regular acrylamide gel mixture if Sequenase Version 2.0 DNA polymerase is diluted with a buffer without glycerol</b>		
Ultrapure Urea (7 M)	21 g	42 g
Ultrapure formamide	15–20 ml	30–40 ml
6% acrylamide/bis-acrylamide	2.8 g/0.15 g	5.7 g/0.3 g
8% acrylamide/bis-acrylamide	3.8 g/0.2 g	7.6 g/0.4 g
5× TBE	5 ml	10 ml
Add dd.H <sub>2</sub> O up to	50 ml	100 ml
<b>Recipe for a regular acrylamide gel mixture if Sequenase Version 2.0 DNA polymerase is diluted in glycerol enzyme dilution buffer</b>		
Ultrapure Urea (7 M)	21 g	42 g
Ultrapure formamide	15–20 ml	30–40 ml
10× glycerol tolerant gel buffer	5 ml	10 ml
6% acrylamide/bis-acrylamide	2.8 g/0.15 g	5.7 g/0.3 g
8% acrylamide/bis-acrylamide	3.8 g/0.2 g	7.6 g/0.4 g
Add dd.H <sub>2</sub> O up to	50 ml	100 ml

2. Electrophoresis. Double the electrophoresis time because formamide slows the migration of DNA by about 50%.

## 5.5 EXTENDING SEQUENCING FAR FROM THE PRIMERS

We routinely use the sequence extending mixture (USB) to obtain sequences beyond 600 to 800 bases from the primer with high resolution. Using multiple loadings, more than 1500 to 2000 bases from the primer can be extended with ease. The protocols of extending sequencing are quite similar to those described in the previous protocols except for the following steps:


1. The labeling mixture should not be undiluted or it may be diluted for 2-fold, instead of using 5-fold dilution.
2. Increase the amount of biotinylated nucleotide or [<sup>35</sup>S]dATP (1000 to 1500 Ci/mmol) from the regular volume of 2 to 4  $\mu$ l (biotinylated nucleotide) or 1 to 2  $\mu$ l (isotopic nucleotide).
3. Extend the labeling reaction from the regular time of 2–5 to 4–8 min at room temperature.
4. In the termination reaction, instead of adding 2.5  $\mu$ l of ddNTPs to the appropriate tubes (A, G, T, C), add 2.5  $\mu$ l of a mixture of the appropriate sequence extending mixture (USB) and the appropriate termination mixture (USB) at ratios of 2:0.5, 2:1.0, 1.5:1 (v/v), depending on the particular DNA sequence to the appropriate tubes.
5. Use a relatively long gel (80 to 100 cm) and extend electrophoresis for 12 to 16 h using a high-quality sequencing apparatus.

## 5.6 DNA SEQUENCING BY PRIMER WALKING

Primer-walking refers to stepwise sequencing starting from the 5' end of the target DNA using a series of primers. The first primer is usually a universal primer that is built-in the plasmid vector such as T3, T7, or SP6 primers. After each DNA sequencing, a new primer will be designed based on the very last sequence. For instance, if the first sequencing has revealed 450 bases with 3'-end sequences of 5'---GCATGTAGACGATAGGATACAG-3'. To continue sequencing of the DNA, the GCATGTAGACGATAGGATACAG can be chosen as the walking primer for the next round of sequencing. In the same way, new walking primers can be selected for subsequent sequencing until the entire target DNA has been completely sequenced.

## 5.7 DNA SEQUENCING BY UNIDIRECTIONAL DELETIONS

It takes a longer time to sequence large DNA molecules as compared with regular stepwise or primer-walking sequencing methods. However, using exonuclease III, the gene or large DNA fragment can be unidirectionally deleted in order to generate a series of shorter fragments with overlapping ends. In this way, these progressively deleted fragments can then be simultaneously sequenced in a short time. The general principles and procedures are outlined in Figure 5.3.



**FIGURE 5.3** Diagram of progressive deletions of DNA insert for sequencing.

1. Recombinant plasmid, phagemid, or bacteriophage M13 replicate form of DNA that contains the cloned DNA of interest is first linearized with two appropriate restriction enzymes. Both enzymes should cut DNA between one end of the target DNA and the binding site for the universal sequencing primer. One enzyme should cleave near the target DNA and generate either a recessed 3' end (or 5' protruding end) or a blunt end. The other enzyme will cleave the DNA near the binding site for the universal sequencing primer and must produce a 4-base protruding 3' end or be filled in with  $\alpha$ -phosphorothioate dNTPs.
2. The linearized DNA is then progressively deleted with exonuclease III that only digests the DNA from the blunt or 5' protruding terminus, leaving the 3' protruding (overhang) or  $\alpha$ -phosphorothioate-filled end intact. The digestion proceeds unidirectionally from the site of cleavage to the target DNA sequence. The digestion is terminated by taking an appropriate volume of the samples at appropriate time intervals, thus generating a series and progressive deletions of shorter DNA fragments.
3. The exposed ssDNAs are then cleaved by nuclease S1 or mung-bean nuclease. This produces blunt termini at both ends of the DNA fragments to be sequenced.
4. The shortened DNA is then recircularized using T4 DNA ligase and transformed into an appropriate bacterial host. Transformants can be selected with appropriate antibiotics in the culture medium and the recombinant plasmids will be purified and subjected to DNA sequencing.

Plasmid based vectors for subcloning of the DNA to be sequenced are commercially available. These include pGEM-5Zf or pGEM-7Zf (Promega Incorporation) whose multiple cloning sites contain two unique restriction sites lying between the end of the DNA insert to be deleted and the binding site for the universal sequencing primer. One of the two unique restriction sites should be near the end of the insert and must generate a blunt or 5' overhang end that is necessary for exonuclease III deletion. The other enzyme should cut near the sequencing primer binding site and must produce a 3' overhang end to protect the end from exonuclease III deletion. Thus, the exonuclease digestion will be unidirectional and proceed into the insert DNA sequence. The unique restriction enzymes that can be used are listed below.

---

#### A. Unique enzymes for generating 5' protruding or blunt ends

Restriction enzyme	Recognition sequence	Enzyme	Recognition Sequence
<i>NotI</i>	5'..GC*GGCC GC..3' 3'..CG CCGG*CG..5'	<i>SmaI</i>	5'..CCC*GGG..3' 3'..GGG*CCC..5'
<i>XbaI</i>	5'..T*CTAG A..3' 3'..A GATC*T..5'	<i>XhoI</i>	5'..CT*CGA G..3' 3'..GA GCT*C..5'
<i>SalI</i>	5'..G*TCGA C..3' 3'..C AGCT*G..5'		

*Note:* Asterisk (\*) indicates the cutting site. In spite of the fact that Hind III, EcoRI, and BamHI can also generate 5' overhangs, they are not usually unique since most of the DNA inserts contain the recognition sites for these enzymes.

---

#### B. Unique enzymes that produce exonuclease III resistant 3' protruding termini

Enzyme	Recognition Sequence	Enzyme	Recognition Sequence
<i>SphI</i>	5'..G CATG*C..3' 3'..C*GTAC G..5'	<i>PvuI</i>	5'..CG AT*CG..3' 3'..GC*TA GC..5'
<i>SacI</i>	5'..G AGCT*C..3' 3'..C*TCGA G..5'	<i>KpnI</i>	5'..G GTAC*C..3' 3'..C*CATG G..5'
<i>AatII</i>	5'..G ACGT*C..3' 3'..C*TGCA G..5'	<i>BglI</i>	5'..GCCN NNN*NGGC..3' 3'..CGGN*NNN NCCG..5'

*Note:* Asterisk (\*) indicates the restriction enzyme cutting site. Plasmid DNA purification and restriction enzyme digestion are described in appropriate chapters of this book.

---

### 5.7.1 PROTOCOL 1. PERFORMING A SERIES OF DELETIONS OF THE LINEARIZED DNA WITH EXONUCLEASE III AND RECIRCULARIZATION OF DNA WITH T4 DNA LIGASE

1. Label 15 to 30 microcentrifuge tubes (0.5 ml) depending on the size of insert to be deleted, and add 7.5 to 8.0  $\mu$ l of nuclease S1 mixture to each tube. Store on ice before use.



2. Dissolve or dilute 6 to 8  $\mu\text{g}$  of linearized DNA in a total 60  $\mu\text{l}$  of 1 $\times$  exonuclease III buffer.
3. Warm the sample to an appropriate temperature and start digestion by adding 250 to 550 units of exonuclease III to the sample. Mix it as quickly as possible. Transfer 2.5 to 3.0  $\mu\text{l}$  of the reaction mixture at 0.5-min intervals to the labeled tubes containing nuclease S1 prepared at step 1. Quickly mix by pipetting up and down several times and place on ice before using (Figure 5.3).

Notes:

- (1) *The digestion rate depends on the reaction temperature.*

Temperature ( $^{\circ}\text{C}$ )	Digestion rate (bp/min)
4	25–30
22	80–85
25	90–100
30	200–220
37	455–465
45	600–630

- (2) *It is not necessary to change the buffer between exonuclease III and nuclease S1 because the S1 buffer contains zinc cations and has a low pH, which can inactivate the exonuclease III. However, some exonuclease III buffer will not inhibit the activity of nuclease S1.*
4. After all samples have been taken, place all tubes at room temperature and carry out the nuclease S1 digestion of single strands by incubating at room temperature for 30 min.
  5. Terminate the reaction by adding 1  $\mu\text{l}$  of S1 stopping buffer and heat at 70 $^{\circ}\text{C}$  for 10 min.
  6. Check the efficiency of digestion by preparing a 1% agarose gel using 2  $\mu\text{l}$  of sample from each time point.
  7. Blunt termini by adding 1  $\mu\text{l}$  of Klenow mixture to each tube and incubating at 37 $^{\circ}\text{C}$  for 4 min followed by adding 1  $\mu\text{l}$  of dNTP mixture to each tube and incubate at 37 $^{\circ}\text{C}$  for 5 to 6 min.
  8. Recircularize the DNA by adding 40  $\mu\text{l}$  of ligase mixture to each tube, mixing, and incubating at 16 $^{\circ}\text{C}$  overnight. Carry out transformation of the plasmid DNA into an appropriate bacterial host as described in the appropriate chapter in this book. The series of plasmids with progressively reduced sizes can now be simultaneously sequenced.

### Reagents needed

- 10 $\times$  exonuclease III buffer
  - 0.66 M Tris-HCl, pH 8.0
  - 6.6 mM  $\text{MgCl}_2$
- S1 buffer
  - 2.5 M NaCl

- 300 mM potassium acetate, pH 4.6
- 10 mM ZnSO<sub>4</sub>
- 50% glycerol
- *Nuclease S1 mixture (fresh)*
  - 54 µl of S1 buffer
  - 0.344 ml dd.H<sub>2</sub>O
  - 120 units nuclease S1
- *S1 stopping buffer*
  - 300 mM Tris base
  - 50 mM EDTA, pH 8.0
- *Klenow buffer*
  - 20 mM Tris-HCl, pH 8.0
  - 100 mM MgCl<sub>2</sub>
- *Klenow mixture*
  - 6 to 12 units Klenow DNA polymerase
  - 60 µl Klenow buffer
- *dNTP mixture*
  - 0.13 mM dATP
  - 0.13 mM dGTP
  - 0.13 mM dCTP
  - 0.13 mM dTTP
- *10× T4 DNA ligase buffer*
  - 0.5 M Tris-HCl, pH 7.6
  - 0.1 M MgCl<sub>2</sub>
  - 10 mM ATP
- *T4 DNA ligase mixture*
  - 0.1 ml 10× ligase buffer
  - 0.79 ml dd.H<sub>2</sub>O
  - 0.1 ml 50% PEG
  - 10 µl of 0.1 M DTT
  - 5 units of T4 DNA ligase

## 5.8 DIRECT DNA SEQUENCING BY PCR

DNA molecules or fragments or RT-PCR products (single-stranded, double-stranded, and plasmid DNA) can be directly sequenced by coupling the PCR technology and the dideoxynucleotide chain termination method. This is a particularly powerful technique when one wants to simultaneously amplify and sequence a DNA fragment of interest.

### 1. Preparation of PCR and sequencing reactions

- (a) Label four 0.5-ml microcentrifuge tubes as A, G, T, or C for each set of sequencing reactions for each PCR primer. A, G, T, and C represent ddATP, ddGTP, ddTTP, and ddCTP, respectively.

- (b) Transfer 0.5  $\mu$ l of 2 $\times$  stock mixture of dNTPs/ddATP, dNTPs/ddGTP, dNTPs/ddTTP, and dNTPs/ddCTP to the labeled tubes A, G, T, and C, respectively. To each tube, add 0.5  $\mu$ l dd.H<sub>2</sub>O, generating 1 $\times$  working mixture solution. Cap the tubes and store on ice before use.
- (c) Prepare the following mixture for each set of four sequencing reactions for each primer (forward or reverse primer) in a 0.5-ml microcentrifuge tube on ice.

Forward or reverse primer	2–5 pmol (15–27 ng) depending on the size of primer
(15 mer–27 mer, 10–30 ng/ $\mu$ l)	
DNA template	100–1000 ng depending on the size of the template
(0.4–7 kb, 10–100 ng/ $\mu$ l)	
[ $\alpha$ - <sup>35</sup> S]dATP	1–1.2 $\mu$ l
(>1000 Ci/mmol)	
or [ $\alpha$ - <sup>32</sup> P]dATP	0.5 $\mu$ l
(800 Ci/mmol)	
<u>5<math>\times</math> Sequencing buffer</u>	4.0 $\mu$ l
Add dd.H <sub>2</sub> O to a final volume of	17 $\mu$ l

- (d) Add 1  $\mu$ l (5 units/ $\mu$ l) of *Taq* DNA polymerase to the mixture at step (c). Gently mix and transfer 4  $\mu$ l of the primer–template–enzyme mixture to each tube containing 1  $\mu$ l of dNTPs and appropriate ddNTP prepared at step (b).
- (e) Overlay the mixture in each tube with approximately 20  $\mu$ l of mineral oil to prevent evaporation of the samples during the PCR amplification. Place the tubes in a thermal cycler and perform PCR as follows:

Profile	Predenaturation	Cycling				Last
		Denaturation	Annealing	Extension	4°C	
Template (<4 kb) Primer is <24 bases or with <40% G-C content	94°C, 3 min	94°C, 1 min	52°C, 1 min	70°C, 1.5 min	4°C	
Template is >4 kb Primer is >24mer or <24 bases with >50% G-C content	95°C, 3 min	95°C, 1 min	60°C, 1 min	72°C, 2 min	4°C	

- (f) When the PCR cycling is complete, carefully remove the mineral oil from each tube using pipette tips (optional) and add 3.5  $\mu$ l of stop solution to inactivate the enzyme activity. Proceed to DNA gel sequencing as described earlier in this chapter.

**Reagents needed**

- *2× dNTPs/ddATP mixture*
  - 80  $\mu$ M dATP
  - 80  $\mu$ M dCTP
  - 80  $\mu$ M dTTP
  - 80  $\mu$ M 7-Deaza dGTP
  - 1.4 mM ddATP
- *2× dNTPs/ddTTP mixture*
  - 80  $\mu$ M dATP
  - 80  $\mu$ M dCTP
  - 80  $\mu$ M dTTP
  - 80  $\mu$ M 7-Deaza dGTP
  - 2.4 mM ddTTP
- *2× dNTPs/ddGTP mixture*
  - 80  $\mu$ M dTTP
  - 80  $\mu$ M dATP
  - 80  $\mu$ M dCTP
  - 80  $\mu$ M 7-Deaza dGTP
  - 120  $\mu$ M ddGTP
- *2× dNTPs/ddCTP mixture*
  - 80  $\mu$ M dTTP
  - 80  $\mu$ M dCTP
  - 80  $\mu$ M dATP
  - 80  $\mu$ M 7-Deaza dGTP
  - 800  $\mu$ M ddCTP
- *Amount of primer per pmole*
  - 5 ng 15mer or 15 bases
  - 5.3 ng 16mer
  - 5.7 ng 17mer
  - 6.0 ng 18mer
  - 6.3 ng 19mer
  - 6.7 ng 20mer
  - 7.0 ng 21mer
  - 7.3 ng 22mer
  - 7.6 ng 23mer
  - 8.0 ng 24mer
  - 8.3 ng 25mer
  - 8.6 ng 26mer
  - 9.0 ng 27mer
  - 9.3 ng 28mer
  - 9.6 ng 29mer
  - 10.0 ng 30mer
- *5× Sequencing buffer*
  - 0.25 M Tris-HCl, pH 9.0 at room temperature
  - 10 mM MgCl<sub>2</sub>

- *Stop solution*
  - 10 mM NaOH
  - 95% formamide
  - 0.05% bromphenol blue
  - 0.05% xylene cyanole

## 5.9 RNA SEQUENCING

Like DNA, RNA can also be sequenced by use of nonisotopic or isotopic sequencing methods. A reverse transcriptase, avian myeloblastosis virus (AMV), is a DNA polymerase that catalyzes the polymerization of nucleotides using RNA or DNA template. In the labeling reaction, a biotinylated or isotopic nucleotide is incorporated into the cDNA strands transcribed from specific mRNA. The power of this technique is that it can allow one to search for the potential existence of mRNA of interest and/or mRNA expression in a specific cell- or tissue type. Specific primers can be designed based on DNA sequences or amino acid sequences of interest. Total RNA can be directly utilized in specific primer–mRNA template annealing reactions.

### 5.9.1 PROTOCOL 1. ANNEALING OF PRIMER AND RNA TEMPLATE

1. For each sequencing reaction (one set of four lanes), add the following components in a 0.5-ml microcentrifuge tube:

Primer	12 pmol
Total RNA template	5 $\mu$ g
or mRNA	100 ng
Add DEPC-dd.H <sub>2</sub> O to final volume	10 $\mu$ l

2. Cap the tube and denature RNA secondary structures at 90°C for 3 min and allow to slowly cool to 30°C over a period of 30 min. Briefly spin down and place the tube on ice before use.

### 5.9.2 PROTOCOL 2. LABELING REACTIONS

1. While the annealing reaction is cooling, label four microcentrifuge tubes for each template–primer mixture, which are A, G, T, and C that respectively represent ddATP, ddGTP, ddTTP, and ddCTP.
2. Transfer 4  $\mu$ l of the termination mixture of ddATP, ddGTP, ddTTP, and ddCTP to the labeled tubes A, G, T, and C, respectively. Cap the tubes and maintain at room temperature until use.
3. Dilute labeling mixture to 5-fold as a working concentration and store on ice before use. For example, 2  $\mu$ l of labeling mixture is diluted to total 10  $\mu$ l with dd.H<sub>2</sub>O.
4. Add the following components in a 0.5-ml microcentrifuge tube for each annealing reaction.

5× AMV RT buffer	5 $\mu$ l
Diluted (1:5) labeling mixture	2.5 $\mu$ l
Biotinylated dCTP or dATP	1 $\mu$ l
or [ $\alpha$ - $^{32}$ P] dATP or dCTP	1 $\mu$ l
Add DEPC-dd.H <sub>2</sub> O to final volume of	10 $\mu$ l

- When the annealing is complete, combine the annealing reaction mixture with the labeling reaction. Then, add 1  $\mu$ l of AMV reverse transcriptase to the combined mixtures.
- Carry out reverse transcription by incubating the tube at 42°C for 8 min.

### 5.9.3 PROTOCOL 3. TERMINATION REACTION

- Carefully and quickly transfer 4  $\mu$ l of the labeling mixture to each of the termination tubes (A, G, T, C) prewarmed at 42°C for 1 min. Mix and continue to incubate the reaction at 42°C in a heating block for 10 min.
- Add 4  $\mu$ l of stopping solution to each tube, mix, and cap the tubes. Store at -20°C until electrophoresis is carried out. Proceed to gel electrophoresis and detection or autoradiography as described earlier in this chapter.

#### Reagents needed

- AMV reverse transcriptase*
- 5× AMV reverse transcription buffer*
  - 0.25 M Tris-HCl, pH 8.3
  - 40 mM MgCl<sub>2</sub>
  - 0.25 M NaCl
  - 5 mM DTT
- DTT stock solution*
  - 100 mM dithiothreitol
- 5× Labeling solution for dGTP (nonisotopic)*
  - 7.5  $\mu$ M dGTP
  - 7.5  $\mu$ M dTTP
  - 7.5  $\mu$ M dCTP or dATP
  - Biotinylated dATP or dCTP
- 5× Labeling mixture for dITP (nonisotopic)*
  - 7.5  $\mu$ M dITP
  - 7.5  $\mu$ M dTTP
  - 7.5  $\mu$ M dCTP or dATP
  - Biotinylated dATP or dCTP
- ddATP termination mixture for dGTP*
  - 0.16 M dATP
  - 0.2 M dGTP
  - 0.2 M dCTP
  - 0.2 M dTTP
  - 0.04 M ddATP

- *ddGTP termination mixture for dGTP*
  - 0.2 M dATP
  - 0.16 M dGTP
  - 0.2 M dCTP
  - 0.2 M dTTP
  - 0.04 M ddGTP
- *ddCTP termination mixture for dGTP*
  - 0.2 M dATP
  - 0.2 M dGTP
  - 0.16 M dCTP
  - 0.2 M dTTP
  - 0.04 M ddCTP
- *ddTTP termination mixture for dGTP*
  - 0.2 M dATP
  - 0.2 M dGTP
  - 0.2 M dCTP
  - 0.16 M dTTP
  - 0.04 M ddTTP
- *Sequence extending mixture for dGTP*
  - 0.4 M dATP
  - 0.4 M dGTP
  - 0.4 M dCTP
  - 0.4 M dTTP
- *Enzyme dilution buffer*
  - 10 mM Tris-HCl, pH 7.5
  - 5 mM DTT
  - 0.5 mg/ml BSA
- *Stop solution*
  - 20 mM EDTA, pH 8.0
  - 95% (v/v) formamide
  - 0.05% bromphenol blue
  - 0.05% Xylene Cyanol FF

## Troubleshooting Guide

1. Gel melts away from the comb during electrophoresis.

*Cause:* Too much heat is built up.

*Solution:* Be sure to set the power supply at a constant power or a constant current. Do not set the voltage at some level; otherwise, the current undergoes changes during electrophoresis, producing a high temperature that would melt the surface of the gel from the top toward the bottom. When that occurs, multiple loadings of the samples are out of the question.

2. No bands appear at all on the developed x-ray film.

*Possible causes:*

- (a) The quality of primer is poor and cannot be annealed with DNA or RNA template.
- (b) Double-stranded DNA is not well denatured, such

that the primer fails to anneal to the template. (c) Some component(s) is(are) missed during the labeling reaction. (d) Sequenase Version 2.0 T7 DNA polymerase has lost its activity.

*Solution:* Make sure to completely denature the DNA template and add all components mandated for the labeling reaction. Try to use control template and primer provided.

3. Bands are fuzzy.

*Possible causes:*

- (a) Urea is not washed away from the wells before loading the samples.
- (b) Labeled samples are overheated during denaturation. (c) It takes too long to finish loading all the samples, generating some reannealing of DNA.

*Solutions:*

- (a) Make sure to rinse the surface of the gel before trying the prerun and repeat washing after the prerun before loading the samples into the wells using a pipette. (b) Set the time for denaturing of the labeled samples between 2 and 3 min and immediately load the sample into the wells. In case of many samples, the loading should be carried out quickly so that all the samples should be loaded within 2 min.

4. No clear bands appear except for a smear in each lane.

*Possible causes:*

- (a) Preparation of DNA template is poor. (b) Labeled DNA samples are not well denatured at 75°C before being loaded into the gel. (c) Gel polymerizes too rapidly (10 to 15 min) due to excess 10% APS added. (d) The gel is electrophoresed at a too cold or too hot setting.

*Solutions:*

- (a) Ensure that the DNA template is very pure without any nicks. (b) Use 0.5 ml of freshly prepared APS per 100 ml of gel mixture and make sure that the gel mixture is cooled to room temperature before it is poured into the glass sandwich. (c) Keep the labeling reaction time to 2 to 5 min for regular sequencing and 4 to 7 min for extending sequencing. (d) Make sure to denature the labeled samples at 75 to 80°C for 2 to 3 min before being them into the gel. (e) Dry the gel at 75 to 80°C under vacuum but not above 80°C.

5. All the bands are weak

*Possible causes:*

- (a) Primer concentration is too low or the annealing of primer and template does not work well. (b) Double-stranded linear DNA and double-stranded plasmid DNA are too large because of the presence of a large DNA insert, resulting in difficulty in denaturation. (c) Biotinylated or isotopic nucleotide has lost its activity. (d) Labeled DNA samples are not completely denatured before loading into the gel.

*Solutions:*

- (a) Heat the primer and double-stranded DNA template at 65°C for 3 to 4 min and slowly cool down to room temperature over 20 to 35 min. (b) Use the alkaline-denaturing method to denature large-size DNA template. If this still does not work well, try to fragment the DNA



- insert to be sequenced and subclone for further sequencing. (c) Make sure that the labeling reaction is carried out properly and denature the labeled sample at 75 to 80°C for 3 to 4 min before loading it into the gel. (d) Try to use fresh biotinylated or isotopic nucleotide with high activity.
6. Bands occur across all four lanes in some areas that are called compressions.  
*Possible cause:*  
Target DNA sequences with strong secondary structure or GC-rich.  
*Solution:*  
Use an appropriate amount of dITP to replace dGTP and an appropriate amount of pyrophosphatase in the labeling reaction, or try formamide gel sequencing.
7. Bands are faint near the primer.  
*Possible cause:*  
Insufficient DNA template or insufficient primer.  
*Solution:*  
(a) Use 1 to 1.5 µg single-stranded M13 DNA or 3 to 5 µg of plasmid DNA per reaction. (b) Increase the molar ratio of primer/DNA template from 1:1 to 1:4–5. (c) Use 1 µl of Mn buffer per regular labeling reaction.
8. Bands are faint or blank in one to two lanes.  
*Possible cause:*  
Some components may have been misadded or missed in the samples loaded in the appropriate lanes.  
*Solution:*  
Be sure that all the components are added properly.
9. No bands are observed in PCR-directed DNA sequencing, including the positive control.  
*Possible cause:*  
*Taq* DNA polymerase has lost polymerization activity or primer is missing.  
*Solution:*  
Try fresh *Taq* DNA polymerase and ensure that the primer is included in the annealing reactions.
10. No bands in RNA sequencing, including positive RNA control lane.  
*Cause:*  
AMV reverse transcriptase is missing or lost its activity in the labeling reaction.  
*Solution:*  
Make sure that the reverse transcriptase is functional.
11. No bands occur in sample RNA sequencing, but visible bands are shown in the positive RNA control lane.  
*Cause:*  
RNA template is degraded or the primer is missing.  
*Solution:*  
Make sure that the RNA is of good quality and that the primer is added in the annealing reaction.

12. High background occurs or no detection at all is obtained in nonisotopic sequencing.

*Cause:*

(a) Blocking is not efficient. (b) Detection reagents have lost their activity.

*Solution:*

Make sure that the nonspecific binding sites are efficiently blocked and try fresh detection reagents.

## REFERENCES

1. Cullmann, G., U. Hubscher, and M. W. Berchtold. 1993. A reliable protocol for dsDNA and PCR product sequencing. *BioTechniques* 15: 578.
2. Sanger, F., S. Nicken, and A. R. Coulson. 1977. DNA sequencing with chain termination inhibitors. *Proceedings of the National Academy of Sciences of the United States of America* 74: 5463.
3. Church, G. M., and W. Gilbert. 1984. Genomic sequencing. *Proceedings of the National Academy of Sciences of the United States of America* 81: 1991.
4. Bishop, M. J., and C. J. Rawlings. 1987. *Nucleic Acid and Protein Sequence Analysis: A Practical Approach*. Oxford: IRC Press.
5. Wiemann, H. V., D. Grothues, C. Sensen, C. S. Zimmermann, H. E. Stegemann, T. Rupp, and W. Ansorge. 1993. Automated low-redundancy large-scale DNA sequencing by primer walking. *BioTechniques* 15: 714.
6. Reynolds, T. R., S. R. B. Uliana, L. M. Floeter-Winter, and G. A. Buck. 1993. Optimization of coupled PCR amplification and cycle sequencing of cloned and genomic DNA. *BioTechniques* 15: 462.
7. Wu, W. L., I. Song, R. Karuppiyah, and P. B. Kaufman. 1993. Kinetic induction of oat shoot pulvinus invertase mRNA by gravistimulation and partial cDNA cloning by the polymerase chain reaction. *Plant Molecular Biology* 21(6): 1175–1179.
8. Wu, W. 1995. DNA sequencing. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke, 211–242. Boca Raton, FL: CRC Press.
9. Wu, W. L., J. P. Mitchell, N. S. Cohn, and P. B. Kaufman. 1993. Gibberellin (GA<sub>3</sub>) enhances cell wall invertase activity and mRNA levels in elongating dwarf pea (*Pisum sativum*) shoots. *International Journal of Plant Science* 154(2): 278–288.

---

# 6 Bioinformation Superhighway and Computer Databases of Nucleic Acids and Proteins

## 6.1 INTRODUCTION

We are living in the era of computer and bioinformation superhighway. To many molecular biologists, the flood of information is particularly overwhelming because gene cloning, gene mapping, human genome projects, DNA, RNA, and protein sequences are growing so rapidly. The fundamental questions are: “How is such an enormous volume of information systematically organized?” and “How can one find what he or she wants from the sea of information?” Obviously, the development of superpower computers and smart computer programs plays a major role in informatics.

This chapter provides investigators with an introduction to GenBank, the “headquarters of sequence information.”<sup>1-5</sup> With the help of the Internet, one can easily send or receive sequences, and view information inside the headquarters without leaving his or her office or laboratory. The topics covered in this chapter include the use of the National Center for Biotechnology Information (NCBI) programs to deposit a sequence to the database, retrieve sequences from the database, and carry out database searching from GenBank.<sup>3</sup> The second part of this chapter provides an introduction computer analysis of DNA or protein sequences via a widely used program, which is the genetics computer group, or the GCG package. It was originally developed by the Department of Genetics at the University of Wisconsin.<sup>4</sup>

## 6.2 COMMUNICATION WITH GENBANK VIA THE INTERNET

### 6.2.1 SUBMISSION OF A SEQUENCE TO GENBANK

Nucleic acid and protein sequences can be submitted to GenBank, the EMBL Data Library, or the DNA Database of Japan (DDBJ), regardless of whether or not they are published. In fact, most journals require that the sequence to be published first

be submitted to whichever of the three libraries is the most convenient. GenBank, the EMBL, and DDBJ are international database partners. Data submitted to one site will be exchanged with another site on a daily basis. Data to be submitted can be saved on a floppy disk or printed out and sent to

National Center for Biotechnology Information  
National Library of Medicine  
National Institutes of Health  
Building 38A, Room 8N-803  
8600 Rockville Pike  
Bethesda, MD 20894, USA

Nonetheless, the fastest and easiest way of submitting DNA, RNA, and protein sequences to the three database sites is via e-mail using the following addresses.

GenBank: [gb-sub@ncbi.nlm.nih.gov](mailto:gb-sub@ncbi.nlm.nih.gov)  
EMBL: [datasubs@ebi.ac.uk](mailto:datasubs@ebi.ac.uk)  
DDBJ: [ddbjsub@dbj.nig.ac.jp](mailto:ddbjsub@dbj.nig.ac.jp)

Special forms for sequence submission are available from these sites by mail or e-mail or from appropriate journals. In general, the questions on the forms are quite straightforward, including the name and features of the sequence. The common questions are as follows.

1. What is name of the sequence? The name is given by the author(s) (e.g., Rat HSP27 cDNA).
2. What organism is the source of the DNA?
3. Is it an mRNA (cDNA) or genomic DNA sequence?
4. If it is a genomic DNA, are the intron sequences determined?
5. Has the sequence been published? What is the title of the publication? What is the journal? etc.

A sequence to be submitted should be prepared according to the detailed instructions on the forms. The newest way to prepare and submit a sequence is to obtain access to the World Wide Web. Here is how it is done:

1. Access to the **World Wide Web** via **Netscape**.
2. Type NCBI World Wide Web home page at <http://www.ncbi.nlm.nih.gov>. Press Enter key. You are in the NCBI home page. Several programs are exhibited on the screen such as **Entrez**, **BLAST**, **BankIt**, **OMIM**, **Taxonomy**, and **Structure**.
3. Click BankIt. The following information will be displayed on the screen, including "To prepare a New GenBank submission, enter the size" and click **New**, and "To update an existing GenBank submission," press **Update**, depending on a specific sequence.

4. Click **Continue**. The electronic submission forms will show up on the screen.
5. Follow the instructions and fill in the appropriate answers in the blanks. Submit the sequence.

For each sequence submitted, a unique accession number will be given, for example, M86389. The accession number is very important because it is considered to be the name of the sequence in the database. After submission, the author(s) are encouraged to update the sequence, including corrections and publication.

## 6.2.2 SEQUENCE SIMILARITY SEARCHING USING BLAST PROGRAMS

Searching of sequence similarity or homology occurs hundreds and thousands of times daily worldwide. It provides scientists with a powerful tool to determine whether a newly isolated gene or DNA or protein is novel. If it is a known DNA or protein sequence, what is the percentage of similarity or homology as compared to other species? How large is the gene family? These interesting questions can be answered by searching the GenBank database. Fortunately, the searching does not cost anything as long as one has a computer and has access to the World Wide Web. Based on our experience, we would like to introduce what is by no means the most powerful and fastest program called **BLAST**.

BLAST stands for Basic Local Alignment Search Tool and represents a family of programs for database searching. This section primarily focuses on three programs: **BLASTN**, **BLASTX**, and **BLASTP**.

### 6.2.2.1 BLASTN

In this program, the sequence submitted for searching is called Query sequence and can be submitted in a single strand of nucleotides or both strands. The database will search for any similarity nucleotide sequences and display similar alignments on the computer screen. If there is not too much "information traffic jam," the searching speed is too fast to be believable. The entire searching and exhibition merely take a few seconds or less than 1 min.

Let us take an example of how to search a database. Assuming that we have a nucleotide sequence, named DNA X, and that we wish to know whether any nucleotide sequences in the database are similar to DNA X. The searching can be performed using the following procedures.

1. Access to the **World Wide Web** system via **Netscape**. In the location box, type <http://www.ncbi.nlm.nih.gov/> and press **Enter** key. Several programs are displayed on the computer screen, including **BLAST** and **NCBI Services**.
2. Find NCBI Services and click **•Blast Sequence Similarity Searching**.
3. Click **•Basic Blast search** or **•Advanced Blast search** (Advanced is recommended). You are now in the **NCBI BLAST program**. From the top to the bottom, there are a number of blank boxes to be filled in or pre-chosen as default.

4. Choose **blastn** for the program and **nr** or **GenBank** for the database. There is a relatively large box in the middle of the screen for entering the sequence to be submitted. The nucleotide sequence should be in the **FASTA format** or written in **Courier Font**.
5. In the sequence box, type the name of the sequence on the first line. The **>** must be included immediately before the first letter. Otherwise, the database will not recognize the name and treat it as an unknown sequence. For example, **>DNA X** is the name here. Starting from the second line, type sequence or paste a sequence cut from another file. An example is given below (part of the sequence is shown here for brevity):

```
>DNA X
1  CAGTGTCTTCT AGATCCTGAG CCCTGACCAG CTCAGCCAAG ACCATGACC
51 AGCGCCGCGT GCCCTTCTCG CTA CTACTGCGGA GCCCCAGCTG GGAGCCGTT
101 CGGGACTGGT ACCCTGCCCA CAGCCGCCTC TTCGATCAAG CTTTCGGGGT
151 GCCTCGGTTT CCCGATGAGT GGTCTCAGTG GTTCAGCTCC GCTGGTTGGC
201 CCGGCTATGT GCGCCCTCTG CCCGCCGCGA CCGCCGAGGG CCCCAGCAG
```

6. Edit the sequence as you wish. Choose an appropriate option as shown below (bold letters):  
Advanced options for the Blast service:  
Expect **default**                      Cut off **default**                      Matrix **default**  
Strand **both**                              filter **default**  
Description **default**                      Alignments **default**
7. Check **In HTML format** to display the search results on the screen. Or, one may choose to check send reply to his/her e-mail address. However, the format of the results on the screen in the e-mail system may be strange. Thus, we recommend that one check In HTML format for a perfect display.
8. Click **Submit Query**. A warning sign of a possible review of the sequence by the third part will show up and ask a question to continue or to cancel.
9. Click **Continue** and the searching is carried out. Once the searching is complete, the sequence alignments will be exhibited, two by two, on the screen.
10. The results can be copied the pasted into a regular Microsoft word file. The Courier font should be used for compatibility with the searching format. The following sequences are examples. The submitted sequence is called **Query**, and the aligned sequence from the database is **Subject**. For brevity, only a part of the sequences is shown here. The first part of the results is a summary of different sequences in the database, which show similarity to the Query sequence. The second part is the similarity alignments of individual sequences. If one wishes to click the name at the beginning of each sequence, you can see detailed features of the searched sequences, including name, features, journal and title, and full length of DNA, cDNA/mRNA, and protein sequences. One can readily copy the sequences into an MS Word file or other files for further analysis. The last part of the results is mainly statistical analysis. An example is shown below:

DNA X  
(787 letters)

Database: Non-redundant GenBank+EMBL+DDBJ+PDB sequences 243,087 sequences;  
337,947,647 total letters.

Sequences producing High-scoring Segment Pairs:	Score	P(N)	N	High Probability	Smallest Sum
gb M86389 RATHSP27A Rat heat shock protein (Hsp27) mRNA, ...	3935	0.0	1		
gb S67755 S67755 hsp 27=heat shock protein 27 [rats, ...	1440	4.9e-301	4		
gb L11610 MUSHSP25PS Mus musculus heat shock 25 (HSP25) p...	2665	1.3e-266	4		
emb X51747 CLSHSP Cricetulus longicaudatus mRNA for sm...	1711	9.3e-264	4		
emb X14686 MURSPH Murine mRNA (pP25a) for 25-kDa mammal...	1361	5.0e-250	4		

**gb|M86389|RATHSP27A Rat** heat shock protein (Hsp27) mRNA, complete cds.  
Length = 787

Plus Strand HSPs:

Score = 3935 (1087.3 bits), Expect = 0.0, P = 0.0

Identities = 787/787 (100%), Positives = 787/787 (100%), Strand = Plus / Plus

Query: 1 CAGTGTCTTAGATCCTGAGCCCTGACCAGCTCAGCCAAGACCATGACCGAGCGCCGCGT 60

|||||

Sbjct: 1 CAGTGTCTTAGATCCTGAGCCCTGACCAGCTCAGCCAAGACCATGACCGAGCGCCGCGT 60

Query: 61 GCCCTTCTCGTACTGCGGAGCCCCAGCTGGGAGCCGTTCCGGGACTGGTACCCTGCCCA 120

|||||

Sbjct: 61 GCCCTTCTCGTACTGCGGAGCCCCAGCTGGGAGCCGTTCCGGGACTGGTACCCTGCCCA 120

Query: 121 CAGCCGCCTCTTCGATCAAGCTTTCGGGGTGCCTCGGTTTCCCGATGAGTGGTCTCAGTG 180

|||||

Sbjct: 121 CAGCCGCCTCTTCGATCAAGCTTTCGGGGTGCCTCGGTTTCCCGATGAGTGGTCTCAGTG 18

**gb|S67755|S67755** hsp 27=heat shock protein 27 [rats, Sprague-Dawley,  
Genomic, 1891 nt]  
Length = 1891

Plus Strand HSPs:

Score = 1440 (397.9 bits), Expect = 4.9e-301, Sum P(4) = 4.9e-301

Identities = 296/306 (96%), Positives = 296/306 (96%), Strand = Plus / Plus

Query: 482 ACGCTCCCTCCAGGTGTGGACCCACCCTGGTGTCTCTTCCCTGTCCCCTGAGGGCACA 541

| |||||

Sbjct: 1570 AGGCTCCCTCCAGGTGTGGACCCACCCTGGTGTCTCTTCCCTGTCCCCTGAGGGCACA 1629

Query: 542 CTCACCGTGGAGGCTCCGCTGCCCAAAGCAGTCACACAATCAGCGGAGATCACCATTCCG 601

|||||

Sbjct: 1630 CTCACCGTGGAGGCTCCGCTGCCCAAAGCAGTCACACAATCAGCGGAGATCACCATTCCG 1689

**gb|L11608|MUSHSP25A1** Mus musculus heat shock protein 25 (HSP25) gene, exon 1.  
Length = 760

Plus Strand HSPs:

Score = 1690 (467.0 bits), Expect = 6.9e-146, Sum P(2) = 6.9e-146  
Identities = 362/392 (92%), Positives = 362/392 (92%), Strand = Plus / Plus

```
Query:   33 CAGCCAAGACCATGACCGAGCGCCGCGTGCCCTTCTCGCTACTGCGGAGCCCCAGCTGGG  92
          |||
Sbjct:  272 CAGCCAAGAACATGACCGAGCGCCGCGTGCCCTTCTCGCTGCTGCGGAGCCCCAGCTGGG  331

Query:   93 AGCCGTTCCGGGACTGGTACCTGCCCCACAGCCGCTCTTCGATCAAGCTTTCGGGGTGC  152
          |||
Sbjct:  332 AACCATTCGGGACTGGTACCTGCACACAGCCGCTCTTCGATCAAGCTTTCGGGGTGC  391
```

### 6.2.2.2 BLASTX

This program allows the user to submit a Query sequence in nucleotides and the database will translate the nucleotide sequence into an amino acid sequence. After that, the database will search for similarity between the translated protein sequence and other protein sequences in the GenBank. The results will be displayed on the screen. The protocol for protein searching is pretty much like **blastn** except for the use of **blastX** for the program at step 4 described above. The example is as follows:

Query= cDNA X  
(100 letters)

Translating both strands of query sequence in all 6 reading frames

Database: Non-redundant GenBank CDS  
translations+PDB+SwissProt+SPupdate+PIR  
202,545 sequences; 57,487,450 total letters.

Sequences producing High-scoring Segment Pairs:	Reading Frame	High Score	Smallest Sum Probability P(N)	N
gi 55514 (X14686) p25 growth-related prote...	+2	103	1.8e-07	1
pir  JN0924 heat shock 27 protein - rat	+2	103	1.9e-07	1
gi 544758 (S67755) heat shock protein 27, H...	+2	103	1.9e-07	1
sp P42930 HS27_RAT HEAT SHOCK 27 KD PROTEIN (HSP 27)...	+2	103	1.9e-07	1
gi 55516 (X14687) p25 growth-related prote...	+2	103	1.9e-07	1

**gi|55514 (X14686)** p25 growth-related protein (pP25a) (AA 1-208) [Mus sp.]  
Length = 199

Plus Strand HSPs:

Score = 103 (47.4 bits), Expect = 1.8e-07, P = 1.8e-07  
Identities = 19/19 (100%), Positives = 19/19 (100%), Frame = +2

```
Query:   44 MTERRVPFSLLRSPSWEPF 100
          MTERRVPFSLLRSPSWEPF
Sbjct:   1 MTERRVPFSLLRSPSWEPF 19
```

**sp|P80492|BRA2\_BRAFL** BRACHYURY PROTEIN HOMOLOG 2 (T PROTEIN).  
Length = 440



Plus Strand HSPs:

Score = 39 (17.9 bits), Expect = 7.5, Sum P(2) = 1.0  
 Identities = 8/18 (44%), Positives = 10/18 (55%), Frame = +2  
 Query: 47 TERRVPFSLLRSPSWEPF 100  
           TER + +L P WE F  
 Sbjct: 31 TERDLKVTLGEKPLWEKF 48

Score = 29 (13.3 bits), Expect = 7.5, Sum P(2) = 1.0  
 Identities = 5/9 (55%), Positives = 6/9 (66%), Frame = +

### 6.2.2.3 BLASTP

This program is used for similarity searching between Query protein and any proteins in the database. The procedures are the same as described above except that a **peptide or protein sequence** needs to be typed or pasted in the sequence box and use **blastp** for program. A part of the results is shown below.

Query= Protein X  
 (28 letters)

Database: Non-redundant GenBank CDS  
 translations+PDB+SwissProt+SPupdate+PIR  
 202,545 sequences; 57,487,450 total letters.

Sequences producing High-scoring Segment Pairs:	High	Smallest	Probability
	Score	Sum	P(N)
			N
gi 55514 (X14686) p25 growth-related protein ...	160	2.1e-16	1
pir  JN0924 heat shock 27 protein - rat	160	2.2e-16	1
gi 544758 (S67755) heat shock protein 27, HSP ...	160	2.2e-16	1
sp P42930 HS27_RAT HEAT SHOCK 27 KD PROTEIN (HSP 27). ...	160	2.2e-16	1

gi|55514 (X14686) p25 growth-related protein (pP25a) (AA 1-208) [Mus sp.]  
 Length = 199

Score = 160 (74.9 bits), Expect = 2.1e-16, P = 2.1e-16  
 Identities = 28/28 (100%), Positives = 28/28 (100%)

Query: 1 MTERRVPFSLLRSPSWEPFRDWYPAHSR 28  
           MTERRVPFSLLRSPSWEPFRDWYPAHSR  
 Sbjct: 1 MTERRVPFSLLRSPSWEPFRDWYPAHSR 28

gnl|PID|e213334 (Z68160) D1046.3 [Caenorhabditis elegans]  
 Length = 269

Score = 50 (23.4 bits), Expect = 1.2, P = 0.71  
 Identities = 7/17 (41%), Positives = 12/17 (70%)

Query: 4 RRVFPFSLLRSPSWEPFR 20  
           R +PFS+++ P WE +  
 Sbjct: 151 REIPFSIIQFPIWEALK 167

## 6.3 COMPUTER ANALYSIS OF DNA SEQUENCES BY THE GCG PROGRAM

To obtain access to the GCG program, one needs a username and a password, which are given by appropriate persons who are in charge of the program. Once you type your username and password, the information of “Welcome to the . . .” will be displayed on your screen, followed by a prompt or dollar sign \$. We routinely use the GCG program to analyze nucleic acid and amino acid sequences. This section will give a “tour” of how to use the GCG program for your research.

### 6.3.1 ENTRY AND EDITING OF A SEQUENCE USING THE GCG PROGRAM

One needs to use the program **SeqEd**. It is especially designed for sequence entry and editing or modification.

#### 6.3.1.1 Sequence Entry

Sequence can be entered by keyboard typing or by cutting and pasting existing sequences from other files or sources.

1. At the prompt or after the \$ sign, type **SeqEd** and press **Enter**. What you can see on your screen is as follows:

```
***** K E Y B O A R D *****
```

```
: Type heading of text as you wish.
: Make comments as you wish.
:
:
```

```
|.....|.....|.....|.....|.....|.....|
0      10     20     30     40     50     60
```

```
|.....|.....|.....|.....|.....|.....|.....|.....|.....|
0      10     20     30     40     50     60     70     80     90
```

SeqEd of what sequence?

2. Type a name after the question. Make sure to type **.seq** after the name. For example, SeqEd of what sequence? **Test.seq** and **enter**. The cursor will move to the first base position and you can start to enter the sequence.
3. Type sequence with the keyboard or paste sequences from other files or GenBank. The length of the entered sequence will be denoted by numbers as follows and the cursor appears at the end of the sequence.  
By keyboard typing:

```
CAGCCAAGACCATGACCGAGCGCCGCGTGCCCTTCTCGCTACTGCGGAGCCCCAG
|.....|.....|.....|.....|.....|.....|.....|.....|
0      10     20     30     40     50     60

~~~~~^

|.....|.....|.....|.....|.....|.....|.....|.....|.....|
0      10     20     30     40     50     60     70     80     90
```

By paste of a file from other file:

```
TTGATACATGTACTTTCTGAAAAACTCAAATAAAAAGTTGGAACTACTGCTC
.....|.....|.....|.....|.....|.....|.....|.....|
 740     750     760     770     780     790

~~~~~^

|.....|.....|.....|.....|.....|.....|.....|.....|.....|
 0      100     200     300     400     500     600     700     800
```

4. Once the nucleotide sequence entry is complete and if there is no need for editing or modification, hold **Ctrl** and press **Z** key. The cursor will move to the bottom left-hand corner of the screen.
5. At the cursor, type **Exit** and then **Enter**, the sequence is saved. The name and length of the sequence are shown at the bottom of the screen. Two examples are given below:

```
CAGCCAAGACCATGACCGAGCGCCGCGTGCCCTTCTCGCTACTGCGGAGCCCCAG
|.....|.....|.....|.....|.....|.....|.....|.....|
0      10     20     30     40     50     60

~~~~~^

|.....|.....|.....|.....|.....|.....|.....|.....|.....|
0      10     20     30     40     50     60     70     80     90
```

"Test.seq" 55 nucleotides

```
TTGATACATGTACTTTCTGAAAAACTCAAATAAAAAGTTGGAACTACTGCTC
.....|.....|.....|.....|.....|.....|.....|.....|
 740     750     760     770     780     790

~~~~~^

|.....|.....|.....|.....|.....|.....|.....|.....|.....|
 0      100     200     300     400     500     600     700     800
```

"HSP27.seq" 787 nucleotides

It should be noted that if one types **Quit** and **Enter**, the sequence will not be saved, in which case one has to start all over again.

### 6.3.1.2 Sequence Editing or Modification

1. If one wishes to edit a sequence, after the \$ sign, type **SeqEd** and press **Enter**. At the end of “**SeqEd of what sequence?**”, type the sequence name to be edited. For instance, **Test.seq** and press **Enter**. The sequence with position numbers will show up on the screen as above.
2. To edit, move the cursor with the left or right arrow key to an appropriate position in the sequence. Hold **Ctrl** and press **Backspace** or **Delete** key to delete base(s) or insert more bases by keyboard or by cutting and pasting a sequence from another file as you wish.
3. When editing is complete, hold **Ctrl** and press **Z** to quit editing. Then, type **Exit** to save the edited sequence. However, if you type **Quit** and **Enter**, the sequence is not saved.

### 6.3.1.3 Review of Sequence Output

To see the entire sequence, at the prompt, type **Type**, followed by a space, and the name of the sequence to be reviewed. For example, **\$Type HSP27.seq** and press **Enter**. The entire sequence will be displayed on the screen as follows:

```
HSP27.seq Length: 787 June 17, 1996 21:00 Type: N Check: 740
  1 CAGTGCTTCT AGATCCTGAG CCCTGACCAG CTCAGCCAAG ACCATGACCG
 51 AGCGCCGCGT GCCCTTCTCG CTACTGCGGA GCCCCAGCTG GGAGCCGTTC
101 CGGGACTGGT ACCCTGCCCA CAGCCGCCTC TTCGATCAAG //
```

## 6.3.2 COMBINATION OR ASSEMBLY OF MULTIPLE FRAGMENTS INTO A SINGLE SEQUENCE

When one performs sequencing of large DNA molecules by primer walking, it is quite often the case that multiple short DNA sequences or fragments will be generated. Because these fragments contain overlapping ends, they can be assembled into a single sequence using the program of Fragment Assembly, which includes four procedures: **GelStart**, **GenEnter**, **GelMerge** or **GelOverlap**, and **GelAssemble**. Let us take the following fragments 1 to 3 as an example, assuming that they have 10-base overlapping ends and that their sequences are as follows:

```
Fragment 1 (30 bases): GACTAGACGATGCTGCTAGGCCTGACGTCG
Fragment 2 (30 bases): CCTGACGTCGGACTAGACGGCTGCGCGCTG
Fragment 3 (30 bases): CTGCGCTGGGGACACACCATAGCTCGC
```

### 6.3.2.1 Generating a New Project File Using the GelStart Program

After the \$ sign, type **GelStart** (i.e., **\$GelStart**) and press **Enter** key. The following information will show up on your screen. After each question, type an appropriate answer [see bold word(s)].

What is the name of your fragment assembly project? **Fragment**  
**GELSTART** cannot find this project. Is it a new one (\* No \*)? **yes**

You have a new project named "FRAGMENT".  
 Which vector sequence(s) would you like to be highlighted? **GACACACCA**  
 (You can type any short sequence.)  
 STOREVECTORS could not open the file GACACACCA.  
 This vector will not be highlighted. Check the file specification and run  
 GELStart/VECTors to reenter this vector. (You can ignore it.)  
 Which restriction site(s) would you like highlighted? **CTCAGA,GAATTC**  
 (You can enter any two restriction enzyme sequences, with a comma  
 between them)  
 Project FRAGMENT has 0 fragments in 0 contigs.  
 You are now ready to run the other fragment assembly programs.  
  
 \$

**6.3.2.2 Enter Sequences to Be Assembled into the Project  
 File Generated in the Previous Section (e.g.,  
 FRAGMENT) Using the GelEnter Program**

1. After the \$ sign, type **GelEnter** and press **Enter**. At the end of "**GelEnter of what sequence?**"; type the sequence name to be entered. For instance, **Fragment1** and press **Enter**. The sequence with position numbers will show up on the screen.
2. Press **Ctrl** and **Z** keys, and type heading or comments as you wish. After you finish or if you do not want heading and comments, press **Ctrl** and **Z** keys and begin to type sequence or paste a sequence of interest cut from another file at the cursor position. It should be noted that if the sequence to be entered is already in the GCG and saved as xx.seq (e.g, Fragment1.seq), one can simply type Fragment1.seq (e.g., "**GelEnter of what sequence?**" **Fragment1.seq**). In this case, the sequence will be automatically pulled out, so the sequence does not need to be retyped.
3. To edit, move the cursor with the left or right arrow keys to an appropriate position in the sequence. Hold **Ctrl** and press **Backspace** or **Delete** key to delete base(s). Or at the cursor, insert more bases by keyboard or by cutting and pasting a sequence from another file as you wish.
4. When editing is completed, hold **Ctrl** and press **Z** key to quit editing. Then, type **Exit** to save the edited sequence. However, if you type **Quit** and **Enter**, the sequence is not saved in the file. The following information will be displayed on your screen.

```
Fragment1          ***** K E Y B O A R D *****
Heading
comments

GACTAGACGATGCTGCTAGGCCTGACGTCG
|.....|.....|.....|.....|.....|.....|
0          10          20          30          40          50          60
```

```

~~~~~^
|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|
0      10     20     30     40     50     60     70     80     90
"Fragment1" (or "Fragment1.seq") 30 nucleotides

$

```

5. Repeat above steps 1–4 to enter other sequences to be assembled. For example, fragments 2–3 are displayed as follows:

```

CCTGACGTCGGACTAGACGGCTGCGCGCTG
|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|
0      10     20     30     40     50     60
~~~~~^
|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|
0      10     20     30     40     50     60     70     80
"Fragment2" 30 nucleotides

CTGCGCGCTGGGGGACACACCATAGCTCGC
|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|
0      10     20     30     40     50     60
~~~~~^
|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|. . . . .|
0      10     20     30     40     50     60     70     80     90
"Fragment3" 30 nucleotides

```

### 6.3.2.3 Compare and Identify Overlap Points of the Entered Fragments Using the GelMerge or GelOverlap Program

Once the fragment sequences have been entered and saved, their sequences can be analyzed to find out the overlapping regions with the **GelMerge** program. This program will align the fragments into assemblies called contigs. However, this program cannot allow you to see the alignment. To do so, you need to proceed to **D. GelAssemble**.

After the \$ sign, type **GelMerge** (\$GelMerge) and press **Enter**. The information will be shown on the screen as follows:

```


What word size (* 7 *)? 7
What fraction of the words in an overlap must match (*0.80*)? 0.8
What is the minimum overlap length (* 14 *)? 10
Reading ...
Comparing ...
Aligning ..
Writing .
      Input Contigs:    3
      Output Contigs:  1
      CPU time:        01.87

$

```

### 6.3.2.4 Assembly and Review of the Combined Sequence Using the GelAssemble Program


1. After the \$ sign, type **GelAssemble** (\$GelAssemble) and press **Enter**. The information will be shown on the screen as follows:



Contig 1 of 1

<Right-arrow> for next contig, <Left-arrow> for previous contig  
 <Ctrl>Z for Screen Mode, <Ctrl>K to load a contig:

2. Press the **Ctrl** and **K** keys to load a contig. The assembled sequences will be displayed on the screen.



3. Press the **Ctrl** and **Z** keys to move the cursor to the sequence. Review the entire sequence using the right or left arrow keys. The overlapping sequences of the present three fragments are indicated in bold letters.

### 6.3.3 IDENTIFICATION OF RESTRICTION ENZYME DIGESTION SITES, FRAGMENT SIZES, AND POTENTIAL PROTEIN TRANSLATIONS OF A DNA SEQUENCE

Cloning, digestion, manipulation, and characterization of DNA molecules mandate detailed analysis of restriction enzyme digests. This section will serve as a simplified guide for investigators seeking information about restriction enzyme digests of a specific DNA via the use of Mapping program in GCG.

### 6.3.3.1 Exhibition of Restriction Enzymes above Both Strands of a DNA Sequence and Possible Protein Translation below the Sequence Using the Map Program

1. Enter and save the DNA sequence of interest using the SeqEd program as described above. For example, a short sequence is saved as DNAX.seq.
2. After the \$ sign, type **Map** (\$Map) and press **Enter**. Information will be displayed on the screen. Type appropriate answers to questions (e.g., bold letters below) and press **Enter**.

```
(Linear) MAP of what sequence ? DNAX.seq
Begin (* 1 *) ? 1
End (* 60 *) ? 60
Select the enzymes: Type nothing or "" to get all enzymes. Type""?
Enzyme(* * *): *
What protein translations do you want:
a) frame 1, b) frame 2, c) frame 3, d) frame 4, e) frame 5
f) frame 6, t)hree forward frames, s)ix frames, o)pen frames only, n)o
protein translation, q)uit
Please select (capitalize for 3-letter) (* t *): o
What should I call the output file (* Dnax.map *)? DNAX.map

$
```

3. At the \$, type **DNAX.map** and press **Enter** key. The output will be displayed as follows. Therefore, one can choose appropriate enzyme(s) of interest to cut the DNA.

```
(Linear) MAP of: DNAX.seq check: 6764 from: 1 to: 60
With 215 enzymes: *

          B          B
          S          S
          p          M
    C      N      F      p      NC B1 CsP
    D v      a      HAuaMaTBa2T M      A lv a2 Avpv
    d i      I      hc4ewcamq8h w      c ai n8 liAu
    e J      I      aiHIo8ugI6a o      i IJ I6 uJII
    I I      I      IIIIIIIIIII I      I VI II IIII
          // / /          / ///
CTCAGCCAAGACCATGACCGAGCGCCGCGTGCCTTCTCGCTACTGCGGAGCCCCAGCTG
1 -----+-----+-----+-----+-----+-----+ 60
GAGTCGGTTCTGGTACTGGCTCGCGGCGCACGGGAAGAGCGATGACGCCTCGGGGTCGAC
a L S Q D H D R A P R A L L A T A E P Q L -
b S A K T M T E R R V P F S L L R S P S -
c Q P R P * -
1 -----+-----+-----+-----+-----+-----+ 60
d * Q P A G A -
e L W S W S R A G R A R R A V A S G W S -
f E A L V M V S R R T G K E S S R L G L Q -
```



Enzymes that do cut:

AciI	AluI	BanII	BmgI	Bsp1286I	Cac8I	CviJI	DdeI
Fnu4HI	HaeII	HhaI	MspA1I	MwoI	NlaIII	NlaIV	PvuII

Enzymes that do not cut: (Here is part of it.)

AatII	AccI	AceIII	AflIII	AflIII	AhdI	AlwI	Alw26I
AlwNI	ApaI	ApaBI	ApaLI	ApoI	AscI	AvaI	AvaII

\$

### 6.3.3.2 Identification of Specific Restriction Enzyme Cutting Sites and Sizes of Fragments Using MapSort Program

1. Enter and save the DNA sequence of interest using the SeqEd program as described above. For example, a short sequence is saved as DNAX.seq.
2. After the \$ sign, type **MapSort** (\$MapSort) and press **Enter**. Information will be displayed on the screen. Type appropriate answers to questions (e.g., boldface letters below) and press **Enter**.

(Linear) MAPSORT of what sequence ? **DNAX.seq**

Begin (\* 1 \*)? **1**

End (\* 60 \*)? **60**

Is this sequence circular (\* No \*)? **no**

Select the enzymes: Type nothing or "\*" to get all enzymes. Type "?"

Enzyme(\* \* \*): **\***

What should I call the output file (\* Dnax.mapsort \*)? **Enter**

Mapping ....

\$

3. At the \$, type **Dnax.mapsort** and press **Enter** key. The output will be displayed on the screen. Here is the part of the output.

(Linear) MAPSORT of: DNAX.seq check: 6764 from: 1 to: 60

With 215 enzymes: \*

June 18, 1996 16:33

AciI C'CG\_C

Cuts at:	0	25	46	60
Size:	25	21	14	

Fragments arranged by size:

25	21	14
----	----	----

Bsp1286I G\_dGCh' C

Cuts at:	0	33	53	60
Size:	33	20	7	

Fragments arranged by size:

33	20	7
----	----	---

HaeII r\_GCGC'y

Cuts at:	0	25	60
Size:	25	35	

PvuII CAG'CTG

Cuts at:	0	57	60
Size:	57	3	

Enzymes that do cut:

AciI	AluI	BanII	BmgI	Bsp1286I	Cac8I	CviJI	DdeI
Fnu4HI	HaeII	HhaI	MspAII	MwoI	NlaIII	NlaIV	PvuII

Enzymes that do not cut:

AatII	AccI	AceIII	AflII	AflIII	AhdI	AlwI	Alw26I
AlwNI	ApaI	ApaBI	ApaLI	ApoI	AscI	AvaI	AvaII
AvrII	BaeI	BaeI	BamHI	BanI	BbsI	BbvI	BccI

\$

### 6.3.4 COMPARISON OF SIMILARITY BETWEEN TWO SEQUENCES

To obtain this information, one may need to use the Comparison program of the GCG. Specifically, programs such as BestFit, Gap, or Gapshow will do the job. Gapshow requires a plotter being attached to a LaserWriter. Here is the introduction of an optimal alignment of the best segment of similarity between two sequences by the BestFit program.

1. Enter and save the two DNA sequences to be analyzed using the SeqEd program as described above. For example, two short DNA sequences are saved as sequence1.seq and sequence2.seq.
2. After the \$ sign, type **BestFit** (\$BestFit) and press **Enter**. Information will be displayed on the screen. Type appropriate answers to questions (e.g., boldface letters below) and press **Enter** key each time.

```
$ BestFit
BESTFIT of what sequence 1? sequence1.seq
```

```
Begin (* 1 *)? 1
End (* 200 *)? 200
Reverse (* No *)? no
```

to what sequence 2 (\* sequence1.seq \*)? **sequence2.seq**

```
Begin (* 1 *)? 1
End (* 150 *)? 150
Reverse (* No *)? no
```

What is the gap creation penalty (\* 5.00 \*) ? **3**  
 What is the gap extension penalty (\* 0.30 \*) ? **0.3**  
 What should I call the paired output display file (\* Sequence1.pair \*) ?  
**Enter** to accept the name

```
Aligning .....
      Gaps:      0
      Quality: 150.0
Quality Ratio:  1.000
% Similarity: 100.000
      Length: 150
```

\$

3. At the \$, type **type Sequence1.pair** and press **Enter** key. The output will be displayed on the screen.

```
$ type Sequence1.pair
BESTFIT of: Sequence1.Seq check: 7766 from: 1 to: 200
to: Sequence2.Seq check: 4913 from: 1 to: 150
```

Gap Weight:	3.000	Average Match:	1.000
Length Weight:	0.300	Average Mismatch:	-0.900
Quality:	150.0	Length:	150
Ratio:	1.000	Gaps:	0
Percent Similarity:	100.000	Percent Identity:	100.000

```
Sequence1.Seq x Sequence2.Seq June 18, 1996 17:15 ..
51  CGGGACTGGTACCCTGCCACAGCCGCCTCTTCGATCAAGCTTTCGGGGT 100
   |||
1  CGGGACTGGTACCCTGCCACAGCCGCCTCTTCGATCAAGCTTTCGGGGT 50
101 GCCTCGGTTTCCCGATGAGTGGTCTCAGTGGTTCAGCTCCGCTGGTTGGC 150
   |||
51  GCCTCGGTTTCCCGATGAGTGGTCTCAGTGGTTCAGCTCCGCTGGTTGGC 100
151 CCGGCTATGTGCGCCCTCTGCCCGCCGACCGCCGAGGGCCCCGAGCA 200
   |||
101 CCGGCTATGTGCGCCCTCTGCCCGCCGACCGCCGAGGGCCCCGAGCA 150
```

\$

### 6.3.5 TRANSLATION OF NUCLEIC ACID SEQUENCES INTO AMINO ACID SEQUENCES OR FROM AN AMINO ACID SEQUENCE INTO A NUCLEIC ACID SEQUENCE

The Translate program can be used for translation of nucleic acid sequences into amino acid sequences. On the other hand, the BackTranslate program is used to reversely translate amino acid sequences into nucleic acid sequences.

#### 6.3.5.1 Translate

1. Enter and save the DNA sequences to be translated using the SeqEd program as described above. For example, the short DNA sequences are saved as `sequence1.seq`.
2. After the \$ sign, type **Translate** (\$translate) and press **Enter**. Information will be displayed on the screen. Type appropriate answers to questions (e.g., boldface letters below) and press the **Enter** key each time.

```
$ Translate
TRANSLATE from what sequence(s)? sequence1.seq

      Begin (* 1 *)? 1
      End (* 200 *)? 200
      Reverse (* No *)? yes
Range begins TGCTG and ends GCGCT. Is this correct (* Yes *)? y
```

That is done, now would you like to:

- A) Add another exon from this sequence
- B) Add another exon from a new sequence
- C) Translate and then add more genes from this sequence
- D) Translate and then add more genes from a new sequence
- W) Translate assembly and write everything into a file

```
Please choose one (* W *): w
What should I call the output file (* Sequence1.pep *)? Enter
```

3. At the \$, type **type sequence1.pep** and press **Enter** key. The output will be displayed on the screen.

```
$ type sequence1.pep
TRANSLATE of: sequence1.seq /rev check: 7766 from: 1 to: 200
generated symbols 1 to: 66.
Sequence1.pep Length: 66 June 18, 1996 18:16 Type: P Check: 7296

  1 CCGALGGRGG QRAHIAGPTS GAEPLRPLIG KPRHPESLIE EAAVGRVPVP
51 ERLPAGAPQ* REGHAA

$
```

#### 6.3.5.2 BackTranslate

In this section, use of the `sequence1.pep` is shown as an example. Shown below is a part of the result that can help you recognize some ambiguous regions that may be useful for synthesis of probes.

```

$ Backtranslate
BACKTRANSLATE what sequence? sequencel.pep
    Begin (* 1 *)? 1
    End (* 66 *)? 66
Would you like to see:
a) table of back-translations and most probable sequence
b) table of back-translations and most ambiguous sequence
c) most probable sequence only
d) most ambiguous sequence only

Please choose one (* b *): b

Use what codon frequency file (*GenRunData:ecohigh.cod*)? Enter
What should I call the output file (*Sequencel.seq*)? Enter

$ type sequencel.seq

BACKTRANSLATE of: : Sequencel.Pep check: 7314 from: 1 to: 66
TRANSLATE of: sequencel.seq check: 7766 from: 1 to: 200
generated symbols 1 to: 66.
Codon usage for enteric bacterial (highly expressed) genes 7/19/83
Ser      Ala      Ala      Cys      Pro      Ser      Arg
UCC 0.37  GCU 0.35  GCU 0.35  UGC 0.51  CCG 0.77  UCC 0.37  CGU 0.74
UCC 0.34  GCA 0.28  GCA 0.28  UGU 0.49  CCA 0.15  UCU 0.34  CGC 0.25
AGC 0.20  GCG 0.26  GCG 0.26          CCU 0.08  AGC 0.20  CGA 0.01
UCG 0.04  GCC 0.10  GCC 0.10          CCC 0.00  UCG 0.04  AGG 0.00
AGU 0.03          AGU 0.03  AGA

Sequencel.Seq Length: 198 June 18, 1996 18:31 Type: N Check: 7709
  1  WSNCGNCGNT GYCCNWSNMG NTAYTGYGGN GCNCCNGCNG GNWSNMGNWS
 51  NNGNACNNGN ACNYTNCCNA CNGCNGCNWS NWSNATHAAR YTNWSNNGNT
101  GYYTNGGNTT YCCNATGWSN GGNyTNWSNG GNWSNGCNCC NYTNGTNGGN
151  CCNGCNATGT GYGCNYTNTG YCCNCCNMGN CCNCCNMNG CNCNCAR

$

```

### 6.3.6 IDENTIFICATION OF ENZYME DIGESTION SITES WITHIN A PEPTIDE OR PROTEIN

To get this information, one may need to use the PeptideMap program. For example, if a nucleic acid sequence is saved as **Nuc.seq** file and its amino acid file is **Nuc.pep**, one can readily use the PeptideMap program to find out the enzyme cutting site in the **Nuc.pep**.

1. Enter and save a new DNA sequence to be translated using the **SeqEd** program as described above. For example, a short DNA sequence is saved as **Nuc.seq**.
2. Translate **Nuc.seq** into protein and save it as **Nuc.pep**. If protein files are already in the GCG, the files can be directly used for mapping.
3. After the \$ sign, type **PeptideMap** (\$PeptideMap) and press **Enter**. Information will displayed on the screen. Type appropriate answers to questions (e.g., bold letters below) and press the **Enter** key each time.

```

$ Peptidemap
(Linear) (Peptide) MAP of what sequence ? Nuc.pep
    Begin (* 1 *)? 1
    End (* 20 *)? 20
Select the enzymes: Type nothing or "*" to get all enzymes. Type "?"
Enzyme(* * *):*
What should I call the output file (*Nuc.map*)? Enter
$ type nuc.map
(Linear) (Peptide) MAP of: Nuc.Pep  check: 6438  from: 1  to: 20
TRANSLATE of: nuc.seq check: 6445 from: 1 to: 60
generated symbols 1 to: 20.
With 11 enzymes: *

                S  PC
T              T C tTT rh
r              r n arr oy
y              y B ppy Em
p              p r hpp no
RS*ALTSSAKTMTERRVPFS
1 -----+-----+ 20

Enzymes that do cut:
Chymo    CnBr    ProEn    Staph    Tryp

Enzymes that do not cut:
NH2OH    NTCB    pH2.5

$

```

### 6.3.7 OBTAINING NUCLEOTIDE AND AMINO ACID SEQUENCES FROM GENBANK

As long as one knows the accession number of the sequence of interest, he or she can easily get access to and pull out the sequences using the **Fetch** program. If the accession number is not known, one may simply type a common name for the sequences just like a keyword search. All sequences under that name will be pulled out and copied into your directory.

1. At the \$ sign, type **fetch**, a space, and **accession number** or **name** of a sequence such as M86389 or hsp27 (**\$fetch M86389** or **\$fetch hsp27**), and then press **Enter**. The program will search for the sequence(s) and make copies from the GCG database into your directory with a specific name such as **M86389.Gb\_Ro** or **Mhsp27.Gb\_Pr**. Information will be displayed on the screen. Type appropriate answers to questions (e.g., bold letters below) and press the **Enter** key each time.

```

$ fetch M86389
M86389.Gb_Ro
$fetch hsp27
Mhsp27.Gb_Pr

```

- At the prompt, type **type**, space, **M86389.Gb\_Ro** (**\$type M86389.Gb\_Ro**) or **type**, space, **Mhsp27.Gb\_Pr**, (**\$type Mhsp27.Gb\_Pr**), and press **Enter**. The sequences from your directory will be displayed on your computer screen. Detailed information of each sequence includes three parts. The first part is the name and features of the sequence. The second part is the translated amino acid sequence. The last part is the entire length of DNA sequences. The examples are given below. Only part of the information is shown here for brevity.

```
$ Type M86389.Gb_Ro
LOCUS       RATHSP27A          787 bp ss-RNA  ROD      03-FEB-1992
DEFINITION   Rat heat shock protein (Hsp27) mRNA, complete cds.
ACCESSION   M86389
NID         g204664
KEYWORDS     heat shock protein 27.
SOURCE      Rattus norvegicus (strain Fisher) (library: Lambda

translation="MTERRVPFSLRLRSPSWEPFRDWYPAH SRLFDQAFGVPRFPDEWS
              QWFSSAGWPGYVRPLPAATAEGPAAVTLARPAFSRALNRQLSSGVSEIRQ  TADRWRVVS
              LDVNHFAPEELTVKTKEGVVEITGKHEERQDEHGYSISRCFTRKYTLPPGV  DPTLVSSS

M86389 Length: 787   May 24, 1996 15:15   Type: N   Check: 740  ..
      1  CAGTGCCTTCT AGATCCTGAG CCCTGACCAG CTCAGCCAAG ACCATGACCG
     51  AGCCGCCGCGT GCCCTTCTCG CTA CTGCGGA GCCCCAGCTG GGAGCCGTTT
    101  CGGGACTGGT ACCCTGCCCA CAGCCGCCTC TTCGATCAAG CTTTCGGGGT
    151  GCCTCGGTTT CCCGATGAGT GGTCTCAGTG GTTCAGCTCC GCTGGTTGGC
```

```
$ fetch hsp27
MHsp27.Gb_Pr
```

```
$ type hsp27.Gb_Pr
```

All the hsp27 sequences will be displayed in a pattern similar to that shown above (omitting the output for brevity).

It is highly recommended that one be familiar with and utilize bioinformation available from the NCBI Web site.

## REFERENCES

- Altschul, S. F., M. S. Boguski, W. Gish, and J. C. Wootton. 1994. Issues in searching molecular sequence databases. *Nature Genetics* 6: 119–129.
- Altschul, S. F., W. Gish, W. Miller, E. W. Myers, and D. J. Lipman. 1990. Basic local alignment search tools. *Journal of Molecular Biology* 215: 403–410.
- Recipon, H. E., G. D. Schuler, and M. S. Boguski. 1996. Informatics for molecular biologists. In *Current Protocols in Molecular Biology*, ed. F. M. Susubel, R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl, 19.0.1–19.3.38. NY: Wiley-Interscience.
- Berg, L., B. Butler, J. Devereux, I. Edelman, D. Katz, A. Kiefer, J. King, J. Murphy, S. Rose, M. Smith, and M. Schultz. 1991. The Sequence analysis software package by Genetics Computer, Inc. (the GCG Package), Version 7.0. WI: University of Wisconsin.
- Wootton, J. C. 1994. Non-globular domains in protein sequences: Automated segmentation using complexity measures. *Computers & Chemistry* 18: 269–285.





---

# 7 Characterization of DNA or Genes by Southern Blot Hybridization


## 7.1 INTRODUCTION

Characterization of DNA or the gene plays an important role in molecular biology research. A traditional and powerful tool that is widely used is Southern blot hybridization, which refers to a procedure in which different sizes of DNA molecules are immobilized from agarose gels onto a solid support such as nylon or nitrocellulose membranes and are then hybridized with a labeled DNA probe. In other words, Southern blot refers to DNA–DNA hybridization. This technique was developed by Southern, so named the Southern blot, that has been subjected to later modification.<sup>1–2</sup> This blotting method becomes one of the most fundamental and powerful tools used in molecular biology studies. It is a sensitive and reliable method. Its applications are remarkably broad, including general DNA analysis, gene cloning, screening and isolation, DNA mapping, mutant detection, identification of genetic diseases, and DNA amplification.<sup>2–5</sup>

Based on our extensive experience, detailed protocols are described in this chapter for a successful Southern blot hybridization using nonradioactive or radioactive probes.<sup>3–9</sup>

## 7.2 PRINCIPLES AND GENERAL CONSIDERATIONS

The general principles and procedures of Southern blot hybridization are outlined in Figure 7.1. Different DNA molecules are first separated based on their molecular weight by standard agarose gel electrophoresis, in which agarose gel serves as a molecular sieve and electrophoresis is the force for migration of negatively charged DNA in the electrical field. The separated double-stranded DNA species are denatured into single-stranded DNAs and are then blotted or immobilized onto a nylon or a nitrocellulose membrane. Usually, different positions of DNA molecules in an agarose gel are exactly blotted on their related positions on the membrane. After covalent cross-linking of DNA molecules on the membrane, specific band(s) of interest can be then hybridized and detected with a specific DNA probe. The nucleotide sequence of one strand of the DNA molecule is complementary to the nucleotide sequence of the other strand. It is exactly the base pairing or complementary rule that makes it possible for a single-stranded DNA probe to hybridize with its target sequences of single-stranded DNA on the membrane.



**FIGURE 7.1** Scheme for DNA analysis by Southern blot hybridization.

Agarose gel electrophoresis is commonly used for separation of DNA fragments. Agarose is extracted from seaweed algae and is a linear polymer that basically consists of D-galactose and L-galactose. Once agarose is melted and then allowed to harden, it forms a matrix that serves as a molecular sieve by which different sizes of DNA molecules can be separated from each other. Agarose is commercially available with varying degrees of purity. An Ultrapure grade agarose that is DNase-free is recommended for Southern blotting.

General considerations should be kept in mind when one carries out agarose gel electrophoresis of DNA. For an optimal separation of DNA species, agarose concentration should be determined based on the following principle. The larger the size of the DNA is, the lower the percentage of agarose that should be used.

Agarose % (w/v)	DNA Size (kb)
0.6%	1.0–20
0.7%	0.8–10
1.0%	0.5–8.0
1.2%	0.4–6.0
1.4%	0.2–4.0

In general, linear duplex molecules move through the gel matrix at a rate that is inversely proportional to the log of their molecular weight. Small DNA molecules move faster than large ones. Also, DNA conformation influences the migration rate.

The speed of DNA migration is supercoiled DNA > slightly coiled DNA > linear DNA > open circular DNA.

Transfer of DNA from agarose onto a solid nitrocellulose or nylon membrane can be carried out via capillary blot, electrophoretic blot, or vacuum blot methods. Each method has its merits and drawbacks. Although electrophoretic and vacuum blotting can offer faster transfer of DNA than capillary blot does, special instruments or systems are required and are not suitable for simultaneous blotting of multiple filters. The present chapter describes the capillary transfer method that is the most convenient, cheapest, and commonly used method in most laboratories. Nylon membranes are selected as transfer solid supports because they are more flexible and tear-resistant as compared with traditional nitrocellulose membranes. Tear-resistant nylon membranes are certainly more desirable for inexperienced students to handle.

### 7.3 ISOLATION OF DNA FOR ANALYSIS

Detailed protocols for isolation of high quality DNA are described in Chapter 15.

### 7.4 RESTRICTION ENZYME DIGESTION OF DNA

Before agarose gel electrophoresis, one may need to digest DNA molecules into fragments using appropriate restriction enzyme(s). Detailed instructions for standard restriction enzyme digestion are given in Chapter 4.

### 7.5 AGAROSE GEL ELECTROPHORESIS OF DNAs

1. Prepare agarose gel mixture in a clean bottle or a beaker as follows:

Component	Mini Gel	Medium Gel	Large Gel
1× TBE buffer	30 ml	75 ml	120 ml
Agarose (1% w/v)	0.3 g	0.75 g	1.2 g

Note: 1× TBE buffer may be diluted from 5× TBE stock solution in sterile dd.H<sub>2</sub>O. Because the agarose is only 1%, its volume can be ignored when calculating the total volume.

2. Place the bottle with the cap loose or beaker in a microwave oven and slightly heat the agarose mixture for 1 min. Briefly shake the bottle to rinse off any agarose powder that is stuck onto the glass walls. To completely melt the agarose, carry out gentle boiling for 1 to 3 min, depending on the volume of agarose mixture. Gently mix, open the cap, and allow the mixture to cool to 50 to 60°C at room temperature.
3. When the gel mixture is cooling, seal a clean gel tray at the two open ends with tape or a gasket and insert the comb in place. Add 1 µl of ethidium bromide (EtBr, 10 mg/ml in dd.H<sub>2</sub>O) per 10 ml of agarose gel solution at 50 to 60°C. Gently mix and slowly pour the mixture into the assembled gel tray and allow the gel to harden for 20 to 30 min at room temperature.

Caution: *EtBr* is a mutagen and a potential carcinogen and should be handled carefully. Gloves should be worn when working with this material. The gel running buffer containing *EtBr* should be collected in a special container for toxic waste disposal.

Notes: The function of *EtBr* is to stain DNA molecules by interlacing between the complementary strands of double-stranded DNA or in the regions of secondary structure in the case of ssDNA. It will fluoresce orange when illuminated with UV light. *EtBr* can be added to DNA samples using 1  $\mu$ l of *EtBr* (1 mg/ml) per 10  $\mu$ l of DNA solution, instead of using *EtBr* in agarose gel. However, the advantage of using *EtBr* in gel is that DNA bands can be stained and monitored with a UV lamp during electrophoresis. During the electrophoresis, the positively charged *EtBr* moves toward the negative pole but negatively charged DNA molecules migrate toward the positive pole. The drawback, however, is that running buffer and gel apparatus are likely contaminated with *EtBr*. Thus, an alternative way is to stain the gel after electrophoresis is completed. The gel can be stained with *EtBr* solution for 10 to 30 min followed by washing in distilled water for 3 to 5 min.

4. Slowly and vertically pull the comb out of the gel and remove the sealing tape or gasket from the gel tray. Place the gel tray in an electrophoresis apparatus and add a sufficient volume of 0.5 $\times$  TBE buffer or 1 $\times$  TAE buffer to the apparatus until the gel is covered to a depth of 1.5 to 2 mm above the gel. Please be advised that the comb should be pulled out from the gel slowly and vertically because any cracks that occur inside the wells of the gel will cause sample leaking when the sample is loaded. The top side of the gel where wells are located must be placed at the negative pole in the apparatus because the negatively charged DNA molecules will migrate toward the positive pole. Should any wells contain visible bubbles, they should be flushed out of the wells using a small pipette tip to flush the buffer up and down the well several times. Bubbles may adversely influence the loading of the samples and the electrophoresis. The concentration of TBE buffer should never be lower than 0.2 $\times$ . Otherwise, the gel may melt during electrophoresis. Prerunning the gel at a constant voltage for 10 min is optional.
5. Add 5 $\times$  loading buffer to the digested DNA sample and DNA standard marker to a final concentration of 1 $\times$ . Mix and carefully load DNA standard markers (0.2 to 2  $\mu$ g/well) into the very left-hand or the right-hand well, or into both left and right hand wells of the gel. Carefully load the samples, one by one, into appropriate wells in the submerged gel.
6. After all the samples are loaded, estimate the length of the gel between the two electrodes and set the power at 5 to 15 V/cm gel. Allow electrophoresis to proceed for 2 h or until the first blue dye reaches a distance of 1 cm from the end of the gel. If overnight running of the gel is desired, the total voltage should be determined empirically.
7. Stop electrophoresis of the gel and visualize DNA bands in the gel under UV light. Photograph the gel with a Polaroid camera.  
Caution: Wear safety glasses and gloves for protection against UV light.

Notes: *The purpose of taking a picture is to record different DNA molecules at different positions after electrophoresis, which is useful once a hybridized signal is detected later. It is recommended that pictures be taken with a fluorescent ruler placed beside the gel. A short exposure time is needed to obtain relatively sharp band(s) and a clear background, and a longer exposure time is needed to visualize very weak band(s). For genomic DNA, smears and some visible bands should appear in each of the lanes.*

## 7.6 BLOTTING OF DNAS ONTO NYLON MEMBRANES

### 7.6.1 METHOD A. UPWARD CAPILLARY TRANSFER (6 TO 12 H)

1. After photography, soak the gel in two volumes of 0.25 N HCl for 5 to 8 min with gentle agitating to depurinate DNA. Acid treatment can increase the efficiency of blotting of DNA species that are larger than 8 kb in length.
2. Replace the HCl solution with four volumes of denaturing solution (approximately 200 ml/gel) to denature dsDNA molecules into ssDNA for later hybridization with a probe. Allow the denaturation to proceed for 30 min at room temperature with shaking at 60 rev/min.
3. While the gel is being denatured, cut a piece of nylon membrane the same size as the gel, two pieces of 3MM Whatman filter paper the same size as the membrane, and a piece of relatively larger and longer size of 3MM Whatman filter paper, as compared with the size of the gel. The membrane filter should be marked at the upper left or the right corner with a pencil as a positional marker.


Notes: *(1) Gloves should be worn while cutting the membrane. (2) Positively charged nylon membranes are better than neutral nylon membranes to bind to negatively charged DNA. However, neutral nylon membranes usually have a lower background than positively charged membranes after detection.*

4. Briefly rinse the denatured gel with 500 ml/gel of distilled water twice and immerse the gel in four volumes of neutralization buffer to partially neutralize the gel conditions but not to renaturation of the ssDNA molecules. Allow the neutralization to proceed for 30 min at room temperature with gentle shaking.
5. Quickly rinse the gel once in distilled water and soak the gel and the cut membrane filter in 10× SSC solution for 20 min.
6. Place a clean glass plate or an equivalent Plexiglas blotting plate on top of a tray or container containing 500 to 1000 ml of 10× SSC buffer. Alternatively, a gel casting tray can be turned upside down to serve as a platform, and then place it in a clean container filled with 10× SSC up to the edges of the platform.

*Do not overfill the container to immerse the plate.*

7. Assemble blotting apparatus in the order shown (Figure 7.2).

Note: *Air bubbles should be removed from each layer of the blot by carefully rolling a pipette over the surface. It is important not to move the gel,*



**FIGURE 7.2** Standard assembly of upward capillary transfer of DNA from an agarose gel onto a nylon membrane filter.

*membrane, or blotting paper until transfer is complete. Otherwise, bubbles will be generated and band positions are likely to be changed.*

- (a) Place the presoaked large piece of 3MM Whatman filter paper on the flat plate with its two ends dipping into the 10× SSC buffer reservoir, which serves as a wick. Remove any bubbles underneath it by pressing or lifting one end of the filter and slowly laying it down on the plate.
- (b) Turn the gel over with the well-side facing down and carefully place the gel, starting from one side of the gel, onto the 3MM Whatman filter paper. Gently press the gel to remove any bubbles underneath.
- (c) Surround the top edges of the gel with Parafilm™ strips to prevent any of the top layers of the gel blot paper from coming in contact with the 10× SSC buffer reservoir, thus eliminating a potential short circuit.
- (d) Carefully overlay the gel with the soaked membrane, starting at one side of the gel, then slowly proceeding to the other end. The marked side of the membrane should face the gel. Wet the filter with some 10× SSC buffer if necessary and carefully remove any bubbles between the membrane and the gel, which can be done by lifting up and laying down the membrane.

*It is recommended that one should not press the membrane. Otherwise, bubbles may be produced underneath the gel that are not visible.*

- (e) Gently overlay the membrane with two pieces of the same size of 3MM Whatman paper, which have been prewetted in 10× SSC buffer.
- (f) Gently place four pieces of dry, precut 3MM Whatman paper and a stack of regular paper towels (5 to 10 cm thick), the same size as the membrane, on the top of 3MM Whatman filter paper.

*Do not distribute the filters lying underneath to prevent from producing bubbles.*

- (g) Put a glass plate, or an equivalent plate, on the top of the paper towel stack. Place a bottle or beaker containing approximately 500 ml of water on top of the plate to serve as a weight.

*Do not place too heavy a weight on the plate; otherwise, the gel may be crushed.*


8. Allow DNA to be transferred onto the membrane filter by capillary action for 6 h or overnight.
9. Remove the paper towel stack, the Whatman filter papers. Mark each of the well positions, if possible, on the membrane filter. The filter is then subjected to cross-linking using one of the methods below.
  - (a) Use UV-induced cross-linking for 30 to 60 s at the optimal setting in a UV cross-linker (Stratagene, Menlo Park, CA) according to the manufacturer's instructions.
  - (b) Alternatively, place the membrane on a piece of Saran Wrap™ that is then placed on a UV light box. Allow exposure to proceed at 254 to 312 nm for 5 min to induce cross-linking between the DNA and the membrane.
  - (c) Another option is to place the membrane between two pieces of 3MM Whatman filter paper to form a sandwich, which is then placed in a vacuum oven. Place a glass plate on the top of the sandwich to flatten the membrane during the baking process. Close the door of the oven and turn on the vacuum, and allow the membrane to bake for 1 to 2 h at 70 to 80°C. After baking is complete, allow the oven to cool for a while. Open the door and allow the sandwich to cool for 5 min before removing the membrane; otherwise, the membrane may curl up.

*Note: After transfer, the gel should be rather thin. The gel may be checked under UV light. An efficient transfer should have very little or no visible DNA staining left in the gel.*
10. Immediately proceed to prehybridization. Or, if one's schedule does not permit, air-dry the membrane filter at room temperature. Wrap the membrane with aluminum foil or with Saran Wrap and store it at 4°C until prehybridization. One can store it for up to 6 months.

*Gloves should be worn and/or changed when handling the membrane.*

## **7.6.2 METHOD B. DOWNWARD CAPILLARY TRANSFER (1 TO 1.5 H USING ALKALINE BUFFER OR 3 H USING NEUTRAL BUFFER)**

1. Carry out steps 1 to 5 in Method A (Section 7.6.1) if a neutral transfer buffer is used, or perform step 1 in Method A (Section 7.6.1) if an alkaline transfer buffer is to be utilized. For alkaline transfer, the HCl-treated gel is subjected to denaturation in alkaline denaturing solution for 2 × 30 min. The gel is then soaked in alkaline transfer buffer for 10 min. Proceed to the next step.
2. Carry out downward capillary transfer as shown in Figure 7.3.
  - (a) Place a stack of precut paper towels (8 to 10 cm thick) on a level bench.
  - (b) Place four pieces of dry 3MM Whatman filter paper on the paper towel stack.



**FIGURE 7.3** Standard assembly of downward capillary transfer of DNA from an agarose gel onto a nylon membrane filter.

- (c) Put two pieces of 3MM Whatman paper, presoaked in transfer buffer, on the dry 3MM Whatman filter papers.
- (d) Carefully overlay the wet 3MM Whatman filters with a presoaked nylon membrane and remove any bubbles underneath.
- (e) Place the soaked gel on the membrane. Make sure that no bubbles are evident between the gel and the membrane.
- (f) Carefully overlay the gel with two pieces of prewet 3MM Whatman filter paper.
- (g) Gently cover the entire stack with two relatively large pieces of Saran Wrap film that has a window precut the same size as the 3MM Whatman filter papers on top of the gel.
- (h) Fill two containers with approximately 200 ml of transfer buffer and place them near the two sides of the stack unit.
- (i) Carefully place a relatively long and large piece of 3MM Whatman filter paper on top of the 3MM Whatman paper on the gel, which serves as a wick. Allow the two sides of the wick to lay down over the Saran Wrap and let the ends be placed into the transfer buffer reservoir in the containers on both sides.
- (j) Place a light glass plate, or its equivalent, on the top of the stack and allow transfer to proceed for 1 to 1.5 h in alkaline transfer buffer, or 3 h in neutral transfer buffer.

*Please be advised that air bubbles should be removed from each layer of the blot by carefully rolling a pipette over the surface. It is important not to move the gel, membrane, and blotting paper until transfer is complete. Otherwise, bubbles will be generated and band positions are likely to be changed.*

3. After transfer is complete, remove the Whatman filter papers. After alkaline transfer, neutralize the membrane in 50 ml/membrane in 0.2 M sodium phosphate buffer (pH 6.8) for 4 min. After neutral transfer, soak the membrane in 5× SSC for 4 min to remove bits of gel from the membrane.



*Note: After transfer, the gel should be rather thin. The gel may be checked under UV light. An efficient transfer should have very little or no visible DNA staining left in the gel.*

4. Mark each of the well positions, if possible, on the membrane filter. The filter is then subjected to cross-linking using one of the methods described below.
  - (a) Perform UV-induced cross-linking for 30 to 60 s at an optimal setting in a UV cross-linker (Stratagene, CA) according to the manufacturer's instructions.
  - (b) Alternatively, place the membrane on a piece of Saran Wrap that is then placed on a UV light box. Allow exposure to proceed at 254 to 312 nm for 5 min to induce cross-linking between the DNA and the membrane.
  - (c) Another option is to place the membrane between two pieces of 3MM Whatman filter paper to form a sandwich, which is then placed in a vacuum oven. Place a glass plate on the top of the sandwich to flatten the membrane during baking. Close the door of the oven and turn on vacuum, and allow the membrane to bake for 1 to 2 h at 70 to 80°C. After baking is complete, allow the oven to cool for a while. Open the door and allow the sandwich to cool for 5 min before removing the membrane; otherwise, the membrane may roll up.
5. Immediately proceed to prehybridization. Or, if one's schedule does not permit, air-dry the membrane filter at room temperature. Wrap the membrane with aluminum foil or Saran Wrap and store at 4°C until prehybridization or store for up to 6 months.

*Gloves should be worn and/or changed when handling the membrane.*


## 7.7 PREPARATION OF PROBES

### 7.7.1 PREPARATION OF NONISOTOPIC DNA PROBES

There are three well-tested and commonly used labeling methods for preparation of nonisotopic probes. Each methodology works equally well but the time and costs needed are different. Protocol 1 is a modified direct labeling using the ECL kit from Amersham Life Science Corporation. One of the major advantages of this method is that it only takes 20 to 30 min to complete DNA labeling without using expensive dNTPs. The probes do not need to be denatured; instead, they can be directly used for hybridization. After hybridization and washing, the membrane filter is ready for detection of hybridized signal(s), thus eliminating antibody incubation that is required in Protocols 2 and 3. Reagents needed are commercially available (e.g., Boehringer Mannheim Corporation, Indianapolis, IN; or Amersham Life Science Corporation, Arlington Heights, IL).

#### 7.7.1.1 Protocol 1. Direct Labeling of ssDNA Using the ECL Kit

The primary principle of direct labeling begins with denaturation of dsDNA into ssDNA by heat. Negatively charged ssDNA species then interact with positively




**FIGURE 7.4** Nonradioactive labeling and detection of DNA in Southern blotting.

charged polymers conjugated to horseradish peroxidase. This enzyme can hydrolyze substrates such as luminol and generate photons or light, which will be recorded on an x-ray film as a result (Figure 7.4).

1. Transfer 100 to 200 ng of dsDNA of interest into a microcentrifuge tube and bring the total volume to 8  $\mu$ l with dd.H<sub>2</sub>O. Tightly cap the tube and denature the DNA by boiling for 10 min and quickly chill the tube on ice for 3 min. Briefly spin down and place it on ice until use.
2. Add 5  $\mu$ l of DNA labeling mixture and 8  $\mu$ l of fixer from the ECL labeling kit to the tube containing the denatured DNA.
3. Incubate the tube at 37°C for 20 min or at room temperature for 30 h.
4. Purify labeled DNA from free positively charged polymer molecules using an appropriate Sephadex column (e.g., G-10 or G-50) (Figure 7.5).

*Tip: Purification is very important to reduce hybridization background. Otherwise, the free positively charged polymers will interact with nontargeting DNA molecules on the membrane. As a result, all DNA or RNA bands will be detected. Sephadex G-10 or G-50 spin columns or Bio-Gel P-60 spin columns are very effective chromatography for separating labeled DNA from free polymers or unincorporated radioactive precursors such as [ $\alpha$ -<sup>32</sup>P]dCTP or [ $\alpha$ -<sup>32</sup>P]dATP and oligomers, which will be retained in the column. This is very useful when an optimal signal-to-noise ratio with 150 to 1500 bases in length of probe are generated for an optimal hybridization.*

- (a) Resuspend 2 to 5 g Sephadex G-10, G-50, or Bio-Gel P-60 in 50 to 100 ml of TEN buffer and equilibrate for at least 1 h at 4°C.
- (b) Insert a small amount of sterile glass wool into the bottom of a 1-ml disposable syringe or an equivalent using the barrel of the syringe to tamp the glass wool in place.




**FIGURE 7.5** Purification of labeled DNA using a G-10 or G-50 Sephadex chromatography column.

- (c) Fill the syringe with the Sephadex suspension until it is completely full.
- (d) Insert the column containing the suspension into a 15-ml disposable plastic tube and place the tube in a swinging-bucket rotor in a bench-top centrifuge. Centrifuge at 1600  $g$  for 4 min at room temperature.
- (e) Repeat the step, adding the suspended resin to the column and centrifuging at 1600  $g$  for 4 min until the packed volume reaches 0.9 ml in the syringe and remains unchanged after centrifugation.
- (f) Add 0.1 ml of 1 $\times$  TEN buffer (10 mM Tris-HCl, pH 8.0, 1 mM EDTA, pH 8.0, 100 mM NaCl) to the top of the column and recentrifuge as described above. Repeat this step twice.
- (g) Transfer the spin column to a fresh 15-ml disposable tube. Add the labeled DNA sample onto the top of the resin dropwise using a pipette. Note: *If the labeled DNA sample is less than 0.1 ml, dilute it to 0.1 ml in 1 $\times$  TEN buffer.*
- (h) Centrifuge at 1600  $g$  for 4 min at room temperature. Collect the void volume fluid containing labeled DNA. Store at  $-20^{\circ}\text{C}$  until use. Proceed to hybridization.

### 7.7.1.2 Protocol 2. Random Primer Digoxigenin Labeling of dsDNA

The basic principle of biotin or digoxigenin labeling is that, in a random labeling reaction, random hexanucleotide primers anneal to denatured DNA template. A new strand of DNA complementary to template DNA is catalyzed by the Klenow enzyme. During the incorporation of four nucleotides, one of them is pre-labeled by digoxigenin such as biotin-dUTP or DIG-dUTP. As a result, dsDNA probes are generated.



**FIGURE 7.6** Random labeling and detection of DNA using biotin–dUTP or DIG–dUTP.

After hybridization of the probe with the target DNA, an anti-digoxigenin antibody conjugated with an alkaline phosphatase will bind to the bound biotin–dUTP or digoxigenin–dUTP. The hybridized signal can then be detected using a chemiluminescent or colorimetric substrate. If one uses chemiluminescent substrates, the detected signal(s) can be exposed onto an x-ray film, whereas colorimetric substrates, NBT and BCIP, or X-Phosphate, can produce a purple/blue color (Figure 7.6).

1. Add an appropriate amount of dsDNA template of interest to a microcentrifuge tube and denature the DNA by boiling for 10 min and quickly chill the tube on ice for 4 min. Briefly spin down and place it on ice until use.
2. Set up a standard labeling reaction as follows:

Denatured DNA template (50 ng–2 µg)	5 µl
10× hexanucleotide primers mixture	2.5 µl
10× dNTPs mixture containing biotin–dUTP or DIG–dUTP	2.5 µl
dd.H <sub>2</sub> O	13.5 µl
<u>Klenow enzyme (2 units/µl)</u>	<u>1.5 µl</u>
Total volume	25 µl

3. Incubate at 37°C for 1 to 2 h.

*Note: The amount of labeled DNA depends on the amount of DNA template and on the length of incubation at 37°C. In our experience, the longer the incubation within a 12-h period, the more DNAs are labeled.*

4. Purify the labeled DNA using G-10 or G-50 Sephadex column chromatography as described in Protocol 1 (Section 7.7.1.1).
5. After the labeling is complete, the mixture can be boiled for 10 min and chilled on ice for 3 min. The probes can be immediately used for hybridization or stored at  $-20^{\circ}\text{C}$  or  $-80^{\circ}\text{C}$  until use. However, if precipitation is desired, add  $2.5\ \mu\text{l}$  of  $0.5\ \text{M}$  EDTA solution to stop the labeling reaction and carry out the following steps.
  - (a) Add 0.15 volumes of  $3\ \text{M}$  sodium acetate buffer (pH 5.2) and 2.5 volumes of chilled 100% ethanol to the mixture. Allow DNA to precipitate at  $-80^{\circ}\text{C}$  for 0.5 h.
  - (b) Centrifuge at  $12,000\ g$  for 6 min at room temperature, and carefully aspirate the supernatant. Briefly rinse the DNA pellet with 1 ml of 70% ethanol and dry the pellet under vacuum for 10 min.
  - (c) Dissolve the labeled DNA in  $50\ \mu\text{l}$  dd.H<sub>2</sub>O or TE buffer. Store at  $-20^{\circ}\text{C}$  before use.

Notes: (1) Labeled dsDNA must be denatured before use for hybridization. This can be done by boiling the DNA for 10 min then quickly chilling it on ice for 3 min. (2) After hybridization, the probe contained in the hybridization buffer can be stored at  $-20^{\circ}\text{C}$  and reused up to four times. (3) If necessary, the yield of the labeled DNA can be estimated by dot blotting of serial dilutions of commercially labeled control DNA and labeled sample DNA on a nylon membrane filter. After hybridization and detection, compare the spot intensities of the control and of the labeled DNA. However, this is optional.

### 7.7.1.3 Protocol 3. Nick Translation Labeling of dsDNA with Biotin-11-dUTP or Digoxigenin-11-dUTP

Nick translation labeling is also a widely used method for labeling DNA probes. In this method, dsDNA templates do not need to be denatured before labeling. The primary principle of nick translation labeling is that single-stranded nicks in dsDNA are first created by *DNase I*. *Escherichia coli* DNA polymerase I with 5' to 3' exonuclease activity removes stretches of ssDNA in the direction of 5'–3'. Almost simultaneously, the DNA polymerase I catalyzes the synthesis of a new strand of DNA from 5'–3', in which a prelabeled deoxyribonucleotide such as DIG-11-dUTP or biotin-11-dUTP is incorporated into the new strand DNA, producing dsDNA probes.

1. Set up, on ice, a labeling reaction as follows:

dsDNA template (1–3 $\mu\text{g}$ )	2–5 $\mu\text{l}$
10 $\times$ biotin or DIG DNA labeling mixture	2.5 $\mu\text{l}$
10 $\times$ reaction buffer	2.5 $\mu\text{l}$
<u><i>DNase I</i>/DNA polymerase I mixture</u>	<u>2.5 <math>\mu\text{l}</math></u>
Add dd.H <sub>2</sub> O to a final volume of	25 $\mu\text{l}$

2. Incubate at  $15^{\circ}\text{C}$  for 70 min. Process the probes as described in Protocol 2 (Section 7.7.1.2).

## 7.7.2 PREPARATION OF ISOTOPIC DNA PROBES

### 7.7.2.1 Protocol 1. Nick Translation Labeling of dsDNA

The procedures are very similar to those described for nonradioactive labeling except that one of four deoxynucleotides, which is radioactively labeled (e.g.,  $\alpha$ - $^{32}\text{P}$ dATP or  $\alpha$ - $^{32}\text{P}$ dCTP, commercially available), is used and is incorporated into the new DNA strand by base complementary to those of the template. A high specific activity ( $10^8$  cpm/ $\mu\text{g}$ ) of labeled DNA can be obtained using  $^{32}\text{P}$ dATP or  $^{32}\text{P}$ dCTP.

1. Set up a reaction in a tube on ice:

10 $\times$ nick translation buffer	5 $\mu\text{l}$
DNA sample	0.4–1 $\mu\text{g}$ in $<2$ $\mu\text{l}$
Mixture of three unlabeled dNTPs	10 $\mu\text{l}$
$[\alpha$ - $^{32}\text{P}$ ]dATP or $[\alpha$ - $^{32}\text{P}$ ]dCTP ( $>3000$ Ci/mmol)	4–7 $\mu\text{l}$
Diluted <i>DNase I</i> (10 ng/ml)	5 $\mu\text{l}$
<i>E. coli</i> DNA polymerase I	2.5–5 units
Add dd.H <sub>2</sub> O to a final volume of	50 $\mu\text{l}$

2. Incubate the reaction for 60 min at 15°C.

Notes: (1) *The temperature should not be higher than 18°C, which can generate “snapback” DNA by E. coli DNA polymerase I. “Snapback” DNA can lower the efficiency of hybridization.* (2) *Relatively longer incubation time (1 to 2 h) is acceptable. However, too long time of incubation may reduce the overall length of the labeled DNA.*

3. Stop the reaction by adding 2.5  $\mu\text{l}$  of 0.2 M EDTA (pH 8.0) solution. Place the tube on ice.
4. Determine the percentage of  $[\alpha$ - $^{32}\text{P}$ ]dCTP incorporated into the DNA using one of the following protocols. The labeled DNA should be purified using Sephadex column chromatography as described previously.

### 7.7.2.2 Protocol 2. DE-81 Filter-Binding Assay

1. Dilute 1  $\mu\text{l}$  of the labeled DNA in 99  $\mu\text{l}$  (1:100) of 0.2 M EDTA solution. Spot 3  $\mu\text{l}$  of the diluted sample, in duplicate, onto Whatman DE-81 circular filters (2.3 cm diameter). Air-dry the filters.
2. Wash one filter in 50 ml of 0.5 M sodium phosphate buffer (pH 6.8) for 5 min to remove unincorporated cpm. Repeat washing once. The other filter will be utilized directly for determination of total cpm in the sample.
3. Add an appropriate volume of scintillation fluid (about 10 ml) to each tube containing one of the filters. Determine the cpm in a scintillation counter according to the manufacturer’s instructions.

### 7.7.2.3 Protocol 3. Trichloroacetic Acid Precipitation

1. Dilute 1  $\mu\text{l}$  of the labeled mixture in 99  $\mu\text{l}$  (1:100) of 0.2 M EDTA solution. Spot 3  $\mu\text{l}$  of the diluted sample onto a glass fiber filter or a nitrocellulose filter for determining the total cpm in the sample. Air-dry the filter.

2. Add 3  $\mu\text{l}$  of the same diluted sample to a tube containing 100  $\mu\text{l}$  of 0.1 mg/ml carrier DNA or acetylated BSA and 20 mM EDTA.
3. Add 1.3 ml of ice-cold 10% trichloroacetic acid (TCA) and 1% sodium pyrophosphate to the mixture at step 2. Mix well and incubate the tube on ice for 20 to 25 min to precipitate the DNA.
4. Filter the precipitated DNA on a glass fiber filter or a nitrocellulose filter using vacuum. Wash the filter with 5 ml of ice-cold 10% TCA four times using vacuum. Rinse the filter with 5 ml acetone (for glass fiber filters only) or 5 ml of 95% ethanol. Air-dry the filter.
5. Add 10 to 15 ml of scintillation fluid to each tube. Count the total cpm and incorporated cpm in a scintillation counter according to the manufacturer's instructions.
6. Calculate the specific activity of the probe as follows:
  - (a) Calculate theoretical yield:

$$\text{ng theoretical yield} = \frac{\mu\text{Ci dNTP added} \times 4 \times 330 \text{ ng/nmol}}{\text{specific activity of the labeled dNTP} (\mu\text{Ci/nmol})}$$

- (b) Calculate the percentage of incorporation:

$$\% \text{ incorporation} = \frac{\text{cpm incorporated}}{\text{total cpm}} \times 100$$

- (c) Calculate the amount of DNA synthesized:

$$\text{ng DNA synthesized} = \% \text{ incorporation} \times 0.01 \times \text{theoretical yield}$$

- (d) Calculate the specific activity of the prepared probe:

$$\text{cpm}/\mu\text{g} = \frac{\text{total cpm incorporated} (\text{cpm incorporated} \times 33.3 \times 50)}{(\text{ng DNA synthesized} + \text{ng input DNA}) \times 0.001 \mu\text{g/ng}} \times 100$$

Note: The factor 33.3 comes from using 3  $\mu\text{l}$  of 1:100 dilution for the filter-binding or TCA precipitation assay. The factor 50 is derived from using 1  $\mu\text{l}$  of the total 50  $\mu\text{l}$  reaction for 1:100 dilution. For example, given that 25 ng DNA is to be labeled and that 50  $\mu\text{Ci}[\alpha\text{-}^{32}\text{P}]\text{dCTP}$  (3000 Ci/mmol) is used in 50  $\mu\text{l}$  of a standard reaction, and assuming that  $4.92 \times 10^4$  cpm is precipitated by TCA and that  $5.28 \times 10^4$  cpm is the total cpm in the sample, the calculations are performed as follows:

$$\text{Theoretical yield} = \frac{50 \mu\text{Ci} \times 4 \times 330 \text{ ng/nmol}}{3000 \mu\text{Ci/nmol}}$$

$$= 22 \text{ ng}$$

$$\% \text{ incorporation} = \frac{4.92 \times 10^4}{5.28 \times 10^4} \times 100$$

$$= 93\%$$

$$\begin{aligned}\text{DNA synthesized} &= 0.93 \times 0.01 \times 22 \\ &= 20.5 \text{ ng}\end{aligned}$$

$$\begin{aligned}\text{Specific activity} &= \frac{4.92 \times 10^4 \times 33.3 \times 50}{(20.5 \text{ ng} + 25 \text{ ng}) \times 0.001 \text{ } \mu\text{g/ng}} \times 100 \\ &= 1.8 \times 10^9 \text{ cpm/} \mu\text{g DNA}\end{aligned}$$

Note: The specific activity of  $2 \times 10^{8-9}$  cpm/ $\mu$ g is considered to be a high specific activity that should be used in Southern, northern, or equivalent hybridizations.

#### 7.7.2.4 Protocol 4. Random Primer Labeling of dsDNA

The general procedures are similar to those described for nonradioactive labeling of DNA except that a radioactively labeled nucleotide is used.

1. Set up a reaction mixture by adding the following components, in the order shown below, in a fresh microcentrifuge tube placed on ice.

5 $\times$ labeling buffer	10 $\mu$ l
Denatured DNA template (25–50 ng)	1 $\mu$ l
Three unlabeled dNTP mixture (500 $\mu$ M each)	2 $\mu$ l
$[\alpha\text{-}^{32}\text{P}]\text{dCTP}$ or $[\alpha\text{-}^{32}\text{P}]\text{dATP}$ (>3000 Ci/mmol)	2.5–4 $\mu$ l
<u>Klenow enzyme</u>	<u>5 units</u>
Add dd.H <sub>2</sub> O to a final volume of	50 $\mu$ l

Note:  $[\alpha\text{-}^{32}\text{P}]\text{dCTP}$  or  $[\alpha\text{-}^{32}\text{P}]\text{dATP}$  (3000 Ci/mmol) used in the reaction should not be >5  $\mu$ l; otherwise, the background will be high.

2. Mix well and incubate the reaction at room temperature for 1 to 1.5 h.
3. Stop the reaction mixture by adding 2  $\mu$ l of 0.2 M EDTA and place on ice. Purify the labeled DNA as described above. Store at  $-20^\circ\text{C}$  until use.

#### 7.7.2.5 Protocol 5. 3'-End Labeling of ssDNA (Oligonucleotides) with a Terminal Transferase

1. 3'-tailing of ssDNA primers
  - (a) Set up a reaction as follows:

5 $\times$ terminal transferase buffer	5 $\mu$ l
ssDNA primers	2 pmol
$[\alpha\text{-}^{32}\text{P}]\text{dATP}$ (800 Ci/mmol)	1.6 $\mu$ l
<u>Terminal transferase (10–20 units/<math>\mu</math>l)</u>	<u>1 <math>\mu</math>l</u>
Add dd.H <sub>2</sub> O to a final volume of	25 $\mu$ l

- (b) Incubate at  $37^\circ\text{C}$  for 1 h and stop the reaction by heating at  $70^\circ\text{C}$  for 10 min to inactivate the enzyme.



Note: *Multiple [ $\alpha$ - $^{32}$ P]dATPs were added to the 3'-end of the DNA.*

- (c) Calculate the percentage of incorporation and the specific activity of the probe.

Note: *The procedures for TCA precipitation assay and DE81 filter binding assay are described in the section on nick translation labeling.*

$$\% \text{ incorporation} = \frac{\text{cpm incorporated}}{\text{total cpm}} \times 100$$

$$\text{Specific activity} = \frac{\% \text{ incorporation} \times \text{total cpm added to the reaction}}{\text{mg of DNA in the reaction mixture}} \times 100$$

Example:  $49,000/51,000 \times 100 = 96\%$

$$\frac{0.96 \times 3.5 \times 10^6}{0.09 \text{ mg}} \times 100 = 3.7 \times 10^7 \text{ cpm}/\mu\text{g DNA}$$

2. 3'-end labeling of ssDNA with a single [ $\alpha$ - $^{32}$ P]cordycepin-5'-triphosphate lacking the 3'-OH.

- (a) Set up a reaction as follows:

5 $\times$ terminal transferase buffer	10 $\mu$ l
ssDNA primers	10 pmol
[ $\alpha$ - $^{32}$ P]cordycepin-5'-phosphate (3000 Ci/mmol)	7.5 $\mu$ l
<u>Terminal transferase (10–20 u/<math>\mu</math>l)</u>	<u>2 <math>\mu</math>l</u>
Add dd.H <sub>2</sub> O to a final volume of	50 $\mu$ l

- (b) Incubate the reaction at 37°C for 1 h.  
 (c) Stop the reaction by incubating at 70°C for 10 min. The labeled reaction can be directly used in hybridization or purified as described for 3'-end labeling in order to fill the recessed 3' ends of dsDNA.

## 7.8 PREHYBRIDIZATION AND HYBRIDIZATION

1. Prepare hybridization buffer based on nonradioactively or radioactively labeled DNA. One filter (10  $\times$  12 cm<sup>2</sup>) needs 10 to 15 ml buffer, or 30 to 40 ml of buffer is sufficient for four to six filters in a single hybridization container.
2. If the blotted membrane is predried, immerse it in 5 $\times$  SSC for 5 min at room temperature to equilibrate the filter.

Note: *Do not allow the filters to dry out during subsequent steps. Otherwise, a high background and/or anomalous results will occur.*

3. Carefully roll the filter and insert it into a hybridization bottle or an equivalent container containing 10 to 15 ml/filter of appropriate prehybridization solution, depending on the isotopic or nonisotopic DNA probe used. Cap the bottle or container and place it in a hybridization oven or equivalent

shaker with controlled speed and temperature. Allow prehybridization to proceed for 1.5 h with gentle agitation.

Notes:

- (a) *It is strongly recommended that one not use traditional plastic hybridization bags because it is usually not easy to remove air bubbles nor can they be well sealed. This will result in leaking and contamination. An appropriate size of plastic beaker or tray or hybridization bottle is the best type of hybridization container to use for this purpose.*
  - (b) *Temperature depends on prehybridization buffer. The temperature should be 42 to 55°C if the buffer contains 30% to 40% (for low stringency conditions) or 50% (for high stringency conditions) formamide. If the buffer contains no formamide, the temperature can be 65°C. High stringency conditions can prevent nonspecific cross-binding during hybridization. Assuming that the buffer used for this experiment contains 50% formamide, in our experience, one can set up the temperature for this experiment at 42°C regardless of which DNA labeling method is used.*
  - (c) *It is highly recommended that one use a regular culture shaker with a cover, controlled speed, and temperature as a hybridization chamber. Such a chamber is easy to handle. One can simply place the hybridization beaker or tray containing the filters and buffer on the shaker in the chamber. Multiple filters can be placed in one container containing an appropriate volume of hybridization buffer. This is particularly useful for biotechnology laboratory classes. In contrast, a commercial hybridization oven may be difficult to operate. It takes time to roll up the filters with a matrix screen and place the roll inside the hybridization bottle, during which time, air bubbles are easily generated.*
4. If the probes are dsDNA, denature the probe to ssDNA in boiling water for 10 min and immediately chill on ice for 4 min. Briefly spin down. *Please note that this is a critical step. If the probes are not completely denatured, a weak or no hybridization signal will occur. However, if the probes prepared are ssDNA, denaturation is not necessary.*
  5. Dilute the probes with 0.8 ml of hybridization solution. Replace prehybridization buffer with fresh prehybridization buffer and add the diluted probes to the freshly replaced prehybridization buffer. Alternatively, diluted probes may be directly added to the old prehybridization buffer without replacing it. Place the container back in hybridization oven or shaker and allow hybridization to proceed for 6 h to overnight under the same conditions as prehybridization.

## 7.9 WASHING AND/OR INCUBATION OF ANTIBODIES

### 7.9.1 PROTOCOL A. WASHING OF FILTERS HYBRIDIZED WITH ECL-LABELED PROBES

1. Wash the filters in 200 ml of 2× SSC solution containing 0.1% SDS (w/v) for 10 min at 42°C with gentle agitation.

2. Wash the filters in 200 ml of 1× SSC solution containing 0.1% SDS (w/v) for 10 min at room temperature with gentle agitation.

### **7.9.2 PROTOCOL B. WASHING AND ANTIBODY INCUBATION OF FILTERS HYBRIDIZED WITH BIOTIN-DUTP- OR DIG-UTP-LABELED PROBES**

1. Wash the filters in 200 ml of 2× SSC solution containing 0.1% SDS (w/v) for 15 min at 55 to 60°C with slow shaking. Repeat it once.
2. Wash the filters in 200 ml of 1× SSC solution containing 0.1% SDS (w/v) for 15 min at room temperature with slow shaking.
3. Block nonspecific binding sites on the membrane in 200 ml of blocking buffer for 1 h at room temperature.
4. Incubate the filters in a solution (10 to 15 ml/filter) containing anti-DIG-alkaline phosphatase antibodies (Boehringer Mannheim Corporation) diluted at 1:5000 to 1:10,000 in blocking buffer with 1% nonfat dry milk. Allow incubation to proceed for 60 min at room temperature with gentle agitation.
5. Transfer the filter to a clean tray containing 200 ml of washing buffer for 2×15 min at room temperature.

*Note: The used antibody solution may be stored at 4°C for up to 1 month and reused for four to five times.*

6. Equilibrate the filter in 100 ml of predetection buffer for 2 to 3 min. Proceed to detection.

### **7.9.3 PROTOCOL C. WASHING OF FILTERS HYBRIDIZED WITH ISOTOPIC PROBES**

1. Wash the filters in 200 ml of 2× SSC solution containing 0.1% SDS (w/v) for 15 min at 65°C with slow shaking. Repeat this step once.
2. Wash the filters in 200 ml of 0.5× SSC solution containing 0.1% SDS (w/v) for 15 min at room temperature with slow shaking. Proceed to detection.

## **7.10 DETECTION OF HYBRIDIZED SIGNAL(S)**

### **7.10.1 METHOD A. CHEMILUMINESCENCE DETECTION**

1. Place a piece of Saran Wrap film on a bench and add 0.4 ml/filter (10 × 12 cm<sup>2</sup>) of detection reagents 1 and 2 from the ECL kit (Amersham Life Science Corporation) or 0.8 ml of the Lumi-Phos 530 (Boehringer Mannheim Corporation) to the center of the Saran Wrap film.
2. Wear gloves and briefly damp the filter to remove excess washing solution and thoroughly wet the DNA binding side by lifting and overlaying the filter with the solution several times.
3. Wrap the filter with Saran Wrap film, leaving two ends of the film unfolded. Place the wrapped filter on a paper towel and using another piece of paper towel, carefully press the wrapped filter to remove excess detection solution from the unfolded ends of the Saran Wrap film. Excess detection solution will most likely cause a high background.

4. Completely wrap the filter and place it in an exposure cassette with DNA binding side facing up. Tape the four corners of the filter.
5. In a dark room with the safe light on, overlay the filter with a piece of x-ray film and close the cassette. Allow exposure to proceed at room temperature for 10 s to 15 h, depending on the intensity of detected signal.
6. In a dark room, develop and fix the film in an appropriate developer and fixer, respectively. If an x-ray processor is available, development, fixation, washing, and drying of the film can be completed in 2 min. If a hybridized signal is detected, it appears as a black band on the film.

*Note: Multiple films may be needed to be exposed and processed until the appropriate intensity of the signals is obtained. Exposure for more than 4 h may generate a high black background. In our experience, good hybridization and detection should display sharp bands within 1.5 h. In addition, the film should be slightly overexposed in order to obtain a relatively black background that will help identify the sizes of the band(s) as compared with the marks made previously.*

### **7.10.2 METHOD B. COLORIMETRIC DETECTION OF FILTERS HYBRIDIZED WITH ANTIBODY-CONJUGATED PROBES**

1. After hybridization and washing, place the filter in color developing solution (10 ml/filter,  $10 \times 12 \text{ cm}^2$ ) containing 40  $\mu\text{l}$  of NBT stock solution and 30  $\mu\text{l}$  of BCIP stock solution. NBT and BCIP stock solutions are commercially available.
2. Allow color to develop in the dark at room temperature for 15 to 120 min or until the desired level of detection is obtained. Positive signals should appear as a blue/purple color.

### **7.10.3 METHOD C. DETECTION OF SIGNALS BY AUTORADIOGRAPHY**

If the isotopic probes are used for hybridization, autoradiography should be used for the detection of signals.

1. Air-dry the washed filters and individually wrap the filters with a piece of Saran Wrap film and place the wrapped filter in an exposure cassette with the DNA-binding side facing up. Tape the four corners of the filter.
2. In a dark room with the safe light on, overlay the filter with an x-ray film and close the cassette. Allow exposure to proceed at  $-80^\circ\text{C}$  for 2 h to 5 days, depending on the intensity of the detected signals.
3. In a dark room, develop and fix the film in an appropriate developer and fixer, respectively. If an x-ray processor is available, development, fixation, washing, and drying of the film can be completed in 2 min. If a hybridized signal is detected, it appears as a black band on the film.

#### **Materials needed**

- 5 $\times$  TBE buffer  
600 ml dd.H<sub>2</sub>O

- 0.45 M boric acid (27.5 g)
- 0.45 M Tris base (54 g)
- 10 mM EDTA (20 ml 0.5 M EDTA, pH 8.0)
- Dissolve well after each addition. Add dd.H<sub>2</sub>O to 1 l. Autoclave.
- *Ethidium bromide*
  - 10 mg/ml in dd.H<sub>2</sub>O; dissolve well and keep in a dark or brown bottle at 4°C.
  - Caution: *EtBr is extremely toxic and should be handled carefully.*
- *5× Loading buffer*
  - 50% glycerol
  - 2 mM EDTA
  - 0.25% bromphenol blue
  - 0.25% xylene cyanol
  - Dissolve well and store at 4°C.
- *10× Nick translation buffer*
  - 0.5 M Tris-HCl, pH 7.5
  - 0.1 M MgSO<sub>4</sub>
  - 1 mM DTT
  - 500 µg/ml BSA (Fraction V, Sigma Chemical Corporation) (optional)
  - Aliquot the stock solution and store at -20°C until use
- *Unlabeled dNTP stock solutions*
  - 1.5 mM each dNTP
- *Radioactive labeled dNTP (commercially available)*
  - [ $\alpha$ -<sup>32</sup>P]dATP or [ $\alpha$ -<sup>32</sup>P]dCTP (3000 Ci/mmol)
- *Pancreatic DNase I solution*
  - DNase I* (1 mg/ml) in a solution containing 0.15 M NaCl and 50% glycerol
  - Aliquot and store at -20°C.
- *E. coli DNA polymerase I solution*
  - Commercial suppliers
- *Stop solution*
  - 0.2 M EDTA, pH 8.0
- *1× TEN buffer*
  - 10 mM Tris-HCl, pH 8.0
  - 1 mM EDTA, pH 8.0
  - 0.1 M NaCl
- *Sephadex G-10, G-50, or Bio-Gel P-60 powder*
  - Commercial suppliers
- *5× Labeling buffer*
  - 0.25 M Tris-HCl, pH 8.0 (from stock solution)
  - 25 mM MgCl<sub>2</sub>
  - 10 mM DTT (dithiothreitol)
  - 1 mM HEPES buffer, pH 6.6 (from stock solution)
  - 26 A<sub>260</sub> units/ml random hexadeoxyribonucleotides
- *Three unlabeled dNTPs solutions*
  - 1.5 mM of each dNTP

- *Klenow enzyme*
  - 5 unit/ $\mu$ l, labeling grade
  - $[\alpha\text{-}^{32}\text{P}]\text{dCTP}$  or  $[\alpha\text{-}^{32}\text{P}]\text{dATP}$
  - Specific activity, 3000 Ci/mmol
- *TE buffer*
  - 10 mM Tris-HCl, pH 8.0
  - 1 mM EDTA
- *5 $\times$  Terminal transferase buffer*
  - 0.5 M cacodylate, pH 6.8
  - 1 mM  $\text{CoCl}_2$
  - 0.5 mM DTT
  - 500  $\mu\text{g/ml}$  BSA
- *ssDNA primers*
  - Prepared from bacteriophage M13 or phagemid, sscDNA, or ssDNA isolated from DNA
- *Terminal transferase*
  - From available commercial source (Promega Incorporation)
- *$[\alpha\text{-}^{32}\text{P}]\text{Cordycepin-5'-phosphate analog}$* 
  - 3000 Ci/mmol
- *Depurination solution*
  - 0.25 M HCl
- *Denaturing solution*
  - 0.5 M NaOH
  - 1.5 M NaCl
- *Neutralization solution*
  - 1.5 M NaCl
  - 1 M Tris-HCl, pH 7.5
- *Alkaline denaturing solution*
  - 3 M NaCl
  - 0.5 N NaOH
- *Alkaline transfer solution*
  - 3 M NaCl, 8 mM NaOH
- *20 $\times$  SSC solution (1 l)*
  - 175.3 g NaCl
  - 88.4 sodium citrate
  - Adjust the pH to 7.5 with HCl
- *Prehybridization buffer for probes prepared with the ECL kit*
  - Add 0.3 g blocking reagent per 10 ml of hybridization buffer. Allow the blocking powder to dissolve in the buffer for 60 min at room temperature or 30 min at 42°C with vigorous agitation.
- *Hybridization buffer for probes prepared using the ECL kit*
  - Add probe to an appropriate volume of freshly prepared prehybridization buffer.
- *Prehybridization buffer for probes prepared with biotin-dUTP or DIG-dUTP*
  - 5 $\times$  SSC

- 0.1% (w/v) *N*-Lauroylsarcosine
- 0.02% (w/v) Sodium dodecyl sulfate (SDS)
- 1% (w/v) Blocking reagent
- 50% (v/v) Formamide
- Dissolve well on a heating plate with stirring at 65°C after each addition. Add sterile water to final volume.
- *Hybridization buffer for probes prepared with biotin-dUTP or DIG-dUTP*  
Add denatured, biotin-dUTP- or DIG-dUTP-labeled probe to an appropriate volume of fresh prehybridization buffer.
- *50× Denhardt's solution*  
1% (w/v) BSA (bovine serum albumin)  
1% (w/v) Ficoll (Type 400, Pharmacia)  
1% (w/v) PVP (polyvinylpyrrolidone)  
Dissolve well after each addition, and adjust the final volume into 500 ml aliquot with distilled water and sterile filter. Divide the solution to 50 ml each and store at -20°C. Dilute tenfold into prehybridization and hybridization buffers.
- *Prehybridization buffer for isotopic probes*  
5× SSC  
0.5% SDS  
5× Denhardt's reagent  
0.2% Denatured and sheared salmon sperm DNA
- *Hybridization buffer for isotopic probes*  
5× SSC  
0.5% SDS  
5× Denhardt's reagents  
0.2% Denatured salmon sperm DNA  
[ $\alpha$ -<sup>32</sup>P]-Labeled DNA probe
- *Washing buffer*  
150 mM NaCl  
100 mM Tris-HCl, pH 7.5
- *Blocking buffer*  
5% (w/v) nonfat dry milk  
150 mM NaCl  
100 mM Tris-HCl, pH 7.5  
Dissolve well with stirring at room temperature
- *Predetection/color developing buffer*  
0.1 M Tris-HCl, pH 9.5  
0.1 M NaCl  
50 mM MgCl<sub>2</sub>
- *NBT stock solution*  
75 mg/ml Nitroblue tetrazolium (NBT) salt in 70% (v/v) dimethylformamide
- *BCIP stock solution*  
50 mg/ml 5-Bromo-4-chloro-3-indolyl phosphate (BCIP or X-phosphate) in 100% dimethylformamide

- *Other equipment and supplier*
  - A microcentrifuge
  - Sterile microcentrifuge tubes (0.5 ml)
  - Pipettes or pipetman (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
  - Sterile pipette tips (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
  - Gel casting tray
  - Gel combs
  - Electrophoresis apparatus
  - DC power supply
  - Small or medium size DNA electrophoresis apparatus depending on samples to be run
  - Ultrapure agarose powder
  - Nylon membranes
  - 3MM Whatman filters
  - Blotting paper towels
  - Anti-DIG-alkaline phosphatase antibodies
  - Chemiluminescent substrates

## Troubleshooting Guide

1. *After electrophoresis, distribution of DNA species stained by EtBr is near the very top or the very bottom in some lanes instead of a long smear ranging from the top to the bottom of the lanes.* These problems are most likely caused by two factors. If genomic DNA is not completely digested, DNA molecules having a high molecular weight remain near the loading wells during electrophoresis. On the other hand, DNA is somehow degraded by DNases, so they become small fragments and distributed at the bottom of a lane. To prevent these problems from occurring, genomic DNA should be properly digested. Ensure that DNA is handled without DNase contamination.
2. *After transfer is complete, obvious DNA staining remains in the agarose gel.* This indicates that the transfer is not efficient. Try to carefully set up DNA transfer and allow blotting to proceed for longer time.
3. *The blotted membrane shows some trace of bubbles.* This is due to bubbles that form between gel and membrane. Please follow instructions carefully when assembling the blotting apparatus.
4. *No signal is detected at all after hybridization.* This is the worst and most disappointing problem in Southern blot hybridization. Genomic DNA may not be denatured before being transferred onto the membrane, or dsDNA probes may not be denatured before hybridization. When this occurs, it is not surprising at all to see a zero hybridization signal. Keep in mind that ssDNA species are the basis for hybridization.
5. *Hybridized signals are quite weak on film or filter.* The activities of DNA probes may be low or hybridization efficiency is not so good. The solution to



- this problem is to allow hybridization to proceed for a longer time and/or to increase exposure time for x-ray film or develop it for a longer time on filter.
6. *A black background occurs on x-ray film using the chemiluminescence detection method.* Multiple factors may be responsible for such a common problem. Membrane filter may have dried out during the hybridization or washing process. Excess detection solution may not have been removed before exposure. Exposure time may have been too long. To solve this problem, make sure that the filter is kept wet and excess detection reagents are completely removed. Try to reduce exposure time for the x-ray film.
  7. *A highly purple/blue background occurs on filter using colorimetric detection method.* Excess detection reagents may have been used or color is allowed to develop for too long. Try to apply an appropriate amount of detection reagents and closely monitor the color development. Once major bands become visible, stop development immediately by rinsing the filter with distilled water several times.
  8. *Unexpected bands show up on the X-ray film or membrane filter.* This problem is most likely caused by nonspecific binding between the probes and different DNA species. To solve or prevent such a problem from occurring, one may increase the blocking time for the blotted membrane and elevate the stringency conditions for both the hybridization and washing processes.

## REFERENCES

1. Southern, E. M. 1975. Detection of specific sequences among DNA fragments separated by gel electrophoresis, *Journal of Molecular Biology* 98: 503.
2. Wu, W. 1995. Electrophoresis, blotting and hybridization. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and C. Leland, 87–122. Boca Raton, FL: CRC Press.
3. Ausubel, F. M., R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl. 1995. *Current Protocols in Molecular Biology*. New York, NY: Greene Publishing Associates and Wiley-Interscience, John Wiley and Sons.
4. Fourney, R. M., R. Aubin, K. D. Dietrich, and M. C. Paterson. 1991. Determination of foreign gene copy number in stably transfected cell lines by Southern transfer analysis. In *Gene Transfer and Expression Protocols*, ed. E. J. Murray. Clifton, NJ: Humana Press Inc.
5. Sambrook, J., E. F. Fritsch, and T. Maniatis. 1989. *Molecular Cloning: A Laboratory Manual*, 2nd ed. Cold Spring Harbor, NY: Cold Spring Harbor Press.
6. Reed, K. C., and D. A. Mann. 1985. Rapid transfer of DNA from agarose gels to nylon membranes. *Nucleic Acids Research* 13: 7207.
7. Khandjian, E. W. 1987. Optimized hybridization of DNA blotted and fixed to nitrocellulose and nylon membranes. *Biotechnology* 5: 165.
8. Amasino, R. M. 1986. Acceleration of nucleic acid hybridization rate by polyethylene glycol, *Analytical Biochemistry* 152: 304.
9. Thomas, P. S. 1980. Hybridization of denatured RNA and small DNA fragments transferred to nitrocellulose. *Proceedings of the National Academy of Sciences of the United States of America* 77: 5201.




---

# 8 Gene Overexpression by Sense RNA in Mammalian Systems

## 8.1 INTRODUCTION

DNA recombination and gene transfer technologies have been well established and are widely utilized in mammalian cells and animals to address a vast spectrum of biological questions. To gain an insight into the function of the gene of interest, we and others use the gene overexpression approach to up-regulate the expression of a specific gene followed by analysis of the potential roles of the gene in cell or animal systems.<sup>1-5</sup> Gene overexpression refers to an increase in the amount of a given protein or the product level of a gene, which may result in an alteration in the function of the gene. We have successfully transfected mammalian cells with DNA constructs containing sense HSP27 cDNA and developed stably transfected cell lines in which the level of HSP27 increased by 4- to 8-fold as compared with nontransfected cells. As a result, cells containing higher levels of HSP27 can protect the cells against heat and toxicants such as heavy metals, demonstrating that one of the functions of the HSP27 protein is to enable cells to survive and recover from stress conditions.<sup>1</sup> In addition, gene overexpression has a broad range of applications in animal systems.<sup>2-6</sup> It is also applied to treat some human diseases resulting from defects in single genes by transferring the cDNA of a normal gene into patients to compensate for the lack of a given protein, which is termed gene therapy. Therefore, gene overexpression technology constitutes one of the major advances in current medicine and molecular genetics.<sup>3,6,7-11</sup>

How to overexpress a gene of interest? The general procedures are outlined in Figure 8.1. The primary principles are that the sense cDNA constructs of interest are first introduced into cells and integrated into the chromosomal DNA of the host, and that the expression of exogenous cDNA is driven by an appropriate promoter to produce sense RNA that is translated into protein. In this way, the endogenous protein plus the exogenous protein significantly elevate the level of the protein in the cell or animal. There are two types of transfection and expression in mammalian cells. One is transient transfection in which exogenous cDNA is introduced into cells, and the cDNA is allowed to be expressed for 1 to 3 days. The transfected cells are lysed and the proteins are analyzed. The purpose of transient transfection is usually to obtain a burst in the expression of the transferred cDNA. However, such transfection is not suitable for the selection of stably transfected cell lines. The other is stable transfection in which foreign genes are introduced into cells and are stably integrated into the chromosomes or genomes of the host cells. The integrated DNA can replicate efficiently and is maintained during cell division. The expressed products can



**FIGURE 8.1** Flowchart of gene overexpression in cells and animals.

be analyzed from successive generations of divided cells, establishing genetically altered cell lines.

Overall, gene overexpression by sense cDNA or RNA approaches consists of highly involved techniques that include isolation and characterization of a specific cDNA, DNA recombination, gene transfer, and analysis of the gene expression in transfected cells or transgenic animals. This chapter provides detailed protocols that have been successfully utilized in our laboratories.

## 8.2 DESIGN AND SELECTION OF PLASMID-BASED EXPRESSION VECTORS


Selection of an appropriate vector is important for the success of gene transfer and analysis of gene expression, including promoters, enhancers, selectable markers, reporter genes, and poly(A) signals. A number of vectors are commercially available. Each vector has its own strengths and weaknesses with regard to gene transfection and expression. We recommend several plasmid-based vectors that have been widely used in mammalian systems.

### 8.2.1 CONSTITUTIVE PROMOTER VECTORS

The anatomy of a constitutive vector is shown in Figure 8.2. The function of each component is described in the following subsections.

#### 8.2.1.1 Constitutive Promoters

The function of this type of promoter is to drive the expression of the cDNA cloned downstream from the promoter. Its driving activity is constitutive. A typical promoter is human cytomegalovirus (CMV). This type of vector is commercially available. For example, pcDNA3 and pcDNA3.1 vectors from Invitrogen contain PCMV consisting of major intermediate early promoter and enhancer regions.



**FIGURE 8.2** Anatomy of a constitutive expression vector.

The commercially available SV40 system has been demonstrated to be a strong expression vector. The simian virus 40 (SV40) is a small double-stranded circular DNA tumor virus with a 5.2-kb genome. The genome contains an early region encoding the tumor (T) antigen, a late region encoding the viral coat proteins, the origin of replication (ori), and enhancer elements near the ori. The ori and early region play essential roles for the expression of genes. Two divergent transcription units are produced from a single complex promoter/replication region. These viral transcripts are called early and late in relation to the time of maximal expression during infection. Both transcripts have introns and are polyadenylated. Using DNA manipulation technology, the SV40 genome has been mutated and fused with a plasmid such as pBR322, generating a series of very valuable vectors that have been used for gene transfer and expression.

### 8.2.1.2 Selectable Marker Genes

Stable transfection mandates a selectable marker gene in a vector so that stably transfected cells will confer resistance to drug selection. The commonly used marker genes include *neo<sup>r</sup>*, *hyg<sup>r</sup>*, and *hyr<sup>r</sup>*. Detailed selection principles are described under drug selection.

### 8.2.1.3 Reporter Genes

Although a reporter gene is not required in an expression vector, it is recommended that one utilize an appropriate reporter gene in the expression constructs. This will allow one to use the activity assay of the reporter gene for selection and/or characterization of stably transfected cells or transgenic animals. The following reporter genes are widely utilized.

*$\beta$ -Galactosidase gene.* *Lac Z* gene encoding for  $\beta$ -galactosidase is widely used as a reporter gene. The cell extracts of transfected cells can be directly assayed for  $\beta$ -galactosidase activity with spectrophotometric methods. The cells and embryos can be directly stained blue using X-gal. Tissues from adult animals can also be stained for tissue-specific expression. Therefore, we strongly recommend that one construct this gene in transfection vectors.

*CAT gene.* A bacterial gene encoding for chloramphenicol acetyl transferase (CAT) has proven to be quite useful as a reporter gene for monitoring the expression of transferred genes in transfected cells or transgenic animals, because eukaryotic cells contain no endogenous CAT activity. The CAT gene is isolated from the *Escherichia coli* transposon, Tn9, and its coding region is fused to an appropriate promoter. CAT enzyme activity can be readily assayed by incubating the cell extracts with acetyl Co-A and <sup>14</sup>C-chloramphenicol. This enzyme acylates the chloramphenicol, and products can be separated by thin layer chromatography (TLC) on silica gel plates followed by autoradiography.

*Luciferase gene.* The luciferase gene that encodes for firefly luciferase has been isolated and widely utilized as a highly effective reporter gene. As compared with the CAT assay, the assay for luciferase activity is more than 100-fold sensitive. It is simple, rapid, and relatively inexpensive. Luciferase is a small, single polypeptide with a molecular weight of 62 kDa. Furthermore, it does not require any post-translational modification for the activity. Other advantages of using the luciferase

gene are as follows: mammalian cells do not have endogenous luciferase activity and luciferase can produce a chemiluminescent light with very high efficiency, which can be easily detected.

*$\beta$ -Glucuronidase (GUS) gene.* Some investigators have used *uidA* or the *gusA* gene from *E. coli*, which encodes for GUS, as a reporter gene used for gene transfer. However, the disadvantage is that mammalian tissues contain endogenous GUS activity, thus making the enzyme assay more difficult. Nonetheless, the GUS reporter gene is an excellent reporter gene widely used in higher plant systems because plants do not contain detectable endogenous GUS activity.

#### 8.2.1.4 Splicing Regions

A sequence of appropriate polyadenylation site and a splicing region should be incorporated downstream from each individual gene in an expression vector so that individual mRNA species to be transcribed in the host cell can be spliced out, avoiding fusion proteins that are functionally different from the nonfusion or native protein of interest.

#### 8.2.1.5 Kozak Sequence and Enhancer Element

To further enhance the expression of the cloned cDNA, it is a good idea to incorporate an enhancer element upstream from the promoter. It has been reported that a Kozak sequence, GCC(A/G)CCAUGG that includes the first codon, AUG, can increase the efficiency of translation up to 10-fold.

### 8.2.2 INDUCIBLE PROMOTER VECTORS

Unlike constitutive promoter vectors, the expression of a cloned cDNA in an inducible vector requires an inducer. The general structure is shown in Figure 8.3. These vectors are commercially available. For instance, the pMAMneo (Clontech) contains the dexamethasone-inducible MMTV-LTR promoter linked to the RSV-LTR enhancer.





FIGURE 8.3 Diagram of an inducible expression vector.

### 8.2.3 RETROVIRUS VECTORS

It has demonstrated that retroviruses can be used as effective vectors for gene transfer in mammalian systems, especially for transient transfection.<sup>12</sup> There are several advantages over other vector systems, which include (1) the retroviral genome can stably integrate into the host chromosome of the host cell and can be passed from generation to generation, thus providing an excellent vector for stable transfection; (2) retroviruses have a great infectivity and expression host range for any animal cells via viral particles; (3) integration is site-specific with respect to the viral genome at long terminal repeats (LTRs)—in other words, any DNA cloned within two LTRs will be expected to be integrated into chromosomal DNA of the host cell, which can preserve the structure of the gene intact with ease after integration; and (4) viral genomes are very plastic and manifest a high degree of natural size manipulation for DNA recombination. The drawback, however, is that the techniques are relatively sophisticated. Therefore, for a successful transfection, it is necessary to briefly elaborate on the life cycle of retroviruses before describing the construction of retrovirus-based vectors for mediating gene transfer.

Retroviruses such as Rous sarcoma virus (RSV) and Moloney murine leukemia virus (MoMLV), are RNA viruses that cause a variety of diseases (e.g., tumors) in humans. The virus has two tRNA primer molecules, two copies of genomic RNA (38S), reverse transcriptase, RNase H, and integrase, which are packaged with an envelope. The viral envelop contains glycoproteins that can determine the host range of infection. As shown in Figure 8.4, when the virus or virion attaches to a cell, the viral glycoproteins in the envelop bind to specific receptors in the plasma membrane of the host cell. The bound complex facilitates the internalization of the virus that is




**FIGURE 8.4** Life cycle of a replication-competent retrovirus.



now uncoated as it passes through the cytoplasm of the host cell. In the cytoplasm, reverse transcriptase in the viral genome catalyzes the formation of a double-stranded DNA molecule from the single-stranded virion RNA. The DNA molecule undergoes circularizing, enters the nucleus, and becomes integrated into the chromosome of the host cell, forming a provirus. Subsequently, the integrated provirus serves as the transcriptional template for both mRNAs and virion genomic RNA. Interestingly, such transcription is catalyzed by the host RNA polymerase II. The mRNAs then undergo translation to produce viral proteins and enzymes using the host machinery. These components are packaged into viral core particles that move through the cytoplasm, attach to the inner side of the plasma membrane, and then bud off. This cycle of infection, reverse transcription, transcription, translation, virion assembly, and budding is repeated over and over again, infecting new host cells.

A well-understood retrovirus is RSV. The mechanism of synthesis of double-stranded DNA intermediates (provirus) from viral RNA is unique and quite complex. The nucleotide sequence of the DNA molecule is different from that of the viral RNA. The sequence U3-R-U5, which is a combination of the 5' r-u5 segment and the 3' u3-r segment of the RNA, is present at both 5'- and 3'-ends of double-stranded DNA molecule. The U3-R-U5 is named the long-terminal repeat. This complete scheme can be divided into eight steps as shown in Figure 8.5.

1. One of the proline tRNA primers first anneals to the pbs region in the 5' r-u5 of the viral genome RNA. Reverse transcriptase catalyzes the extension of the tRNA primer from its 3'-OH end to the 5'-end, producing a DNA fragment called 3' R'-(U5)'-tRNA.
2. RNase H removes the cap and poly(A) tail from the viral RNA as well as the viral r-u5 segment in the double-stranded region.
3. The 3' R'-(U5)'-tRNA separates from the pbs region, jumps to the 3'-end of the viral RNA and forms an R'/r duplex.
4. The 3' R'-(U5)'-tRNA undergoes elongation up to the pbs region of the viral RNA by reverse transcriptase, producing the minus (-) strand of DNA.
5. RNase H removes the u3-r from the 3'-end of the viral RNA, followed by synthesis of DNA from the 3'-end of the RNA via reverse transcriptase, generating the first LTR (U3-R-U5) that contains the promoter sequence. This serves as a part of the plus (+) strand of DNA.
6. All RNA including the tRNA primer are removed by RNase H.
7. The U3-R-U5 (PBS) separates from (U3)R' (U5)', jumps to the 3'-end of the complementary strand of DNA and forms a (PBS)/(PBS)' complex. *This is an essential process for the virus since the jumping action brings the promoter in the U3 region from 3'-end to the 5'-end of the plus strand of DNA. So, the promoter is now upstream from the coding region for gag-pol-env-src in the 38S RNA genome.*
8. Reverse transcriptase catalyzes the extension of DNA from the 3'-termini of both strands, producing a double-stranded DNA (provirus). The LTRs at both ends of the DNA molecule contain promoter and enhance elements for transcription of the virus genome. The double-stranded DNA molecule can now become integrated into the chromosomes of the infected cell.



**FIGURE 8.5** Scheme for synthesis of double-stranded DNA containing two long terminal repeats (LTR) from Rouse sarcoma viral RNA.

How to make use of the harmful infectious retrovirus for gene transfer and expression? Because retroviruses can cause tumors in animals and human beings, we obviously do not want the whole virus genome to be used for gene transfer or as an expression vector. Recent DNA recombination technology makes it possible to manipulate the retrovirus genome so that it is a powerful tool for gene transfer. The simplest type of gene transfer system is that all or most of the *gag*, *pol*, and *env* genes in the provirus are deleted. Nonetheless, all of the *cis*-active elements, such as the 5' and 3' LTRs, PBS(+), PBS(-), and  $\psi$  packaging sequence, are left intact. A foreign cDNA of interest or a selectable gene such as *neo*, *gpt*, *dhfr*, and *hpvt* can be inserted at the initiating ATG site for *gag*. The expression of the inserted gene is driven by the 5' LTR. This manipulated vector is then fused with a plasmid fragment such as pBR322 containing the origin of replication (*ori*) and an antibiotic resistant gene. The recombinant plasmids are propagated in a bacterial strain of *E. coli*. The vectors are then utilized for standard DNA-mediated transfection of suitable recipient cells and stable transformants can be selected by using an appropriate antibiotic chemical such as G418. The partial viral RNA transcribed in the host cell can be further packaged into retroviral particles, which become an infectious recombinant retrovirus. This can be done by cotransfecting the host cells with a helper virus that produces *gag* and *env* proteins, which can recognize the  $\psi$  sequence on the recombinant transcript and become packaged to form viral particles. The disadvantage of this strategy is that the culture supernatant contains recombinant and wild-type viruses. To overcome this problem, some vectors are constructed by deleting the  $\psi$  sequence, replacing the 3' LTR with a SV40 terminator, the poly(A) signal, and fusing to the backbone of pBR322. Another type of expression vector may be constructed by deleting *gag* and *env* genes, and by inserting a selectable marker gene (e.g., *neo*) or a reporter gene followed by polylinker sites for the insertion of the foreign gene or cDNA of interest at the ATG site for *gag* downstream from the 5' LTR. The 3' LTR can be replaced with the SV40 poly(A) signal downstream from the introduced cDNA or gene.

This chapter focuses on a replication-incompetent viral vector (Figure 8.6). A replication-incompetent vector lacks *gag*, *pol*, and *env* genes encoding virus structural proteins. These deleted viral genes are replaced by a marker gene (e.g., *neo*)




FIGURE 8.6 Diagram of a retrovirus expression vector.

and the cDNA of interest. cDNA to be expressed can be cloned at the multiple cloning site (MCS) and be driven by the CMV promoter or other promoters such as the herpes simplex thymidine kinase promoter (TK). The major advantage of this vector is that any genes cloned between the 5' LTR and 3' LTR can be efficiently integrated into the chromosomes of the host cell because the LTRs contain a short sequence that facilitates the integration. The recombinant vector is then fused with the pBR322 backbone containing the origin of replication and the *Amp<sup>r</sup>* gene. The recombinant plasmids are then amplified in *E. coli*. The foreign gene or cDNA of interest can be cloned at the polylinker site downstream from the 5' LTR of recombinant vectors, and gene transfer can be carried out via a standard plasmid DNA-mediated procedure.

### 8.3 PREPARATION OF PLASMID SENSE cDNA CONSTRUCTS

cDNA isolation and characterization are described in Chapter 3. Restriction enzyme digestion of DNA, ligation, bacterial transformation, and purification of plasmid DNA are given in Chapter 4.

This section emphasizes the following special points with respect to the preparation of sense cDNA constructs. Any mistakes will cause failure in the expression of the cloned cDNA.

1. *Length of cDNA to be cloned.* For the overexpression of a functional protein from a cDNA, the cDNA must include the entire coding region or ORF. In our experience, 10 to 20 base pairs in 5'UTR or 3'UTR are recommended for subcloning. Long 5'UTR or 3'UTR sequences may not be good for overexpression of the cloned cDNA.
2. *Orientation of the cDNA.* It is absolutely essential that the cDNA be placed in the sense orientation downstream from the promoter. In other words, the poly(T) strand or (–) strand of the cDNA should be 3' → 5' downstream from the driving promoter in order to make 5' → 3' mRNA.
3. *Start or stop codon.* Make sure that there is no start codon between the driving promoter and the first start codon ATG of the cDNA. Otherwise, the protein to be expressed will be a fusion protein other than the protein of interest. For this reason, we strongly recommend that the plasmid construct DNA be partially sequenced at the MCS to make sure that the cDNA is cloned at the right place without any ATG codon upstream from the first ATG codon in the cDNA. However, if a stop codon is present upstream from the first codon ATG, it is alright because during translation the small subunit of ribosome will locate the ATG codon instead of the stop codon.

### 8.4 TRANSIENT TRANSFECTION OF MAMMALIAN CELLS WITH SENSE CONSTRUCTS

#### 8.4.1 METHOD A. TRANSFECTION BY CALCIUM PHOSPHATE PRECIPITATION

The principle of calcium phosphate transfection is that the DNA to be transferred is mixed with  $\text{CaCl}_2$  and phosphate buffer to form a fine calcium phosphate precipitate.

The precipitated complexes/particles are then placed on a cell monolayer. They bind/attach to the plasma membrane and are taken into the cell by endocytosis. This is one of the most widely used methods for both transient and stable transfection.

1. Perform trypsinizing to remove adherent cells for subculture or cell counting as well as for monolayer cell preparation.
  - (a) Aspirate the medium from the cell culture or the tissue culture dish and wash the cells twice with 10 to 15 ml of PBS buffer or other calcium- and magnesium-free salt solutions.
  - (b) Remove the washing solution and add 1 ml of trypsin solution per 100-mm dish. Quickly overlay the cells with the solution and incubate at 37°C for 5 to 10 min, depending on the cell type (e.g., NIH 3T3, 2 min; CHO, 2 min; HeLa, 2.5 min; COS, 3 min).
  - (c) Closely monitor the cells. As soon as they begin to detach, immediately remove the trypsin solution and tap the bottom and sides of the culture flask or dish to loosen the remaining adherent cells.
  - (d) Add culture medium containing 10% serum [e.g., fetal bovine serum (FBS) or fetal calf serum (FCS)] to the cells to inactivate the trypsin. Gently shake the culture dish. The cells can be used for cell subculturing or counting.
2. Prepare cell monolayers the day before the transfection experiment. The cell monolayers should be at 60% to 70% confluence. Aspirate the old culture medium and feed the cells with 5 to 10 ml of fresh culture medium.

Notes:

- (1) *It is recommended that this procedure be carried out in a sterile laminar flow hood. Gloves should be worn to prevent contamination of the cells.*
  - (2) *The common cell lines used for transfection are NIH 3T3, CHO, HeLa, COS, and mouse embryonic stem (ES) cells. Other mammalian cells of interest can also be transfected in this manner.*
  - (3) *The density of the cells to be seeded depends on the particular cell line. A general guideline is 1 to  $5 \times 10^6$  cells per 100-mm culture dish.*
  - (4) *All solutions and buffers should be sterilized by autoclaving or by sterile filtration.*
3. Prepare a transfection mixture for each 100-mm dish as follows:

2.5 M CaCl <sub>2</sub> solution	50 μl
<u>DNA construct</u>	<u>15–30 μg</u>
Add dd.H <sub>2</sub> O to a final volume of	0.5 ml

Mix well, and slowly add the DNA mixture dropwise to 0.5 ml of well-suspended 2× HBS buffer with continuous mixing by vortexing. Incubate the mixture at room temperature for 30 to 45 min to allow coprecipitation to occur.

Notes:

- (1) *The DNA to be transferred can be in a circular form (e.g., recombinant plasmids) or be linear chimeric genes.*

- (2) After the DNA mixture has been added to the 2× HBS buffer, the mixture should be slightly opaque due to the formation of a fine coprecipitate particles of DNA with calcium phosphate.
4. Slowly add the precipitated mixture dropwise to the dish containing the cells with continuous swirling of the plate. For each 100-mm dish, add 1 ml of the DNA mixture or 0.5 ml of the DNA mixture to each 60-mm dish.
  5. Place the dishes in a culture incubator overnight at 37°C and provide 5% CO<sub>2</sub>.
  6. Aspirate the medium and wash the monolayer once with 10 ml of serum-free Dulbecco's modified Eagle's medium (DMEM) medium and once with 10 ml PBS. Add fresh culture medium and return the dishes to the incubator. In general, cells can be harvested 48 to 72 h after transfection for transient expression analysis.

### Reagents needed

- *10× HBS buffer*
  - 5.94% (w/v) HEPES [4-(2-hydroxyethyl)-1-piperazine ethanesulfonic acid], pH 7.2
  - 8.18% (w/v) NaCl
  - 0.2% (w/v) Na<sub>2</sub>HPO<sub>4</sub>
- *2× HBS buffer*
  - Dilute the 10× HBS in dd.H<sub>2</sub>O
  - Adjust the pH to 7.2 with 1 N NaOH solution
- *DNA to be transferred*
  - Circular or linear recombinant DNA constructs in 50 µl of TE buffer, pH 7.5
- 2.5 M CaCl<sub>2</sub>
- *DMEM culture medium*
  - Dissolve one bottle of DMEM powder in 800 ml dd.H<sub>2</sub>O; add 3.7 g NaHCO<sub>3</sub>; adjust the pH to 7.2 with 1 N HCl. Add dd.H<sub>2</sub>O to 1 l. Sterile-filter the medium (do not autoclave) in a laminar flow hood. Aliquot the medium into 200- to 500-ml portions in sterile bottles. Add 10% to 20% FBS, depending on the particular cell type, to the culture medium. Store at 4°C until use.
- *PBS buffer*
  - 0.137 M NaCl
  - 4.3 mM Na<sub>2</sub>HPO<sub>4</sub>
  - 2.7 mM KCl
  - 1.47 mM KH<sub>2</sub>PO<sub>4</sub>
  - The final pH is 7.2–7.4
- *1× Trypsin–EDTA solution*
  - 0.05% (w/v) trypsin
  - 0.53 mM EDTA, pH 7.6
  - Dissolve in PBS buffer, pH 7.4–7.6


### 8.4.2 METHOD B. TRANSFECTION BY RETROVIRUS VECTORS

This section focuses on a replication-incompetent viral vector (Figure 8.6) and describes in detail the protocols for retroviral transfection. As shown in Figure 8.6, a replication-incompetent vector lacks *gag*, *pol*, and *env* genes that encode virus structural proteins, which are replaced by marker *neo* gene and cDNA to be expressed. To generate a retrovirus producer cell line, replication-incompetent viral vectors are first introduced into a murine packaging cell line that is able to produce the proteins (e.g., virus structural proteins) necessary for production of retroviral particles. The cloned cDNA and *neo* gene between the two LTRs will integrate into the genome of the packaging cells. After drug selection (e.g., use of G418), stably transfected packaging cells will survive and produce retroviral particles whose genomic RNA contains the packaging sequence, the *neo* gene and the cDNA of interest, generating retrovirus producer cells. The retrovirus particles will leave the host cells by budding and are able to reinfect these host cells. After serial drug selections, a high titer of specific retrovirus producer cell lines can be established. These cells are then utilized to prepare a large-scale and a high concentration of retrovirus stocks that can be used to infect other animal cells of interest for high efficiency of transfection. It should be noted that these retrovirus particles cannot replicate themselves because they lack *gag*, *pol*, and *env* genes that encode virus structural proteins. Thus, retrovirus particles are solely generated from the producer cell lines.

*Caution: The authors wish to remind investigators about the biological safety requirements involved in the use of retroviruses. Occasionally, a replication-incompetent retrovirus stock may contain a helper virus that is a replication-competent virus. The presence of a helper virus could be problematic. If such a virus infects animals, leukemia and other diseases may be generated. Therefore, extreme precautions should be taken when using retroviruses for research. A proven proposal may be needed from an appropriate committee. Any solutions and media containing potential retrovirus particles should be collected in special containers and be autoclaved before being disposed of or being given to authorized people to handle.*

#### 8.4.2.1 Protocol 1. Preparation of Viral Supernatant by Transient Transfection of a Packaging Cell Line with Retrovirus Vector Constructs

As shown in Figure 8.6, replication-incompetent retrovirus DNA constructs lack the structural genes (*gag*, *pol*, *env*) encoding the retrovirus structural proteins. Therefore, production of infectious viral particles mandates transfection of a packaging cell line with the plasmid-based retrovirus constructs. Packaging cell lines are derived from either mouse-fibroblast cells or avian cells. These cell lines have been stably transfected with retroviruses whose genomic RNA does not contain the packaging sequence  $\Psi$ . In this way, even though the cells contain *gag*, *pol*, and *env* genes encoding viral structural proteins, the cells cannot package the viral RNA. However, these cells are very valuable packaging cell lines that can be used for transfection with a plasmid-based replication-incompetent retrovirus vector (Figure 8.6). Because the packaging sequence  $\Psi$  is incorporated into the construct, viral RNA molecules can be readily



**FIGURE 8.7** Transfection of a packaging cell line with a replication-incompetent retrovirus vector and production of infectious retroviral particles.

packaged. As a result, infectious viral particles will be produced. The commonly used packaging cell lines include murine-ecotropic GP + E-86,  $\Omega$ E, and murine-amphotropic  $\psi$ CRIP. These cell lines cannot produce the replication-competent helper virus and they provide safe cell lines for packaging. A number of packaging cell lines are either commercially available or obtained from other investigators with permission from appropriate authorities. The general procedure is outlined in Figure 8.7.

1. Culture packaging cells to 40% to 50% confluence before transfection.
2. Perform transfection of cells with replication-incompetent retrovirus constructs (Figure 8.6) using the calcium phosphate precipitation method. The detailed protocol is described in Method A (Section 8.4.1).  
*Note: Electroporation can also be applied for transfection except for the fact that approximately 50% of cells may be killed by a high voltage pulse. The DNA constructs can be linear. However, since the vector contains both 5'-LTR and 3'-LTR, circular plasmid DNA works better.*
3. For transient transfection, harvest the medium 24 to 48 h after transfection and filter through a 0.45- $\mu$ m filter. Now, the supernatant should contain infectious viruses. The supernatant can be used immediately for titer or stored at  $-80^{\circ}\text{C}$  until use. The cells can be utilized for drug selection to generate stable producer cells (see Protocol 2 below).

#### 8.4.2.2 Protocol 2. Production of Stably Transfected Producer Cell Lines

1. Trypsinize the cells (see Chapter 16 for detailed protocols) left at step 3 in Protocol 1 (Section 8.2.4.1) and plate them at a 1:10 to 1:50 dilution. Add an



appropriate volume of medium (10 ml/100 mm dish or 15 ml/T75 flask) and allow the cells to grow for 24 to 48 h.

2. Replace the medium with selection medium containing an appropriate amount of drug (e.g., G418). The cells are cultured in the selection medium for 10 to 14 days with a change of medium once every 2 to 7 days, depending on the specific cell lines, to remove dead cells and cellular debris. In theory, only those cells that bear and express the drug-selectable marker gene can survive in the selection medium.

Notes: *For selection, a killing curve should first be established from non-transfected cells that are cultured in the medium containing serial concentrations of an appropriate drug. Choose the concentration that kills 100% of the cells in 5 days as the concentration to be used for selection of stably transfected cells. On the other hand, the concentration used for selection can be found from previous studies using the same cell line.*

3. Transfer well-isolated individual colonies to separate dishes or flasks and expand these clones in the selection medium until 70% to 90% confluence is obtained.
4. Harvest the medium and filter it with a 0.45- $\mu$ m filter. The virus stock can be immediately used for titer or stored at  $-80^{\circ}\text{C}$  until use.
5. Freeze back as many vials of the stable producer cell lines as possible. The detailed protocols for cell freezing are described in Chapter 16.

### 8.4.2.3 Protocol 3. Determination of Viral Titer

After individual clones have been isolated, it is necessary to produce virus stocks from each of the clones and titer the virus in the stocks. To do so, a targeting or titering cell line is needed. The most widely used cell lines are NIH 3T3 (mouse fibroblast), avian QT6, and chicken embryo fibroblast CEF.

1. Culture stable producer clones to 80% to 90% confluence in 100 mm dishes or in T25 or T75 flasks.
2. Individually harvest the medium and filter it through a 0.45- $\mu$ m filter. Store the medium at  $-80^{\circ}\text{C}$  until use.
3. Plate  $1 \times 10^4$  NIH 3T3 into each of 6-cm dishes 1 day before infection. Allow the cells to grow for 24 h in an incubator at  $37^{\circ}\text{C}$ , 5%  $\text{CO}_2$ .
4. Collect the medium and filter it through a 0.45- $\mu$ m filter. Store the supernatant containing viruses at  $-80^{\circ}\text{C}$  until use. This supernatant will serve as the virus stock.
5. Make serial 10-fold dilutions of the virus stock into the culture medium for the target cells. It is recommended that one start from 1000  $\mu\text{l/ml}$   $\rightarrow$  100  $\mu\text{l/ml}$   $\rightarrow$  10  $\mu\text{l/ml}$   $\rightarrow$  1  $\mu\text{l/ml}$   $\rightarrow$  0.1  $\mu\text{l/ml}$   $\rightarrow$  0.01  $\mu\text{l/ml}$   $\rightarrow$  0.001  $\mu\text{l/ml}$ . For each 6-cm dish or 100-mm dish, make 5 or 10 ml of dilution viral medium. Add polybrene (Sigma Chemical Co., St. Louis, MO) to a final concentration of 2 to 4  $\mu\text{g/ml}$  using 100 $\times$  stock in dd.H<sub>2</sub>O.


Note: *The diluted viral medium should be used in 1 h.*

6. Aspirate the medium from the target cells at step 3 (above) and add 5 ml of the diluted medium prepared at step 5 to each 6-cm dish or 10 ml to 100-mm dish. Incubate the cells at 37°C for 24 h.
7. Replace the medium with fresh culture medium without virus and allow the cells to grow for 24 h. At this point, there are two options. If the retroviral particles contain a reporter gene, such as *lac Z*, the infected cells can be stained with X-gal (see reporter gene assay in this chapter). No drug selection is necessary. However, if the viruses carry a selectable marker gene such as *neo*, the infected cells can be identified by drug (G418) selection, which is described in the next steps.
8. Replace the medium at step 7 with drug selection medium containing an appropriate concentration of G418, which should be based on the killing curve. The concentration of G418 that results in 100% killing of the target cells will be chosen as the selection medium.
9. Allow the cells to be selected and cultured for 10 to 12 days with changes of the culture medium once every 3 days. Stably infected cells should survive and expand to form colonies within 2 weeks.
10. Count the colonies and calculate the titer as CFU/ml. Titer is expressed as the number of colonies per milliliter virus stock. It is easy to use the highest dilution for calculation. For example, if a dish has five stably infected colonies in 10<sup>6</sup> dilution medium, the titer will be 5 × 10<sup>6</sup> G418<sup>r</sup> CFU/ml of virus stock. In the same way, if the cells are stained with X-gal, then, X-gal CFU/ml = no. of blue colonies/virus volume (ml) × dilution factor. A rate of 10<sup>6-8</sup> CFU/ml is considered a good titer of virus stock.

#### 8.4.2.4 Protocol 4. Amplification of Virus Stock by Serial Reinfection of Fresh Target Cells

A good titer of virus stock can be utilized to reinfect fresh target cells to obtain a large scale of a high titer of virus stock (Figure 8.8).

1. Plate 1 × 10<sup>4</sup> NIH 3T3 in each of 6-cm dishes and allow the cells to grow to about 20% to 30% confluence in an incubator at 37°C with 5% CO<sub>2</sub>.
2. Collect a good titer of virus stock and filter through a 0.45-μm filter. Store the supernatant containing viruses at -80°C until use.
3. Make a dilution of the culture medium using 10<sup>5</sup> CFU/ml. For each 6-cm dish or 100-mm dish, make 5 or 10 ml of diluted viral medium. Add polybrene to a final concentration of 2 to 4 μg/ml using 100 × stock in dd.H<sub>2</sub>O.
4. Aspirate the medium from the target cells and add 5 ml of the diluted medium to each 6-cm dish or 10 ml to 100-mm dish. Incubate the cells at 37°C for 24 h.
5. Replace the medium with fresh culture medium without virus and allow the cells to grow for 24 h.
6. Replace the medium with drug selection medium containing an appropriate concentration of G418, which should be based on the killing curve. The concentration of G418 that results in 100% killing of the target cells will be chosen as the selection medium.




**FIGURE 8.8** Transfection of a packaging cell line with a replication-incompetent retrovirus vector and production of infectious retroviral particles.

7. Allow the cells to be selected and cultured for 15 to 21 days with changes of the medium once every 3 days. Stably infected cells should be expanded to 90% confluence.
8. Pick up well-isolated colonies and expand them in individual flasks or dishes. Grow the cells to confluence.
9. Harvest the virus supernatant and filter it. Freeze back as many vials of stably infected target cells as possible. The filtered virus stock with high titer can be used to infect other animal cells of interest (see Protocol 5).

#### 8.4.2.5 Protocol 5. Transfection of Cells of Interest with the High Titer Stock of Replication-Incompetent Retroviruses

1. Plate  $1 \times 10^4$  cells of interest in each 6-cm dishes and allow the cells to grow to about 20% to 30% confluence in an incubator at 37°C with 5% CO<sub>2</sub> (Figure 8.9).
2. Filter the high titer stock of virus prepared in Protocol 4 using a 0.45-μm filter. Store the supernatant containing viruses at -80°C until use.
3. Make a dilution of culture medium using 10<sup>6-7</sup> CFU/ml. For each 6-cm dish or 100-mm dish, make 5 or 10 ml of diluted viral medium. Add polybrene to a final concentration of 2 to 4 μg/ml using 100 × stock in dd.H<sub>2</sub>O.
4. Aspirate the medium from the cultured cells and add 5 ml of the diluted medium to each 6-cm dish or 10 ml to 100-mm dish. Incubate the cells at 37°C for 24 h.
5. Replace the medium with fresh culture medium without virus and allow the cells to grow for 24 h.
6. Replace the medium with drug selection medium containing an appropriate concentration of G418, which should be based on the killing curve.



**FIGURE 8.9** Infection of an animal cell of interest by a replication-incompetent retrovirus containing the introduced cDNA and *neo* gene.

7. Allow the cells to be selected and cultured for 15 to 21 days with changes of the medium once every 3 days. Stably infected cells should be expanded to 90% confluence.
8. Pick up well-isolated colonies and expand them in individual flasks or dishes. Allow the cells to grow to confluence.
9. Freeze back the stably infected cells.

## 8.5 STABLE TRANSFECTION OF MAMMALIAN CELLS WITH SENSE DNA CONSTRUCTS

### 8.5.1 METHOD A. TRANSFECTION BY LIPOSOMES

Detailed protocols are described under “Transient Transfection” in Section 8.4.1.

### 8.5.2 METHOD B. TRANSFECTION BY ELECTROPORATION

This is a fast and effective transfection technique. The principle underlying this method is that cells and DNA constructs to be transferred are mixed and subjected to a high voltage electrical pulse that creates pores in the plasma membranes of the cells. This allows the exogenous DNA to enter the cytoplasm of the cell and the nucleus through the nuclear pores and become integrated into the genome. This method is suitable for both transient and stable transformation experiments. However, the pulse conditions should be adjusted empirically for the particular cell type. Although this method has a high efficiency of transfection, its drawback is that approximately 50% of the cells are killed by the high voltage electrical pulse. These dead cells should be removed on a daily basis in order to reduce toxicity.

1. Linearize the DNA constructs to be transferred by a unique restriction enzyme. Protocols for appropriate restriction enzyme digestion are described in Chapter 4.

*Tips: (1) The unique restriction enzyme cut should be in the plasmid backbone area such as ColEI, fi ori, or ampicillin gene. It is extremely important that this cut cannot be in any region that will affect gene targeting by homologous recombination. The activities of Lac Z and selectable marker genes such as neo, hyg, hyrt, and HSV-tk should not be affected. In the case of double knockout rescue DNA, ensure that the cut is not in any area in the promoter, inserted cDNA, or the splicing site. (2) In our experience, plasmid DNA constructs do not need to be linearized for homologous recombination. In fact, plasmid DNA enhances the transfection efficiency up to 30%.*

2. Harvest the cells by gentle trypsinization as described in Chapter 16. Centrifuge the cells at 150 g for 5 min and resuspend the cells well in normal culture medium at about  $10^6$  cells/ml.  
*Note: Make sure that the cells are gently but well suspended before transfection because aggregation of cells may cause difficulty in isolation of stably transfected cell clones.*
3. In a laminar flow hood, gently mix 0.6 ml of the cell suspension with 15 to 30  $\mu$ l of DNA constructs (25 to 50  $\mu$ g) in a disposable electroporation cuvette (Bio-Rad, Hercules, CA).
4. According to the manufacturer's instructions, carry out electroporation using a Gene Pulser (Bio-Rad) with a Pulse Controller and Capacitance Extender at 300 V and 250  $\mu$ F.
5. The electroporated cells are immediately plated in culture dishes at a density of about 3000 cell/100 mm Petri dish and culture the cells at 37°C with 5% CO<sub>2</sub>. Proceed to drug selection.

### 8.5.3 METHOD C. TRANSFECTION BY RETROVIRUS VECTORS

Detailed protocols are described in Method B (Section 8.1.4.1).

## 8.6 SELECTION OF STABLY TRANSFECTED CELL LINES WITH APPROPRIATE DRUGS

As shown in Figure 8.1, foreign DNA enters the cells after transfection, but only a small portion of the DNA gets transferred to the nucleus in which some of the DNA might be transiently expressed for a few days. A smaller portion of the DNA that is introduced into the nuclei of some of the transfected cells undergoes integration into the chromosomes of the host and will be expressed in future generations of the cell population, generating stably transfected cells. The selection of the transfected cells depends on the drug-selectable marker gene fused in the recombinant plasmid, or linear DNA construct or a separate plasmid that can be cotransfected into the cells. Generally, the transfected cells are cultured for 30 to 60 h in the medium lacking specific antibiotics in order to allow the cells to express the selectable marker gene. The cells are then subcultured in a 1:10 to 1:100 dilution in a selective medium containing an appropriate drug. The cells are cultured in the selective medium for 10 to 14 days with changes of medium once every 2 to 7 days, depending on specific cell lines, to remove dead cells and cellular debris. In theory, only those cells that bear

and express the drug-selectable marker gene can survive in the selective medium. The common marker genes that have been used for transfection and the selection can be carried out as described below.

#### 1. *Use of aminoglycoside antibiotics*

If cells are transfected with recombinant gene constructs that contain a bacterial gene *neomycin* or Tn60 for aminoglycoside 3'-phosphotransferase (*aph*), the stably transfected cells can confer resistance to aminoglycoside antibiotics such as kanamycin (*kan*) and geneticin (G418). For selection, a killing curve should first be established from nontransfected cells that are cultured in the medium containing different concentrations of an appropriate drug. Choose the concentration that kills 100% cells in 5 days as the concentration for selection of stably transfected cell. On the other hand, the concentration used for selection can be found in previous studies using the same cell line. For instance, we use 250  $\mu\text{g/ml}$  and 1  $\text{mg/ml}$  G418 to select mouse ES cells and fibroblast STO cells, respectively.

#### 2. *Hygromycin- $\beta$ -phosphotransferase*

Stably transfected cells containing the hygromycin- $\beta$ -phosphotransferase gene can be selected with hygromycin B, which is a protein synthesis inhibitor. Hygromycin B stocks are available from Sigma Chemical Co. Use 10 to 500  $\mu\text{g/ml}$  in the culture medium, depending on the pre-killing curve of a specific cell line.

#### 3. *Thymidine kinase*

If cells lacking the thymidine kinase gene (*tk*<sup>-</sup>) are transfected by recombinant gene constructs containing the *tk* gene, the stable transformants can be selected by culturing the transfected cells in a medium containing hypoxanthine, aminopterin, and thymidine (HAT). Nonstable transfected cells cannot metabolize this lethal analog and will be killed. The HAT medium is prepared as follows:

Dissolve 15 g hypoxanthine and 1 mg aminopterin in 8 ml of 0.1 N NaOH solution. Adjust the pH to 7.0 with 1 N HCl and then add 5 mg thymidine. Add water to 10 ml and sterile filter it. Dilute the stock HAT to 100-fold in the culture medium used for selection. Again, the dilution or concentration of the HAT should be based on the pre-killing curve. Different cell lines confer different degrees of resistance.

#### 4. *Tryptophan synthetase*

If cells are transfected with DNA constructs containing the tryptophan synthetase gene (the *trp B*), the stably transfected cells can be selected by culturing the cells in a medium lacking tryptophan, an essential amino acid necessary for the growth of cells.


## 8.7 CHARACTERIZATION OF STABLY TRANSFECTED CELL CLONES

Characterization of stably transfected cell lines will provide information about whether the developed clones contain and express the genes introduced into the cells. This verification step is required because drug-resistant cells may not contain or


express the gene of interest. Traditionally, characterization begins with DNA analysis by Southern blotting, then proceed to the mRNA level by northern blotting followed by protein analysis by western blotting. Nonetheless, in practice, the putative clones that express the cDNA introduced is only approximately 10% of the stably selected cell clones. Obviously, if one starts from the Southern blot analysis, there will be a tremendous amount of work, assuming that he or she has obtained 100 clones after drug selection and only 10 or less clones really express the cDNA or gene of interest. In our experience, Southern blotting as the first step of analysis may not be a good idea. It is time-consuming and costly. The same situation prevails if one begins with northern blotting, which is a relatively complicated procedure. We strongly recommend that one start with protein analysis either by dot blotting or western blot analysis using antibodies that are specific against the protein expressed from the introduced cDNA or gene. Keep in mind that the bottom line of gene expression is the protein or the product of interest. We first choose western blot analysis<sup>12</sup> because it is faster, less expensive, and a more reliable procedure as compared with Southern and northern blot analyses. We have found that a majority of nonputative clones can be ignored after western blot analysis. Once the putative clones have been identified to express the protein of interest, one can go back to Southern blot or northern blot analysis. Therefore, one can consider that this is the reverse sequence to traditional characterization.

### 8.7.1 ANALYSIS OF GENE OVEREXPRESSION AT THE PROTEIN LEVEL BY WESTERN BLOTTING

The detailed protocols for protein extraction and western blot hybridization are described in Chapter 11. This section focuses primarily on how to analyze western blot data. Assuming that the product or protein of the cDNA is 50 kDa, and that monoclonal antibodies have been raised to be against the 50-kDa protein, as shown in Figure 8.10, in control cells (lane 1), only a weak 50-kDa band is detected. This is the endogenous level of the protein in the cells. In contrast, putative clones show overexpression of the 50-kDa protein (lanes 2 to 4) as compared with the control cells.



**FIGURE 8.10** Protein analysis by western blotting. Lane 1: nontransfected cells. Lanes 2 to 4: overexpression of the 50-kDa protein in different cell clones.



**FIGURE 8.11** mRNA analysis by northern blotting. Lane 1: nontransfected cells. Lanes 2 to 4: overexpression of the 1-kb mRNA in different transfected cell clones.

## 8.7.2 EXAMINATION OF THE EXPRESSION OF SENSE RNA BY NORTHERN BLOTTING


The detailed protocols for RNA isolation and northern blot hybridization are described in Chapter 10. The major focus of this section is on how to analyze northern blot data. Assuming that the mRNA of the gene is 1 kb, and that specific oligonucleotides or the cDNA is labeled as the probe, as shown in Figure 8.11, in control cells (lane 1), only a weak 1-kb band is detected. This is the endogenous mRNA level in the cells. In contrast, putative clones show overexpression of the mRNA (lanes 2 to 4) as compared with the control cells.

## 8.7.3 DETERMINATION OF INTEGRATION COPY NUMBER BY SOUTHERN BLOT ANALYSIS

### 8.7.3.1 Isolation of Genomic DNA from Cultured Cells

- (1) Aspirate the culture medium from cultured cells and rinse the cells twice in PBS.
- (2) Add 10 ml/60 mm culture plate (with approximately  $10^5$  cells) of DNA isolation buffer to the cells and allow the cells to be lysed for 5 min at room temperature with shaking at 60 rev/min.
- (3) Incubate the plate at 37°C for 5 h or overnight to degrade proteins and extract the genomic DNA.
- (4) Allow the lysate to cool to room temperature and add 3 volumes of 100% ethanol (precooled at  $-20^{\circ}\text{C}$ ) to the lysate. Gently mix it and allow the DNA to be precipitated at room temperature with slow shaking at 60 rev/min. Precipitated DNA, like white fibers, should be visible in 20 min.
- (5) “Fish” out the DNA using a sterile glass hook or spin down the DNA. Rinse the DNA twice in 70% ethanol and partially dry the DNA for 40 to 60 min at room temperature to evaporate the ethanol. The DNA can be directly subjected to restriction enzyme digestion without being dissolved





**FIGURE 8.12** DNA analysis by Southern blotting. Lane 1: nontransfected cells. Lanes 2 to 3: putatively transfected cell lines.

in TE buffer or dd.H<sub>2</sub>O. We usually overlay the precipitated DNA with an appropriate volume of restriction enzyme digestion cocktail and incubate the mixture at the appropriate temperature for 12 to 24 h. The digested DNA is mixed with an appropriate volume of DNA loading buffer and is now ready for agarose gel electrophoresis.

- *DNA isolation buffer*  
 75 mM Tris-HCl, pH 6.8  
 100 mM NaCl  
 1 mg/ml protease K  
 0.1% (w/v) *N*-lauroylsarcosine

### 8.7.3.2 Analysis of Southern Blot Data

Chapter 7 describes the detail protocols for Southern blot hybridization. Assuming that genomic DNA is digested with a unique restriction enzyme that cut outside of the endogenous gene or cDNA introduced, and that the cDNA is labeled as the probe for hybridization, as shown in Figure 8.12, lane 1 represents the control cells containing one band (5 kb) of the gene. Lane 2 shows that a putative clone carries one copy insertion of the introduced cDNA. In lane 3, a putative clone shows two copies of integration of the cDNA.

## 8.7.4 EXPRESSION ASSAY OF A REPORTER GENE

### 8.7.4.1 Activity Assay of CAT

#### 8.7.4.1.1 Protocol 1. Preparation of a Cytoplasmic Extract from Transfected Cells for the CAT Assay

1. For transient transfection, approximately 48 to 72 h after transfection, remove the culture medium from the dish and wash the cells twice with 10 ml PBS. For stable transfection, proteins can be extracted from stably transfected cells.

2. Aspirate the PBS buffer and add 1 ml of fresh PBS. Loosen and resuspend the cells into the buffer using a sterile rubber policeman.
3. Transfer the cell suspension into a fresh microcentrifuge tube, centrifuge at 1200 g for 5 min, and decant the supernatant.  
Note: *Do not centrifuge at top speed. Otherwise, the cells may rupture.*
4. Resuspend the cells in 0.3 ml of 250 mM Tris-HCl, pH 8.0.
5. Lyse the cells by 3 to 4 cycles of freezing (dry ice or dry ice-methanol bath, 5 min) and thawing (37°C, 5 to 10 min).
6. Centrifuge at 10,000 g for 10 min in a microcentrifuge and transfer the supernatant (extract) to a fresh tube. Store the extract at -70°C before use.

#### 8.7.4.1.2 Protocol 2. CAT Enzyme Assay

The CAT enzyme, expressed by the CAT gene, originally comes from bacteria. It catalyzes the conversion of [<sup>14</sup>C]chloramphenicol to its 1-acetyl and 3-acetyl derivatives. The derived products are separated from the unconverted compound by TLC on plates that are precoated with silica gel, which are then exposed to x-ray film for autoradiography.

1. Add the following components into a microcentrifuge tube:

Prepared cell extract	0.1 ml
500 mM Tris-HCl, pH 8.0	60 µl
[ <sup>14</sup> C]Chloramphenicol (0.025 mCi/ml) 10 µl	
<u><i>n</i>-Butyryl coenzyme A (5 mg/ml)</u>	<u>10 µl</u>
Total volume	180 µl

Note: *A standard curve for CAT activity includes one blank with the CAT enzyme.*

2. Incubate reaction at 37°C for an optimum period (0.5 to 20 h) as determined from previous experiments.
3. Terminate the reaction by adding 0.5 ml of ethyl acetate to the tube for the TLC assay and vortex for 1 min.
4. Centrifuge at 10,000 g for 4 min and transfer the upper, organic phase to a fresh tube and dry down the ethyl acetate in a vacuum evaporator.
5. Resuspend the residue in 20 µl of ethyl acetate and spot 10 µl of each sample onto a silica gel TLC plate and air-dry.
6. Place the TLC plate in a tank containing 100 ml of solvent (chloroform/methanol, 95:5). Once the solvents migrate up to about 1 cm from the top of the plate, remove the plate and air-dry.
7. Expose the plate to x-ray film for 10 h or overnight at room temperature. In order to carry out a quantitative assay, for each sample, slice a square corresponding to the monoacetylated form from the silica plate and place in a vial. Add 5 to 10 ml of scintillation fluid to the vial and count in a scintillation spectrometer.

#### 8.7.4.2 Luciferase Assay

Luciferase is encoded by the luciferase gene. Its assay is based on an oxidation reaction mediated by luciferyl-CoA, and light is produced as a result of this reaction.

1. For each sample, add 30  $\mu\text{l}$  of the cell extract as previously described to a vial containing 150  $\mu\text{l}$  of luciferase assay reagent at room temperature.
2. Quickly place the reaction mixture in a luminometer and measure light produced for a period of 10 s over a 2- to 3-min period depending on the sensitivity.

Note: *The luciferase activity decreases very rapidly with time.*

### Reagents needed

- *Luciferase assay reagents*
  - 20 mM Tricine
  - 1.07 mM  $(\text{MgCO}_3)_4 \text{Mg}(\text{OH})_2 \cdot 5\text{H}_2\text{O}$
  - 0.1 mM EDTA, pH 7.8
  - 2.67 mM  $\text{MgSO}_4$
  - 33.3 mM DTT
  - 0.27 mM coenzyme A
  - 0.47 mM luciferin
  - 0.53 mM ATP
  - Adjust the pH to 7.8

#### 8.7.4.3 $\beta$ -Galactosidase Assay

1. For each sample, add the following components to a microcentrifuge tube.

Magnesium solution	3 $\mu\text{l}$
CPRC (4 mg/ml)	66 $\mu\text{l}$
0.1 M sodium phosphate buffer	200 $\mu\text{l}$
Cell extract	31 $\mu\text{l}$
Total volume	300 $\mu\text{l}$

*For blank:*

Magnesium solution	3 $\mu\text{l}$
CPRC (4 mg/ml)	66 $\mu\text{l}$
0.1 M sodium phosphate buffer	200 $\mu\text{l}$
0.25 M Tris-HCl, pH 8.0	31 $\mu\text{l}$
Total volume	300 $\mu\text{l}$

2. Incubate at 37°C for 30 to 60 min and add 0.7 ml of 1 M of  $\text{Na}_2\text{CO}_3$  to terminate the reaction.
3. Measure the absorbency at  $A_{574 \text{ nm}}$  against blank reference.

### Reagents needed

- Magnesium solution
  - 0.1 M  $\text{MgCl}_2$
  - 5 M 2-mercaptoethanol
- 0.1 M sodium phosphate buffer, pH 7.3

- CPRG solution  
4 mg/ml chlorophenol red- $\beta$ -D-galactopyranoside in 0.1 M sodium phosphate buffer

#### 8.7.4.4 $\beta$ -Galactosidase Staining of Cells

This is a fast procedure to assay the activity of the *lac Z* gene if it is incorporated into the DNA construct.  $\beta$ -Galactosidase can hydrolyze X-gal (5-bromo-4-chloro-3-indolyl- $\beta$ -D-galactoside) and yield a blue precipitate, staining the cells blue. Protocol is as follows:

1. Culture the stably transfected cells in a Petri dish for 1 to 2 days.
2. Aspirate the medium and rinse the cells with PBS.
3. Fix the cells in 0.2% glutaraldehyde or 4% paraformaldehyde (PFA) for 5 to 10 min at room temperature.
4. Wash the cells for  $3 \times 5$  min.
5. Stain the cells with X-gal solution for 1 to 24 h at 37°C.
6. Wash the cells for  $3 \times 5$  min in PBS. Any blue cells or colonies indicate that the cells express  $\beta$ -galactosidase, and that the cells most likely contain the targeted gene.

#### Reagents needed

- *Potassium phosphate buffer (PBS)*  
2.7 mM KCl  
1.5 mM  $\text{KH}_2\text{PO}_4$   
135 mM NaCl  
15 mM  $\text{Na}_2\text{HPO}_4$   
Adjust pH to 7.2, then autoclave
- Preparation of 4% (w/v) paraformaldehyde (PFA) fixative (1 l):
  - (a) Carefully weigh out 40 g paraformaldehyde powder and add it to 600 ml preheated dd.H<sub>2</sub>O (55 to 60°C) and allow the paraformaldehyde to dissolve at the same temperature with stirring.  
*Caution: Paraformaldehyde is toxic and should be handled carefully. The preparation should be carried out in a fume hood on a heating plate. The temperature should not be above 65°C and the fixative should not be overheated.*
  - (b) Add one drop of 2 N NaOH solution to clear the fixative.
  - (c) Remove from heat source and add 333.3 ml (1/3 total volume) of 3 $\times$  PBS (8.1 mM KCl, 4.5 mM  $\text{KH}_2\text{PO}_4$ , 411 mM NaCl, 45 mM  $\text{Na}_2\text{HPO}_4$ , pH 7.2, autoclaved).
  - (d) Adjust the pH to 7.2 with 4 N HCl and bring the final volume to 1 l with dd.H<sub>2</sub>O.
  - (e) Filter the solution to remove undissolved fine particles, cool to room temperature, and store at 4°C until use.

- X-gal solution:  
PBS solution contains 0.5 mg/ml X-gal and 10 mM  $K_3 [Fe(CN)_6]$ . X-gal stock solution contains 50 mg/ml in dimethylsulfoxide (DMSO) or dimethylformamide. The stock solution should be kept in a brown bottle at  $-20^\circ\text{C}$  before use.

## 8.8 GENERATION OF TRANSGENIC MICE FROM SENSE ES CLONES

Detailed protocols are described in Chapter 9.

## 8.9 CHARACTERIZATION OF TRANSGENIC MICE

Detailed protocols are given in Chapter 9.

### Troubleshooting Guide

1. *Low efficiency of transfection of cells by liposomes, electroporation, and calcium phosphate methods.* If cells are normal and the cell density is appropriate, it is likely that the amount of DNA constructs used and parameters applied in transfection are not optimal. Make sure to optimize the conditions for transfection of the cells, including DNA concentration, lipids ratio, and voltage pulse. In case of stable transfection, ensure that the concentration of the drug used in the selection is not too high. A killing curve should be established.
2. *Low titer of retroviruses.* The virus stock is overdiluted or there is a low density of retrovirus particles due to low efficiency of stable transfection of packaging cells with modified virus DNA constructs. Try to use a good packaging cell line and optimize the parameters for transfection. One may perform reinfection to amplify the virus titer.
3. *Low efficiency of transfection with frozen high titer viruses.* Assuming transfection conditions are optimal, it is very likely that the viruses have lost significant activity. It is recommended that high titer viruses be used within 2 h. Frozen aliquots should not be frozen and thawed.
4. *Southern blot analysis shows that sense cDNA is correctly integrated into the genome of the host cell, but no exogenous mRNA and protein are expressed.* Something is wrong with the inserted cDNA. This could be due to a minor mutation that occurs during integration. Once this occurs, the best way is to forget it. However, if one wishes to verify the cell clone, he may use a PCR approach to sequence the insertion site, especially the 5'-end of the cDNA introduced. If some bases are missing or ORF has been shifted, there is no way to salvage the cell clone.
5. *Low level expression of mRNA and protein of interest.* This is obviously related to the activity of the promoter driving the expression of the introduced cDNA. If it is a constitutive promoter, its activity is low. Try to switch to other stronger promoters. If the driving promoter is inducible, try to optimize the concentration of the appropriate inducer.

6. *Some of drug selected stably transfected cell clones show 100% death during subsequent cloning or culture in the selection medium.* If these clones are not frozen, it is certain that these isolated clones are false stably transfected cells. It is likely that during trypsinization and resuspension, the cells are not well suspended. Instead, they are aggregated. After transfection, some of the cells within the aggregated colonies receive less drug and still undergo proliferation, forming false colonies that are picked up in the process. During the trypsinizing and picking up, these cells become loosened by physical force. Because they are not real stable colonies, they are killed by the drug selection medium during the subsequent expanding or culture.
7. *Very few frozen, stably transfected cells survive during subsequent culture.* Certainly, this is due to inappropriate freezing. Make sure to use 5% to 10% (v/v) DMSO in the freezing medium.

## REFERENCES

1. Wu, W., and M. J. Welsh. 1996. Expression of HSP27 correlates with resistance to metal toxicity in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Applied Toxicology and Pharmacology* 141: 330–339.
2. Mehlen, P., X. Preville, P. Chareyron, J. Briolay, R. Klemenz, and A.-P. Arrigo. 1995. Constitutive expression of human hsp27, *Drosophila* hsp27, or human  $\alpha$ B-crystallin confers resistance to TNF- and oxidative stress-induced cytotoxicity in stably transfected murine L929 fibroblasts. *Journal of Immunology* 154: 363–374.
3. Iwaki, T., A. Iwaki, J. Tateishi, and J. E. Goldman. 1994. Sense and antisense modification of glial  $\alpha$ B-crystallin production results in alterations of stress fiber formation and thermoresistance. *Journal of Cell Biology* 15: 1385–1393.
4. Yang, N. S., J. Burkholder, B. Roberts, B. Martinell, and D. McCabe. 1990. *In vitro* and *in vivo* gene transfer to mammalian somatic cells by particle bombardment. *Proceedings of the National Academy of Sciences of the United States of America* 87: 9568.
5. Carmeliet, P., L. Schoonjans, L. Kiechens, B. Ream, J. Degen, R. Bronson, R. D. Vos, J. Oord, D. van den Collen, and R. C. Mulligan. 1994. Physiological consequences of loss of plasminogen activator gene function in mice. *Nature* 368: 419.
6. Zelenin, A. V., A. V. Titomirov, and V. A. Kolesnikov. 1989. Genetic transformation of mouse cultured cells with the help of high-velocity mechanical DNA injection. *FEBS Letters* 244: 65.
7. Johnston, S. A. 1990. Biolistic transformation: microbes to mice. *Nature* 346: 776.
8. Moore, K. A., and J. W. Belmont. 1993. Analysis of gene transfer in bone marrow stem cells. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: IRL Press, Oxford University Press, Inc.
9. Hasty, P., and A. Bradley. 1993. Gene targeting vectors for mammalian cells. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: IRL Press, Oxford University Press.
10. Papaioannou, V., and R. Johnson. 1993. Production of chimeras and genetically defined offspring from targeted ES cells. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: IRL Press, Oxford University Press, Inc.
11. Gossler, A., and J. Zachgo. 1993. Gene and enhancer trap screens in ES cell chimeras. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: IRL Press, Oxford University Press, Inc.
12. Wu, W. 1995. Gene transfer and expression in animals. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. J. Cseke. Boca Raton, FL: CRC Press.

---

# 9 Gene Underexpression in Cultured Cells and Animals by Antisense DNA and RNA Strategies

## 9.1 INTRODUCTION

To gain insight into the function of the protein of a gene of interest, antisense DNA and RNA approaches have been widely applied in eukaryotes in which antisense oligonucleotides or antisense RNA transcripts that are expressed successfully inhibit the expression of specifically targeted sense RNA or mRNA.<sup>1-6</sup> In recent years, the antisense approach has been utilized to address fundamental questions in molecular and cellular biology in animals, human diseases, and plants.<sup>1,3,6-10</sup> Gene underexpression refers to a decrease in the protein level of a gene, which in turn may alter the function of the gene.

Although the precise mechanism by which antisense DNA/RNA inhibits gene expression is not well known, it is generally assumed that antisense oligonucleotides or antisense RNA can interact with complementary sequence or sense RNA transcripts by base pairing, thus blocking the processing and/or translation of the sense RNA or mRNA. The duplex of antisense RNA and sense RNA may be rapidly degraded, resulting in a decrease in specific mRNA level. There is no evidence, however, that the antisense RNA can directly affect the target gene or DNA sequence. Therefore, the primary principle of using antisense DNA and antisense RNA is to partially or completely inhibit the expression of the target gene or mRNA level.

How to underexpress a gene of interest? In general, gene underexpression by antisense DNA or RNA approaches consists of highly involved techniques that include design of antisense oligonucleotides, isolation and characterization of a specific cDNA, gene transfer, and analysis of gene expression in transfected cells or transgenic animals. This chapter will focus on techniques using exogenous antisense oligonucleotides and antisense cDNA constructs to down-regulate the expression of a specific gene. These protocols have been successfully utilized in our laboratories.

## 9.2 ANTISENSE OLIGONUCLEOTIDE APPROACHES

### 9.2.1 DESIGN AND SYNTHESIS OF ANTISENSE OLIGONUCLEOTIDES


Antisense oligomers can be chemically synthesized based on any known sequence of DNA or RNA of interest. If the DNA sequence is not known, a specific peptide

sequence is available. Antisense oligonucleotides can be designed based on the amino acid sequence of the peptide.

1. Design appropriate antisense oligomers based on the target, known sequence of the mRNA (sense RNA) or its first strand cDNA, which is the poly(T) or (–)strand. For example, if the target sequence is 5'-ACAUGCCCCUCAACGUUAGC-3' (mRNA), the antisense oligonucleotide should be designed as 3'-TGTACGGGGAGTTGCAATCG-5'. The oligo is complementary to the target sequence and both can form a hybrid as follows:



If, on the other hand, the amino acid sequence is known, the nucleotide sequence can be derived.



Tips:

A. *Target region(s)*

- (a) *The upstream nucleotide sequence from the initiation codon AUG and the first codon AUG should be selected as the most effective target region when designing an antisense oligomer. The hybridization of the antisense oligomers may prevent the small subunit of the ribosome from interacting with the upstream region of the initiating AUG codon, thus blocking the initiation of translation.*
- (b) *Antisense oligonucleotides can also be designed to be complementary to the coding regions such as conserved motif(s) to block the chain elongation of the specific polypeptide. However, it will be less effective compared to (a).*
- (c) *The terminal region of translation is a good target to block the termination of translation. The partial-length polypeptide may not be folded properly and will be rapidly degraded.*
- (d) *The most effective strategy for blocking translation of an mRNA is to use antisense oligonucleotides that are complementary to the upstream region including the first codon AUG and to the terminal site of the coding region. The efficiency of inhibition of specific gene expression can be up to 95%.*
- (e) *Unlike the design of primers for polymerase chain reaction, which involves the  $T_m$  value, the oligomers for inhibition of gene expression do not need computer analysis of  $T_m$ .*



**B. Oligomer modifications**

*Conventional or unmodified oligonucleotides may be substrates for nucleases (DNases) such as RNase H and cannot effectively block the expression of a specific gene. To prevent oligonucleotides from being degraded by nucleases, the antisense oligomers may be chemically modified before use. Active compounds such as cross-linking and cleaving reagents can be coupled with the oligomers so that they will be much more stable, and they cause irreversible damage to the target sequence. Subsequently, this will result in very effective blocking of translation. For example, oligomers may be conjugated to photosensitizers. Antisense oligomer linked to either nuclease or chemical reagents will produce sequence-dependent cleavage of the target RNA after the binding of the oligomer to its complementary sequence. The cleavage site in the target RNA is usually in the area surrounding the modified antisense oligomer. This will prevent the translation of the target RNA. Chemical groups linked to the end of the oligomers can introduce strand breaks either directly (e.g., metal chelates and ellipticine) or indirectly (e.g., photosensitizers) after alkaline treatment. Metal complexes such as  $Fe^{2+}$ -EDTA,  $Cu^{+}$ -phenanthroline, and  $Fe^{2+}$ -porphyrin can also produce hydroxyl radicals (OH) that can oxidize the sugar and subsequently result in phosphodiester bond cleavage. Phosphodiester internucleoside linkages may be substituted with phosphotriester,<sup>3-5</sup> methylphosphonate, phosphorothioate, or phosphoroselenoate. Oligomers that are modified to phosphorothioates and phosphoroselenoates are resistant to nuclease (RNase H) and can induce cleavage of the target RNA. For this reason, phosphorothioate analogs have been widely used in cultured cells.*

**C. Oligomer size**

*Size ranges from 15- to 30-mer, depending on the particular nucleotide sequences.*

**D. Oligomer dose**

*Dose is 10 to 100  $\mu M$  in total, depending on the particular experiments.*

2. Based on the design, synthesize and purify appropriate antisense oligonucleotides by a DNA synthesizer according to the instructions.

## **9.2.2 TREATMENT OF CULTURED CELLS WITH ANTISENSE OLIGOMERS AND DETERMINATION OF THE OPTIMUM DOSE OF OLIGOMERS BY WESTERN BLOT ANALYSIS**

1. Under sterile conditions, culture the cells of interest in prewarmed, appropriate medium such as modified Dulbecco's modified Eagle's medium containing 10% to 15% (v/v) heat-inactivated fetal bovine serum (FBS) or 5% to 10% (v/v) heat-inactivated newborn calf serum (NCS) with appropriate antibiotics such as 50  $\mu g/ml$  penicillin and 100  $\mu g/ml$  streptomycin. Culture the cells at 37°C in 5%  $CO_2$  and 95% air incubator. Allow cells to grow to 70% to 80% confluence.

2. Trypsinize (for attaching cell lines) and spin down the cells at 1000 rev/min for 5 min under sterile conditions. In a sterile laminar flow hood, carefully aspirate the supernatant and resuspend the cells in a minimum volume of fresh medium. Determine the viability and density of the cells by counting Trypan blue excluding cells using a hemocytometer.
3. Perform a dose-response experiment using the synthetic antisense oligomers in order to optimize the amount of the oligomers to use in order to efficiently block the expression of the gene of interest as follows:
  - (a) Seed  $2 \times 10^6$  cells in each well of 24-well culture plates or T-flasks containing 2 to 5 ml of culture medium. Prepare seven wells or T25 flasks with equal density of cells.
  - (b) Add the oligomers to the medium as follows:

No treatment: no antisense oligomer used as a negative control

Treatment #1: 6  $\mu\text{M}$  antisense oligomers

Treatment #2: 4  $\mu\text{M}$  antisense oligomers

Treatment #3: 2  $\mu\text{M}$  antisense oligomers


Treatment #4: 1  $\mu\text{M}$  antisense oligomers

Treatment #5: 0.5  $\mu\text{M}$  antisense oligomers

Treatment #6: 0.25  $\mu\text{M}$  antisense oligomers

*Note: The initial concentration of the appropriate oligomers varies with a particular experiment.*

- (c) Incubate the cells for 2 to 6 days, add the same concentration of the oligomers to the cells every day, and gently mix in the medium.
- (d) Harvest the cells for protein analysis. If the protein of interest is a secretory protein, the supernatant should be used for extraction of the proteins. If not, the pellet of cells from each treatment should be washed with an appropriate buffer, lysed, and extracted for proteins analysis. The detailed protocols for protein extraction from cultured cells are described in Chapter 11. The protein of interest may be purified from the total proteins with specific antibodies against the protein via the immunoprecipitation method. We recommend to use total proteins for inhibition analysis with the antibodies against an appropriate house-keeping gene product as a normalization control.
- (e) Analyze the inhibition of protein expression by western blotting. The detailed protocol for western blot hybridization is described in Chapter 11. The major task here is to focus on analysis of western blot data. The data are diagrammed in Figure 9.1. Assuming that the protein to be inhibited is 60 kDa, and that monoclonal antibodies are used in western blotting, as shown in the diagram, the oligomer at 4  $\mu\text{M}$  is the optimal concentration that sufficiently inhibits the expression of the protein. Antibodies against actin or tubulin should be used as controls. The detected signals for actin in each of the samples are very similar, indicating that the amount of total protein from each of the cell extracts is equally loaded into sodium dodecyl sulfate-polyacrylamide gel electrophoresis (SDS-PAGE).



**FIGURE 9.1** Protein analysis by western blotting after antisense oligonucleotide treatment. Lane 1: Control cells. Lanes 2 to 7: Underexpression of the 60 kDa protein after treatment of oligomers at 6, 4, 2, 1, 0.5, and 0.25 mM, respectively.

### 9.2.3 TREATMENT OF CULTURED CELLS USING AN OPTIMUM DOSE OF OLIGOMERS


1. Seed  $2 \times 10^6$  cells in each T-flask containing 5 ml of culture medium. Prepare three replicates for each of the samples.
2. Add the optimum dose of antisense oligomers ( $4 \mu\text{M}$ ) to the medium for each of the samples and culture for appropriate time intervals as follows:

Samples #1: no oligomer used as a control for 7 days  
 Sample #2:  $4 \mu\text{M}$  antisense oligomers for 0.5 day  
 Sample #3:  $4 \mu\text{M}$  antisense oligomers for 1.5 days  
 Sample #4:  $4 \mu\text{M}$  antisense oligomers for 2 days  
 Sample #5:  $4 \mu\text{M}$  antisense oligomers for 2.5 days  
 Sample #6:  $4 \mu\text{M}$  antisense oligomers for 3 days  
 Sample #7:  $4 \mu\text{M}$  antisense oligomers for 3.5 days  
 Sample #8:  $4 \mu\text{M}$  antisense oligomers for 4 days  
 Sample #9:  $4 \mu\text{M}$  antisense oligomers for 5 days  
 Sample #10:  $4 \mu\text{M}$  antisense oligomers for 6 days  
 Sample #11:  $4 \mu\text{M}$  antisense oligomers for 7 days

3. Incubate the cells for 6 days, add the same amount of oligomers to the cells every day, and gently mix in the medium.

### 9.2.4 ANALYSIS OF INHIBITION OF GENE EXPRESSION BY WESTERN BLOTTING

1. Harvest the cells at step 3 above for protein analysis. If the protein of interest is a secretory protein, the supernatant should be used for extraction of proteins. If not, the pelleted cells from each treatment should be washed with an appropriate buffer, lysed, and extracted for protein analysis. The detailed protocols for protein extraction from cultured cells are described in Chapter 11. The protein of interest may be purified from the total proteins



**FIGURE 9.2** Protein analysis by western blotting after antisense oligonucleotide treatment. Lane 1: Control cells. Lanes 2 to 11: Time-course of underexpression of the 60 kDa protein after treatment of oligomers at 4 mM for 0.5, 1, 1.5, 2, 2.5, 3, 3.5, 4, 5, 6, and 7 days, respectively.

with specific antibodies against the protein using the immunoprecipitation method. We recommend to use total proteins for the inhibition analysis with the antibodies against an appropriate housekeeping gene product as a normalization control.

- Analyze the inhibition of protein expression by western blotting. The detailed protocol for western blot hybridization is described in Chapter 11. The major task here is to focus on analysis of western blot data. An example of western blot data is diagrammed in Figure 9.2. Assuming that the protein to be inhibited is 60 kDa, and that monoclonal antibodies are used in the western blotting, as shown in the figure, the level of the 60-kDa protein gradually decreases during the time-course of oligomer treatment. Antibodies against actin are used as control. The detected signals for actin in each of samples are very similar, indicating that the amount of total protein from each of the cell extracts is equally loaded into the SDSPAGE.


### 9.3 DESIGN AND SELECTION OF PLASMID-BASED EXPRESSION VECTORS

Use of antisense oligonucleotides, described above, provides an effective and fast strategy for down-regulation of the expression of a protein of interest. Nonetheless, this approach gives very temporary underexpression. However, to stably inhibit the expression of a specific gene, a genetic approach is necessary. In fact, to use stably transfected cell lines or to make transgenic animals to study the function of a gene, one may have to choose the strategy of stable genetic alteration of the expression of the gene of interest.

Detailed descriptions for the design and selection of eukaryotic expression vectors are given in Chapter 8.

### 9.4 PREPARATION OF PLASMID ANTISENSE cDNA CONSTRUCTS

cDNA isolation and characterization are described in Chapter 3. Restriction enzyme digestion of DNA, ligation, bacterial transformation, and purification of plasmid DNA are given in Chapter 4.



**FIGURE 9.3** Diagram of a retrovirus expression vector.

This section emphasizes special notes regarding the preparation of antisense cDNA constructs.

1. *Length of cDNA to be cloned.* Unlike gene overexpression described in Chapter 8, underexpression of a gene of interest does not need full-length cDNA, nor is the entire ORF required. In our experience, the 5'UTR and the 5'-portion of the ORF have high efficiencies of translational inhibition.
2. *Orientation of the cDNA.* It is absolutely important that the cDNA be placed in the antisense orientation downstream from the driving promoter. In other words, the poly(A) strand, or (+) strand of the cDNA, should be 3' → 5' downstream from the promoter in order to make 5' → 3' poly(T) RNA or antisense RNA (Figure 9.3).
3. *Start or stop codon.* Unlike gene overexpression in Chapter 8, the presence of a stop or start codon between the driving promoter and the first start codon ATG of the cDNA is acceptable. Remember, antisense RNA will primarily hybridize with sense RNA. As a result, mRNA will undergo degradation or the translation process is blocked.

## 9.5 TRANSIENT TRANSFECTION OF CULTURED CELLS WITH ANTISENSE CONSTRUCTS

Methods and detailed protocols are described in Section 8.4.1 in Chapter 8.

## 9.6 STABLE TRANSFECTION OF CULTURED CELLS WITH ANTISENSE DNA CONSTRUCTS

### 9.6.1 METHOD A. TRANSFECTION BY LIPOSOMES

Liposome-mediated transfection is relatively safe and has a higher efficiency of transfection in cultured cells. It is suitable for both transient and stable transfection of tissues or cells. It mandates a smaller amount of DNA for transfection as

compared with electroporation and other methodologies. Lipofectin reagents are commercially available (e.g., Gibco BRL Life Technologies). Liposomes are composed of polycationic lipids and neutral lipids at an appropriate ratio (e.g., 3:1). The primary principles of this method are: (1) the positively charged and neutral lipids can form liposomes that can complex with negatively charged DNA constructs; (2) the DNA–liposome complexes are applied to cultured cells and are uptaken by endocytosis; (3) the endosomes undergo breakage of membranes, releasing the DNA constructs; and (4) the DNA enters the nucleus through the nuclear pores and facilitates homologous recombination or integration into the chromosomes of the cell.

The major disadvantage of the lipotransfection method is that if the lipids/DNA and the cell density are not appropriate, severe toxicity will be generated, killing quite a large number of cells. ES cells are more sensitive to toxicity compared with other fibroblasts such as NIH 3T3 and mouse STO cells.

1. Harvest cells by gentle trypsinization as described in Chapter 16. Centrifuge the cells at 900 rev/min for 5 min and well resuspend the cells in normal culture medium at about  $10^6$  cells/ml.

*Note: Make sure that the cells are gently but well suspended before transfection because aggregation of the cells may cause difficulty in the isolation of stably transfected cell clones.*

2. In a 60-mm tissue culture dish, seed the suspended cells at about  $1 \times 10^6$  cells in 5 ml of normal culture medium. Allow the cells to grow under normal conditions for 12 h. Proceed to transfection.

*Note: Mouse ES cells grow fast and form multiple layers of clones instead of monolayers seen in other cell lines. Because of these features, it is not recommended to overculture ES cells before transfection since multilayers of ES cells may result in a low efficiency of transfection and a high percentage of potential cell death. Therefore, once a relatively high density of cells has been obtained, transfection can be carried out as soon as the ES cells attach to the bottom of the dish and grow for 6 to 12 h.*

3. During cell culture, one can linearize DNA constructs to be transferred by using a unique restriction enzyme. Protocols for appropriate restriction enzyme digestion are described in Chapter 4.
4. In a sterile laminar flow hood, dissolve 10 to 20  $\mu\text{g}$  DNA in 0.1 ml of serum-free medium (free of antibacterial agents) and dilute the lipofectin reagents 2- to 5-fold in 0.1 ml of serum-free medium (free of antibacterial agents). Combine and gently mix the DNA–lipids media in a sterile tube. Allow this mixture to incubate at room temperature for 15 to 30 min. A cloudy appearance of the medium indicates the formation of DNA–liposome complexes.
5. Rinse the cells once with 10 ml of serum-free medium. Dilute the DNA–liposome solution to 1 ml in serum-free medium (free of antibacterial agents) and gently overlay the cells with the diluted solution. Incubate the cells for 4 to 24 h under normal culture conditions. During this period, transfection takes place.

6. Replace the medium with 5 ml of fresh, normal culture medium with serum every 12 to 24 h. Allow the cells to grow for 2 to 3 days before doing drug selection.
7. Trypsinize the cells and plate the cells at a density of about 3000 cells/100 mm dish or T25 flask culture for 24 h at 37°C with 5% CO<sub>2</sub>. Proceed to drug selection.

### 9.6.2 METHOD B. TRANSFECTION BY MICROINJECTION

Microinjection is one of the most efficient transfection methods, although the number of cells that can be injected within a given time is usually limited, depending on personal experience. The equipment for microinjection should include: (1) an injection microscope on a vibration-free table (Diaphot TMD microscope with Nomarski optics is available from Nikon Ltd.); (2) an inverted microscope for setting up the injecting chamber, holding pipette, and needle (A SMZ-2B binocular microscope is available from Leitz Instruments Co); (3) two sets of micromanipulators (Leitz Instruments Ltd.); (4) Kopf needle puller model 750 (David Kopf Instruments); (5) a finer needle and a pipette holder; and (6) a Schott-KL-1500 cold light source (Schott).

1. Thoroughly clean a depression slide with teepol-based detergent and extensively rinse it with tap water and distilled water. Rinse it with ethanol and air dry. Add a drop of culture medium to the depression slide and a drop of liquid paraffin on top of a drop of medium. This is preparation for suspension cells but not for fibroblast cells attaching on the bottom of culture dishes or flasks.
2. Assemble all parts that are necessary for the injection according to the manufacturer's instructions. Carry out pretesting of the procedure before injection of the DNA sample.
3. For cultured fibroblast cells attached to the bottom, transfer the cultured cells onto the stage under the microscope. For cell suspensions, carefully transfer the cells to the medium drop using a handling pipette that can take up the cells by suction under the microscope.
4. Prepare microinjection needles with Kopf needle puller (model 750). Slowly take the DNA sample up into the injection needle by capillary action.
5. Under the microscope, hold the suspended cells with the holding pipette and use the micromanipulator to individually insert the needle into the cell. Slowly inject the DNA sample into the nucleus. The pressure can be maintained on the DNA sample in the needle by a syringe connected to the needle holder. As soon as the nucleus swelling occurs, immediately remove the needle a short distance from the cell. The volume injected is approximately 1 to 2 pl. For cultured fibroblast cells attached to the bottom of a culture dish or flask, no holding of the cell with a pipette is needed. Injection can be directly performed into the nucleus of the cell.

6. Transfer the injected cells to one side and repeat injections for other cells. About 40 to 60 cells can be injected in 1 to 2 h, depending on the individual's experience.
7. Carefully transfer the injected cells back to the incubator. Allow the cells to grow for 2 to 3 days before they are harvested or subjected to drug selection.

### 9.6.3 METHOD C. TRANSFECTION BY ELECTROPORATION

Detailed protocols are given in Chapter 8.

### 9.6.4 METHOD D. TRANSFECTION BY RETROVIRUS VECTORS

Detailed protocols are described in Chapter 8.

## 9.7 SELECTION OF STABLY TRANSFECTED CELL LINES WITH APPROPRIATE DRUGS


Detailed descriptions are given in Chapter 8.

## 9.8 CHARACTERIZATION OF STABLY TRANSFECTED CELL CLONES

Characterization of stably transfected cell lines will provide information about whether the developed clones contain and express antisense-induced inhibition in the cells.


### 9.8.1 ANALYSIS OF GENE UNDEREXPRESSION AT THE PROTEIN LEVEL BY WESTERN BLOTTING

The detailed protocols for protein extraction and western blot hybridization are described in Chapter 11. The major focus of this section is on how to analyze western blot data. Assuming that the product or protein of the cDNA is 80 kDa, and that monoclonal antibodies have been raised to be against the 80-kDa protein, as shown in Figure 9.4, in control cells (lane 1), a strong 80-kDa band is detected. In contrast, putative antisense clones show a significant reduction of the 800-kDa protein (lanes 2 to 4) compared with the control cells.



**FIGURE 9.4** Protein analysis of antisense clones by western blotting. Lane 1: Nontransfected cells. Lanes 2 to 4: Underexpression of the 80 kDa protein in different antisense cell clones.






**FIGURE 9.5** Antisense RNA analysis by northern blotting using a sense RNA probe. Lane 1: Nontransfected cells. Lanes 2 to 5: Expression of antisense RNA (0.8 kb) in four antisense clones.

### 9.8.2 EXAMINATION OF THE EXPRESSION OF ANTISENSE RNA BY NORTHERN BLOTTING

The detailed protocols for RNA isolation and northern blot hybridization are described in Chapter 11. The major focus of this section is on how to analyze northern blot data. Assuming that the antisense RNA of the gene is 0.8 kb, and that a specific sense RNA probe is used, as shown in Figure 9.5, in control cells (lane 1), no band is detected. However, four stably transfected clones clearly show expression of antisense RNA (lanes 2 to 5).

### 9.8.3 DETERMINATION OF INTEGRATION COPY NUMBER BY SOUTHERN BLOT ANALYSIS

Chapter 7 describes the detailed protocols for Southern blot hybridization. Assuming that genomic DNA is digested with a unique restriction enzyme that cuts outside of



**FIGURE 9.6** Antisense DNA analysis by Southern blotting using the introduced cDNA as a probe. Lane 1: Nontransfected cells. Lanes 2 and 4: Single copy integration of antisense cDNA. Lane 3: Two copies of insertion of antisense cDNA.

the endogenous gene or cDNA introduced, and that the cDNA is labeled as the probe for hybridization, as shown in Figure 9.6, lane 1 shows the control cells and contains one band. Lanes 2 and 4 have one copy of integration of the introduced cDNA. In lane 3, a clone shows two copies of insertion of the cDNA.

#### **9.8.4 EXPRESSION ASSAY OF REPORTER GENES**

Detailed protocols are described in Chapter 8.

### **9.9 GENERATION OF TRANSGENIC MICE**

There are two methods for the production of transgenic mice. One is to develop stably transfected mouse embryonic stem (ES) cells with antisense cDNA constructs. The ES cells can be injected into female mice to generate genetically altered animals. The other method is to directly inject antisense cDNA constructs into mouse oocytes by microinjection. The injected oocytes are then transferred into the oviduct of a female mouse to produce transgenic mice.

#### **9.9.1 METHOD A. PRODUCTION OF TRANSGENIC MICE FROM STABLY TRANSFECTED ES CELLS**

##### **9.9.1.1 Selection of C57BL/6J Estrous Females**

The C57BL/6J mouse is a well-established strain and is widely chosen as the best choice of host embryo for ES cell chimeras and germline transmission. These mice have a coat color that is different from 129 SVJ mice, which can be used as a coat color selection marker. In order to relatively synchronize the estrous cycle and simplify female selection, it is recommended that female mice be caged together without a male. Their estrous cycle is approximately 3 to 4 days and ovulation usually occurs at about the midpoint of the dark period in a light/dark cycle. This light and dark cycle can be altered to meet one's schedule. For example, the cycle may be adjusted to 14 h light and 10 h darkness. In this way, most strains of mice produce blastocysts that can be utilized for injection in the late morning of the third or fourth day. The question here is how to identify proestrous or estrous females for mating. The basic criteria are the external vaginal epithelial features. At proestrous stage, the vaginal epithelium is usually characterized by being moist, folded, pink/red, and swollen. At the estrous stage, the features of the vaginal epithelium, in general, is dry but not wet, pink but not red or white, wrinkled epithelium on both upper and lower vaginal lips, and swollen. After the females have been caged for a while and when they reach the prediction of proestrous stage, they should be monitored on a daily basis. Once they are at the estrous stage, mating should be allowed to occur.

An alternative way to promote the estrous cycle is through hormonal regulation of ovulation with exogenous hormones. This procedure is termed superovulation. Injection of pregnant mice with mare serum gonadotropin (PMSG, Sigma) can stimulate and induce immature follicles to develop to the mature stage. Superovulation can be achieved by further administration of human chorionic gonadotropin (HCG; Sigma). The procedure is outlined as follows:

1. Three days or 72 to 75 h prior to mating, induce superovulation of 10 to 15 female mice (3 to 4 weeks old) by injecting 5 to 10 units PMSG intraperitoneally into each female between 9:00 A.M. and noon on day 1.
2. Two days or 48 to 50 h later, inject 5 to 10 units of HCG intraperitoneally into each female between 9:00 A.M. and noon on day 3. After injection, cage the females and proceed to mate them with sterile males.

*Tip: Superovulation will occur about 12 h after HCG administration. The injection time at step (b) will coincide with the midpoint of the dark cycle.*

### 9.9.1.2 Preparation of a Bank of Sterile Males by Vasectomy

While females undergo their estrous cycle, prepare a stock of sterile males to mate with the estrous female chosen as the embryo transfer host so as to generate pseudo-pregnancy. The following procedures are recommended to be performed in as sterile conditions as possible.

1. Weigh a mouse and use 0.2 to 25 ml of tribromoethanol anesthesia to anesthetize the mouse. Swab the abdomen with 70% ethanol using cotton.
2. Lift the skin free of the peritoneum with forceps and carefully make a 1-cm transverse skin incision at approximately 1 cm rostral to the penis. Carefully make another similar incision through the peritoneum.
3. Use blunt forceps and reach laterally into the peritoneum and carefully grasp the testicular fat pad located ventral to the intestine and attached to the testis. Through the incision, gently pull out the pad together with the testis.
4. Distinguish the vas deferens from the corpus epididymis and carefully separate the vas deferens from the mesentery by inserting the closed tips of the iridectomy scissors through the mesentery. Next, open the scissors and leave the scissors at this position to support the isolation of a length of the vas deferens.
5. Insert two pieces of suture under the vas deferens with forceps, tie up the vas deferens, with forceps, at two sites approximately 2 cm apart, and cut out a piece of the vas deferens (about 1 cm in length) between the two knots.
6. Return the testis to the peritoneum and perform the same procedures on the other side.
7. Suture the peritoneal wall and clip the skin incision with a couple of small wound clips. Leave the vasectomized males for 10 to 14 days to clear the tract of viable sperm and ensure that the males are sterile prior to use for mating.

### Materials needed

- Small blunt, curved forceps
- Three pairs watchmaker's forceps
- Small sharp scissors
- Iridectomy scissors

(These surgical instruments can be wrapped in foil and kept in a 120 to 140°C oven for at least 6 h before use.)

- Surgical gloves
- Small wound clips
- Tribromoethanol anesthesia
- 70% ethanol and cotton
- Surgical silk suture and needle

### 9.9.1.3 Pairing of Estrous Females and Sterile Males

1. Once the estrous females and stud males are ready for mating, cage them together overnight.
2. Check for vaginal plugs in the morning on day 4 and record that this is the first day of pregnancy.

*Tips: If mating takes place, a white or yellow vaginal plug composed of male secretions from the vesicular and coagulating glands should be present within 12 h after mating. The plug may be visible at the surface or out of sight deep in the vagina. Therefore, a narrow, clean steel spatula or its equivalent (3 to 4 mm wide) may be used to detect the plug(s) in the vagina, which feel(s) harder compared with the surrounding soft tissue. Thus, pseudopregnancy has been induced because the males are sterile.*

### 9.9.1.4 Preparation of Blastocyst-Stage Embryos from Pseudopregnant Mice

Approximately 4 days after the presence of vaginal plugs, blastocysts usually present and the uterine lumen can be removed by flushing the uterine horns with embryo culture medium. Surgical gloves should be worn during the procedure.

1. Kill the pregnant females on the fourth day (84 to 96 h) of pregnancy by cervical dislocation.
2. Briefly clean the abdomen with 70% ethanol and make a small, transverse incision in the middle area of the abdomen. Remove the cut hairs with alcohol-soaked cotton.
3. At the incision site, tear the skin and pull it away to the front and hind legs, respectively. At this point, the peritoneum should be exposed.
4. Make a large, transverse incision in the peritoneum to expose the abdominal cavity.
5. Identify the reproductive tract by pushing aside the intestines and use blunt forceps to grasp the point of bifurcation of the uterus near the base of the bladder.
6. Carefully lift the uterus with blunt forceps, remove the supporting mesentery on both sides of the uterus, and cut across the cervix at the base.
7. Remove the entire tract by cutting it between the oviduct and the ovary and place the tract in a sterile Petri dish.
8. Under the low power of a dissecting microscope, carefully remove any mesentery and fat. At the utero-tubal junction site, cut off the oviduct and make an approximately 0.5 cm longitudinal clip at the end of each horn. Finally, cut across the cervix, exposing the entrances to both uterine horns.
9. Rinse the tract with embryo culture medium and place it in a sterile Petri dish. Take up 0.5 ml of embryo culture medium using a small Pasteur pipette

or a pipette attached to a sterile 1 ml tip, insert the tip into the cervical end, and gently flush the lumen a few times. The uterus should be slightly inflated and the medium containing embryos should flow through the tract.

10. Under the low power of a dissecting microscope, quickly transfer the blastocyst-stage embryos that have settled to the bottom of the flush dish into a micromanipulation chamber or dish using a sterile Pasteur pipette or pipette tip.

### Materials needed

- Small blunt, curved forceps
- Watchmaker's forceps
- Small sharp scissors
- Iridectomy scissors
- Surgical gloves
- 70% ethanol and cotton
- Embryo culture medium (1 l)
  - 3.0 g  $\text{Na}_2\text{HPO}_4 \cdot 12\text{H}_2\text{O}$
  - 6.2 g NaCl
  - 0.2 g KCl
  - 0.2 g  $\text{KH}_2\text{PO}_4$
  - 0.1 g  $\text{CaCl}_2 \cdot 2\text{H}_2\text{O}$
  - 0.1 g  $\text{MgCl}_2$
  - 0.05 g Na pyruvate
  - 62 mg Penicillin
  - 1.04 g D-Glucose
  - 100 mg Phenol red

Dissolve well after each addition in 1000 ml distilled water. Add 10% (v/v) of heat-inactivated fetal calf serum to the medium. Filter sterilize and aliquot before use. The medium can be stored at 4°C for up to 5 weeks.

#### 9.9.1.5 Preparation of Micromanipulation Apparatus

Micromanipulation can be set up with a micromanipulator system, including (1) an inverted microscope or a standard microscope (Leitz Instruments, Ltd.), (2) two sets of micromanipulators (Leitz Instruments Ltd.), (3) Kopf needle puller model 750 (David Kopf Instruments), (4) a finer needle and a pipette holder; and (e) a Schott-KL-1500 cold light source (Schott).

##### 1. Holding pipette

To hold and stabilize a blastocyst during the injection of ES cells, a holding pipette needs to be prepared as follows:

- (a) Pull out a length of glass capillary with a pipette puller according to the manufacturer's instructions or by hand over a low flame.
- (b) Break the pipette at point of 70 to 90  $\mu\text{m}$  with a microforge according to the manufacturer's instructions. Fire-polish the tip of the pipette and

close it down to a diameter of approximately 15  $\mu\text{m}$ . The pipette may be further bent so that it can be placed horizontally in the microscope field.

2. *ES cell injection pipettes*

These pipettes will be used to inject ES cells into the blastocyst. The procedures are similar to those described for holding pipette except that the tip should be broken off to generate about 12 to 15  $\mu\text{m}$  for ES cells to pass through. No fire-polishing and bending are necessary.

3. *Blastocyst injection pipettes*

This type of pipette will be utilized to transfer blastocyst embryos for injection of ES cells into the embryos. The procedures are similar to those described for holding pipettes except that the tip should be broken off to generate a relatively large inside diameter (about 130  $\mu\text{m}$ ) for the blastocyst to pass through, and that fire-polishing should be very brief to eliminate the sharp edges.

4. *Embryo transfer pipettes*

These pipettes will be used to transfer the blastocyst embryos containing the injected ES cells back to the uterus of the host. The procedures are similar as those described for holding pipettes except that the tip should be broken off to generate a relatively large inside diameter (about 130  $\mu\text{m}$ ) for the blastocyst to freely pass through, and that fire-polishing should be very brief to eliminate the sharp edges.

### 9.9.1.6 Injection of ES Cells into Blastocysts

1. Set up a suitable schedule so that ES cells may be trypsinized and gently suspend them to maintain them as a single cell suspension in embryo culture medium at 4°C before use, and the blastocysts may be prepared in the morning.
2. Take up a tiny volume of light liquid paraffin (optional) by positive pressure and then take up blastocysts or ES cells into an embryo transfer pipette by capillary suction. Under the microscope, introduce the blastocysts into drops of embryo culture medium in a chamber, a dish, or a depression slide.
3. Assemble all parts that are necessary for the injection according to the manufacturer's instructions.
4. Position the pipette tips so that they are parallel in the field using the coarse adjustments of the manipulator. The holding pipette and ES cell injection pipette should be placed in opposite directions (e.g., north and south). Focus and place them in the same plane utilizing the fine adjustments.
5. Carefully pull out the pipettes far enough to allow the introduction of a chamber, a dish, or a slide containing the blastocysts onto the stage.
6. Carefully reposition the pipettes and focus. Position and place the relatively dark side of the blastocysts in the center of the field, then carefully bring the ES cell pipette closer to the blastocyst.
7. Carefully insert the ES cell pipette and expel one to five ES cells into the blastocoelic cavity (relatively light part of the blastocyst). Slightly remove the ES cell pipette and place aside the injected blastocyst.
8. Repeat the procedure for other blastocysts.

### 9.9.1.7 Reimplantation of the Injected Blastocysts into the Uterus of Recipient Females

1. Prepare the third or fourth day pseudopregnant females as described above. It is recommended that these mice be prepared 1 day later than the mice prepared as the blastocyst donors.
2. Weigh and anesthetize a couple of females as described above.
3. Clean the back of a female with 70% ethanol and make an approximately 1 cm transverse incision in the skin in the area of the first lumbar vertebra. Clean the cut hairs with cotton wetted in alcohol.
4. Carefully slide the skin incision to both sides until the left ovarian fat pad and the ovary can be seen through the peritoneal wall.
5. Make a 4-mm incision through the peritoneum. Locate the ovary, oviduct, and uterus using blunt forceps. Grasp the fat pad and carefully pull it out together with the uterus through the opening.
6. Under a dissecting microscope, hold a pipette loaded with the embryos and a hypodermic needle in the right hand and carefully hold the uterus with forceps in the left hand. Insert the needle through the muscle layers of the uterus and position the needle parallel to the long axis of the uterus in order to allow the tip to enter the lumen.
7. Pull out the needle and insert the tip of the embryo transfer pipette through the hole made by the needle into the lumen of the uterus. Carefully expel all of the blastocysts into the lumen and remove the pipette. Bubbles should be avoided as much as possible.
8. Replace the uterus and perform the same procedure for the other side if bilateral transfer is necessary.
9. Seal the incision or close it with a small wound clip.
10. Recover the foster mothers by briefly warming them under an infrared lamp (do not overheat), and house two or three in one cage. Live offspring are usually born 18 days after the surgery. The initial offspring are called the founder animals or the GO animals in terms of genetics. The offspring can be allowed to breed to maintain the animals.

## 9.9.2 METHOD B. PRODUCTION OF TRANSGENIC MICE FROM OOCYTES

### 9.9.2.1 Preparation of Oocytes

1. Four days (94 to 96 h) before removing the eggs, induce superovulation of ten to fifteen 3- to 4-week-old female mice by injecting 5 units/female of pregnant mare's serum (PMS) as a stimulating hormone.
2. At 75 to 76 h after the injection of PMS, inject 5 units/female of HCG. This injection should be made 19 to 20 h before the eggs are harvested.
3. After the injection of HCG, cage the females with males overnight by maintaining them on a 12-h light/12-h dark cycle.
4. The next morning, check the females for vaginal plugs. The mated females should have vaginal plugs within 24 h after mating.

5. Kill the superovulated females that have visible vaginal plugs by cervical dislocation.
6. Clean the body surface with 70% ethanol, then dissect the oviducts and transfer them to disposable Petri dishes containing 30 ml of medium A. Carefully transfer the oocytes from the oviducts to the medium.  
Note: *Under a dissecting microscope, the fertilized eggs can be identified as containing two nuclei that are called pronuclei. The male pronucleus is bigger than that of the female.*
7. Aspirate medium A, then carefully transfer the oocytes to a fresh Petri dish and incubate the oocytes with hyaluronidase for an appropriate period to remove the cumulus cells.
8. Rinse the oocytes extensively with four changes of medium A and carefully transfer the oocytes to a fresh Petri dish containing 10 to 30 ml of medium B. Place the dish in a 37°C incubator with 5% CO<sub>2</sub>.

### Reagents needed

- *Medium A*

- 4.78 mM KCl
- 94.66 mM NaCl
- 1.19 mM KH<sub>2</sub>PO<sub>4</sub>
- 1.19 mM MgSO<sub>4</sub>
- 1.71 mM CaCl<sub>2</sub>
- 4.15 mM NaHCO<sub>3</sub>
- 23.38 mM sodium lactate
- 0.33 mM sodium pyruvate
- 5.56 mM glucose
- 20.85 mM HEPES, pH 7.4 (adjust with 0.2 N NaOH)
- BSA, 4 g/l
- Penicillin G (potassium salt), 100,000 units/l
- Streptomycin sulfate, 50 mg/l
- Phenol Red, 10 mg/l

Dissolve well after each addition. Filter sterilize and store at 4°C. Warm up the medium to 37°C prior before use.

- *Medium B*

- 4.78 mM KCl
- 94.66 mM NaCl
- 1.71 mM CaCl<sub>2</sub>
- 1.19 mM KH<sub>2</sub>PO<sub>4</sub>
- 25 mM NaHCO<sub>3</sub>
- 1.19 mM MgSO<sub>4</sub>
- 23.38 mM sodium lactate
- 0.33 mM sodium pyruvate
- 5.56 mM glucose
- BSA, 4 g/l
- Penicillin G (potassium salt), 100,000 units/l



Streptomycin sulfate, 50 mg/l

Phenol Red, 10 mg/l

Dissolve well after each addition. Filter-sterilize and store at 4°C. Warm up to 37°C prior to use.

### 9.9.2.2 Microinjection of DNA Constructs into Oocytes

The equipment used for microinjection includes the following: (1) an injection microscope on a vibration-free table (Diaphot TMD microscope with Nomarski optics is available from Nikon Ltd.); (2) an inverted microscope for setting up the injecting chamber, holding pipette, and needle (A SMZ-2B binocular microscope available from Leitz Instruments Co.); (3) two sets of micromanipulators (Leitz Instruments Ltd.); (4) Kopf needle puller model 750 (David Kopf Instruments); (5) a finer needle and a pipette holder; and (6) a Schott-KL-1500 cold light source (Schott).

1. Thoroughly clean a depression slide with Teepol-based detergent and extensively rinse it with tap water and distilled water. Rinse it with ethanol and air dry. Add a drop of culture medium to the depression slide and a drop of liquid paraffin on the top of the medium drop.
2. Assemble all parts that are necessary for the injection according to the manufacturer's instructions. Carry out a pretest of the procedure before injection of the DNA sample.
3. Carefully transfer the eggs into the medium drop using a handling pipette that can take up the cells by suction under the microscope.
4. Prepare microinjection needles with Kopf needle puller model 750. Slowly take up the DNA sample into the injection needle by capillary action.
5. Under the microscope, hold the suspended eggs with the holding pipette and use the micromanipulator to individually insert the needle into the male pronucleus, which is larger than the female pronucleus. Slowly inject the DNA sample into the pronucleus. The pressure can be maintained on the DNA sample in the needle by a syringe connected to the needle holder. After swelling of the pronucleus occurs, immediately remove the needle a short distance from the cell. The volume injected is approximately 1 to 2 pl.
6. Transfer the injected eggs to one side and repeat injections for others. About 40 to 60 eggs can be injected in 1 to 2 h, depending on the individual's experience.
7. Transfer the injected eggs into a fresh dish containing medium B and place it in the incubator.

### 9.9.2.3 Reimplantation of Injected Eggs into Recipient Female Mice and Generation of Founder Mice

The injected eggs can be reimplanted into recipient female mice right after injection (one-cell stage embryo) or after being incubated in the incubator overnight (two-cell stage embryo). It is recommended that the injected eggs be transferred at the

one-cell stage so that the introduced DNA integrates into chromosomes at the same site. Thus, all of the cells in transgenic animals contain the injected DNA. In general, the introduced DNA integrates randomly at a single site. In some cases, however, multiple copies of DNA insertion may occur.

1. Prepare pseudopregnant females by caging four to eight females (6 to 9 weeks old) with vasectomized males (two females per male) on the day they are needed. Thus, the females will be in the correct hormonal stage to allow the introduced embryos to be implanted but none of their own eggs can form embryos. The pseudopregnant females can be distinguished by inspecting the vaginal area for swelling and moistness (see Method A).
2. Carefully make a small incision in the body wall of a half-day pseudopregnant female (e.g., C57B1/CBA F1), and gently pull out the ovary and oviduct from the incision. Hold the oviduct in place with a clip placed on the fat-pad attached to the ovary.
3. Under a binocular dissecting microscope, place the injected eggs or embryos into the infundibulum using a sterile glass transfer pipette. Generally, 10 to 15 injected eggs can be transferred into an oviduct.
4. Carefully place the oviduct and ovary back in place and seal the incision.
5. Recover the foster mothers by briefly warming them under an infrared lamp (do not overheat), and keep two or three in one cage. Live offspring are usually born 18 days after the surgery. These initial offspring are named as the founder animals or GO animals in terms of genetics.
6. Allow the offspring to breed in order to maintain the transgenic mice.

## 9.10 CHARACTERIZATION OF TRANSGENIC MICE

Detailed protocols for isolation of DNA, RNA, extraction of proteins and Southern blot, northern blot, and western blot hybridizations are described in Chapters 10, 11, and 15, respectively. Data analyses are very similar to cellular characterization protocols described above in this chapter.

### Troubleshooting Guide

1. *Low efficiency of transfection of cells by liposomes, electroporation, and calcium phosphate methods.* If cells are normal and the cell density is appropriate, it is likely that the amounts of DNA constructs used and parameters applied in transfection are not optimal. Make sure to optimize the conditions for transfection of the cells, including DNA concentration, lipids ratio, or voltage pulse. In the case of stable transfection, ensure that the concentration of drug used in selection is not too high. A killing curve should be established.
2. *Low titer of retroviruses.* The virus stock is overdiluted or there is a low density of retrovirus particles due to low efficiency of stable transfection of packaging cells with modified virus DNA constructs. Try to use a good

packaging cell line and optimize the parameters used for transfection. Reinfection may be performed to amplify the virus titer.

3. *Low efficiency of transfection with frozen high titer viruses.* Assuming transfection conditions are optimal, it is very likely that the viruses have lost significant activity. It is recommended that high titer viruses be used in a couple of hours. Frozen aliquots should not be frozen and thawed.
4. *No antisense RNA is expressed in transfected cells.* This could be due to the orientation of the introduced cDNA. Make sure that the poly(A) strand of the cDNA is inserted downstream from the driving promoter in 3' to 5' orientation in order to make the antisense RNA or poly(T) strand. Try to check the mRNA level in the cells. If the level is equivalent to that of the control cells, the wrong orientation of the introduced cDNA is the case.
5. *Low reduction of the protein of interest.* This is obviously low efficiency of antisense inhibition. Try to run a northern blot analysis to check for antisense RNA expression using labeled sense RNA as a probe. Very little antisense RNA or not much reduction in mRNA level compared with non-transfected cells is exactly the cause of a low percentage reduction of the protein. In addition, it may be related to the activity of the promoter driving the expression of the introduced cDNA. If it is a constitutive promoter, its activity is low. Try to use a stronger promoter. If the driving promoter is inducible, try to optimize the concentration of the inducer.
6. *Some of the drug-selected stably transfected cell clones show 100% death during subsequent expanding or culture in a selection medium.* If these clones are not frozen, it is certain that these isolated clones are false stably transfected cells. It is likely that during trypsinization and resuspension, the cells are not well suspended; instead, they aggregated. After transfection, some of the cells within the aggregated colonies received a smaller amount of drug and still underwent proliferation, forming false colonies that were picked up. During the trypsinizing and picking-up, these cells were loosened by physical force. Because they were not particularly stable colonies, they were killed in drug selection medium during subsequent expanding or culture.

## REFERENCES

1. Wu, W., and M. J. Welsh. 1996. Expression of HSP27 correlates with resistance to metal toxicity in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Applied Toxicology and Pharmacology* 141: 330–339.
2. Robert, L. S., P. A. Donaldson, C. Ladaigue, I. Altosaar, P. G. Arnison, and S. F. Fabijanski. 1990. Antisense RNA inhibition of  $\beta$ -glucuronidase gene expression in transgenic tobacco can be transiently overcome using a heat-inducible  $\beta$ -glucuronidase gene construct. *Biotechnology* 8: 459.
3. Rezaian, M. A., K. G. M. Skene, and J. G. Ellis. 1988. Anti-sense RNAs of cucumber mosaic virus in transgenic plants assessed for control of the virus. *Plant Molecular Biology* 11: 463.

4. Hemenway, C., R.-X. Fang, W. K. Kaniewski, N.-H. Chua, and N. E. Tumer. 1988. Analysis of the mechanism of protection in transgenic plants expressing the potato virus X coat protein or its antisense RNA. *EMBO Journal* 7: 1273.
5. Dag, A. G., E. R. Bejarano, K. W. Buck, M. Burrell, and C. P. Lichtenstein. 1991. Expression of an antisense viral gene in transgenic tobacco confers resistance to the DNA virus tomato golden mosaic virus. *Proceedings of the National Academy Sciences of the United States of America* 88: 6721.
6. Iwaki, T., A. Iwaki, J. Tateishi, and J. E. Goldman. 1994. Sense and antisense modification of glial  $\alpha\beta$ -crystallin production results in alterations of stress fiber formation and thermoresistance. *Journal of Cell Biology* 15: 1385.
7. Yang, N. S., J. Burkholder, B. Roberts, B. Martinell, and D. McCabe. 1990. *In vitro* and *in vivo* gene transfer to mammalian somatic cells by particle bombardment. *Proceedings of the National Academy of Sciences of the United States of America* 87: 9568.
8. Wu, W. 1995. Gene transfer and expression in animals. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke. Boca Raton, Florida: CRC Press.
9. Zelenin, A. V., A. V. Titomirov, and V. A. Kolesnikov. 1989. Genetic transformation of mouse cultured cells with the help of high-velocity mechanical DNA injection. *FEBS Letters* 244: 65.
10. Hasty, P., and A. Bradley. 1993. Gene targeting vectors for mammalian cells. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: Oxford University Press.

---

# 10 Analysis of Gene Expression at Functional Genomic Level Using Northern Blotting or PCR

## 10.1 INTRODUCTION

Northern blot hybridization is a procedure in which different sizes of RNA molecules are separated in an agarose gel, immobilized onto a solid support of either nylon or nitrocellulose membranes, and then subjected to hybridization with a labeled DNA or RNA probe. Unlike the Southern blotting technique that involves DNA–DNA hybridization, northern blot hybridization refers to RNA–DNA or RNA–RNA hybridization. Technically, northern is not a person’s name; nor is it due to a geographic location. As a matter of fact, this technique was developed later than the Southern blot method, and so named the northern blot method.


Although current reverse transcription-polymerase chain reaction (RT-PCR) (see Chapter 19) provides a relatively rapid analysis of the dynamic changes in the mRNA level of the gene of interest, the northern blot technique is the most fundamental and powerful tool used in analysis of full-length mRNA expression level.<sup>1</sup> It is a reliable and quantitative method widely used in the characterization of the steady-state level of RNA transcripts. RNA analysis is a powerful approach to monitoring the activity of an endogenous or introduced gene in specific cell lines or tissues. In spite of the fact that other methods such as RNase protection and dot/slot blot hybridization can be used for RNA analysis and are relatively more sensitive, the northern blot method has several advantages. As has been demonstrated,<sup>2–4</sup> expression patterns of genes are often complex. Multiple RNA molecules can be expressed from a single gene and thousands of RNA species are generated from a single cell, tissue, or organism. Northern blot analysis can simultaneously provide information on the species, sizes, and expression levels of diversity of RNAs that cannot be displayed by alternative techniques such as the dot/slot blot and RNA protection assays. Also, membrane filters containing a record of different RNA species can be reused for analysis of multiple RNAs transcripts from several genes in the same RNA sample. Therefore, the value and applications of northern blot technology are immeasurable.

This chapter provides detailed protocols for standard northern blot hybridization and for semiquantitative PCR and dot blot analysis of mRNA.<sup>1,2,4-9</sup> For real-time RT-PCR, please see Chapter 19.

## 10.2 PRINCIPLES AND GENERAL CONSIDERATIONS

The general principles and procedures of northern blot hybridization are illustrated in Figure 10.1. Different RNAs are first denatured by formaldehyde and then subjected to separation according to their molecular weights by standard agarose gel electrophoresis. An agarose gel serves as a molecular sieve and electron transport in an electrical field is the driving force for migration of negatively charged RNAs during electrophoresis. The separated RNAs are then blotted or transferred onto a nylon or a nitrocellulose membrane. Generally, different positions of RNAs in the agarose gel are identically recorded on the membrane. After covalent cross-linking of RNA molecules on the membrane, specific or target sequences of RNA(s) can be hybridized with a DNA or RNA probe of interest followed by detection using an appropriate method.

One important concept to know is that the principle of mRNA transcribed from its gene or DNA is the base pairing rule. This means that the sequence of an mRNA is complementary to that of the DNA template from which it was copied, except that base T is replaced by U. It is exactly the base pairing or complementary rule that makes it possible for a single-stranded DNA or RNA probe to hybridize with its target sequences of denatured mRNA by means of hydrogen bonds. With regard to probes, an RNA probe or riboprobe transcribed *in vitro* has been demonstrated



**FIGURE 10.1** Scheme of mRNA analysis by northern blot hybridization.

to be more sensitive or hotter than a DNA probe.<sup>1</sup> In addition, RNA–RNA hybrids are more stable compared with RNA–DNA hybrids. Therefore, hybridization and washing can be carried out under relatively high stringency conditions, thus reducing potential developments of a nonspecific background.

Because RNAs, as compared to DNA, are very mobile molecules due to potential degradation by RNases, much care should be taken to maintain the purity and integrity of the RNA. This is certainly critical for northern blot hybridization. RNase activity is not readily inactivated. Two major sources of RNase contamination are from the user's hands and from bacterial and fungal molds present on airborne dust particles. To avoid RNase contamination, gloves should be worn and changed frequently when handling RNAs. Disposable plasticware should be autoclaved. Nondisposable glass- and plasticware should be treated with 0.1% diethyl pyrocarbonate (DEPC) in dd.H<sub>2</sub>O and be autoclaved before use. DEPC is a strong RNase inhibitor. Glassware may be baked at 250°C overnight. Gel apparatus should be soaked with 0.2% sodium dodecyl sulfate (SDS) overnight and thoroughly cleaned with detergent followed by thorough rinsing with DEPC-treated water. Apparatus for RNA electrophoresis, if possible, should be separated from that used for DNA or protein electrophoresis. Chemicals to be used should be of ultrapure grade and RNase-free. Gel mixtures, running buffers, hybridization solutions, and washing solutions should be made with DEPC-treated water or treated with a few drops of DEPC.

Similar to Southern blot hybridization, a standard northern blot consists of five procedures: (1) preparation of RNAs to be analyzed, (2) agarose gel electrophoresis of RNA molecules, (3) blotting of RNAs onto a solid membrane, (4) hybridization of the RNA with a labeled DNA or RNA probe, and (5) detection of the hybridized signal(s). Agarose gel electrophoresis is a common tool for separation of different RNAs. Agarose comes from seaweed algae and is a linear polymer that is basically composed of D-galactose and L-galactose. Once agarose powder is melted and then hardened, it forms a matrix that serves as a molecular sieve by which different sizes of RNAs are separated during electrophoresis.

A number of general factors should be considered when one performs agarose gel electrophoresis of RNA. An ultrapure grade agarose that is RNase-free is highly recommended for northern blotting. The concentration of agarose will influence separation of RNAs. A general chart is shown below. Normally, the larger the size of the RNA, the lower the percentage of agarose that should be used to obtain sharp bands.

Agarose % (w/v)	RNA Size (kb)
0.6%	1.0–20
0.8%	1.0–10
1%	0.6–7.0
1.2%	0.5–5.0
1.4%	0.2–2.0

During electrophoresis, RNAs move through the gel matrix at a rate inversely proportional to the log of their molecular weight. Small RNA species move faster than large RNA molecules.

### 10.3 ISOLATION OF TOTAL RNAs AND/ OR PURIFICATION OF mRNAs

Detailed protocols are described in Chapter 3.

### 10.4 ELECTROPHORESIS OF RNAs USING FORMALDEHYDE AGAROSE GELS

1. Thoroughly clean an appropriate gel apparatus and combs by soaking them in 0.2% SDS solution overnight and washing them with a detergent. Completely wash out the detergent with tap water and rinse with distilled water three to five times.
2. Prepare a formaldehyde agarose gel mixture in a clean bottle or a beaker as follows:

Component	Mini Gel	Medium Gel	Large Gel
dd.H <sub>2</sub> O	21.6 ml	54 ml	86.4 ml
Ultrapure agarose	0.3 g	0.75 g	1.2 g

Note: *The percentage of agarose is normally 1% (w/v), but it can be adjusted with the sizes of RNAs to be separated. The dd.H<sub>2</sub>O should be DEPC-treated. Because the agarose is small in amount, its volume can be ignored in calculating the total volume.*

3. Place the bottle with the cap loose or beaker in a microwave oven and slightly heat the agarose mixture for 1 min. Briefly shake the bottle to rinse any agarose powder stuck to the glass sides. To completely melt the agarose, carry out gentle boiling for 1 to 3 min, depending on the volume of agarose mixture. Gently mix, open the cap, and allow the mixture to cool to 50 to 60°C at room temperature.
4. While the gel mixture is cooling, seal a clean gel tray at the two open ends with tape or a gasket and insert the comb in place.
5. Add the following components to the cooled gel mixture:

Components	Mini Gel	Medium Gel	Large Gel
10× MOPS buffer	3 ml	7.5 ml	12 ml
Ultrapure formaldehyde (18%, v/v) (37%, 12.3 M)	5.4 ml	13.5 ml	21.6 ml
Ethidium bromide (EtBr, 10 mg/ml)	3 µl	7.5 µl	12 µl

6. Gently mix after each addition and pour the mixture into the assembled gel tray placed in a fume hood. Allow the gel to harden for 30 min at room temperature.

Caution: *Formaldehyde is toxic. Both DEPC and EtBr are carcinogenic. These reagents should be handled with care. Gloves should be worn when working with these chemicals. Gel running buffer containing EtBr should*



*be collected in a special container designated for toxic waste disposal. Formaldehyde serves to denature any secondary structures of RNAs. EtBr is used to stain RNA molecules by intercalating in the regions of secondary structure of RNAs and fluoresces orange when illuminated with UV light. An alternative way is to stain the gel after electrophoresis is completed. The gel can be stained with EtBr solution for 10 to 30 min followed by washing in distilled water for 3 to 5 min. In addition, an appropriate volume of EtBr stock solution can be directly added to RNA sample (1  $\mu$ l of 1 mg/ml per 10  $\mu$ l RNA) before loading.*

7. While the gel is hardening, prepare the RNA sample(s) in a sterile tube as follows:

Total RNA (10–35 $\mu$ g/lane)	
or poly(A) + RNA (0.2–2 $\mu$ g/lane)	6 $\mu$ l
10 $\times$ MOPS buffer	3.5 $\mu$ l
Ultrapure formaldehyde (37%, 12.3 M)	6.2 $\mu$ l
Ultrapure formamide (50% v/v)	17.5 $\mu$ l
Add DEPC-treated dd.H <sub>2</sub> O to	35 $\mu$ l

8. Heat the tubes at 55°C for 15 min and immediately chill on ice to denature the RNAs. Briefly spin down afterward.
9. Add 3.5  $\mu$ l of 5 $\times$  DEPC-treated loading buffer to the RNA sample. Proceed to sample loading.
10. Slowly and vertically pull the comb out of the gel and remove the sealing tape or gasket from the gel tray. Place the gel tray in an electrophoresis apparatus and add a sufficient volume of 1 $\times$  MOPS buffer to the apparatus until the gel is covered to a depth of 1.5 to 2 mm above the gel.  
*The comb should be slowly and vertically pulled out from the gel because any cracks occurring inside the wells of the gel will cause sample leaking when the sample is loaded. The top side of the gel where wells are located must be placed at the negative pole in the apparatus because the negatively charged RNA molecules will migrate toward the positive pole. Should any of the wells contain visible bubbles, they should be flushed out of the wells using a small pipette tip to flush the buffer up and down the well several times. Bubbles may adversely influence the loading of the samples and the electrophoresis. The concentration of TBE buffer should never be lower than 0.4 $\times$ . Otherwise, the gel may melt during electrophoresis. Prerunning the gel at a constant voltage for 10 min is optional.*
11. Carefully load the samples, one by one, into appropriate wells in the submerged gel.

Notes: (1) *One should not insert a pipette tip all the way down to the bottom of a well, because this will likely break the well and cause sample leaking and contamination. The tip containing RNA sample should be vertically positioned at the surface of the well, stabilized by a finger of the other hand*

and slowly loaded into the well. (2) The loading buffer should be at least  $1\times$  to final concentration; otherwise, the sample may float out of the well.

12. After all samples are loaded, estimate the length of the gel between the two electrodes and set up the power supply at 5 to 15 V/cm of gel. Allow electrophoresis to proceed for 2 h or until the first blue dye reaches a distance of 1 cm from the end of the gel. If overnight running of the gel is desired, the total voltage should be determined empirically.
13. Stop electrophoresis and visualize the RNA bands in the gel under UV light. Photograph the gel with a Polaroid camera.

Caution: *Wear safety glasses and gloves for protection against UV light.*

Notes: *The purpose of taking a picture is to record different RNA molecules at different positions after electrophoresis, which is useful once a hybridized signal is detected later. It is recommended that pictures be taken with a fluorescence ruler placed beside the gel. An appropriate exposure is needed to obtain two relatively sharp rRNA bands and a black background. For successful RNA separation on a gel, smear mRNAs and sharp rRNA bands should be visible in each lane. The two sharp rRNA bands are 28S and 18S for animal RNAs or 25S and 18S for plant RNAs.*

### Materials needed

- A microcentrifuge
- Sterile microcentrifuge tubes (0.5 or 1.5 ml)
- Pipette or pipetmans (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
- Sterile pipette tips (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
- Gel casting tray
- Gel combs
- Electrophoresis apparatus
- DC power supply
- Small or medium size of RNA electrophoresis apparatus depending on samples
- Ultrapure agarose powder
- Total RNA samples
- Specific DNA or RNA as a probe
- Nylon membranes
- 3MM Whatman filters
- Paper towels for blotting
- UV transilluminator
- Hybridization oven or shaker
- Water bath with temperature control
- Diethylpyrocarbonate (DEPC)
- Formaldehyde (37%)
- Formamide
- *DEPC water*

0.1% (v/v) DEPC in dd.H<sub>2</sub>O, placed at room temperature overnight with a stir bar to inactivate any potential RNases. Autoclave to remove the DEPC.

- *10× MOPS buffer*  
0.2 M 3-(*N*-morpholino)propanesulfonic acid (MOPS)  
80 mM sodium acetate  
10 mM EDTA (pH 8.0)  
Dissolve well after each addition in DEPC-treated dd.H<sub>2</sub>O.  
Adjust the pH to 7.0 with 2 N NaOH.  
Filter-sterilize and store at room temperature.
- *Ethidium bromide (EtBr)*  
10 mg/ml in DEPC-treated dd.H<sub>2</sub>O, dissolve well and keep in a dark or brown bottle at 4°C.  
Caution: *EtBr is extremely toxic and should be handled carefully.*
- *5× Loading buffer*  
50% glycerol  
2 mM EDTA  
0.25% bromphenol blue  
0.25% xylene cyanol  
Dissolve well in DEPC-treated water, filter-sterilize, and store at 4°C.


## 10.5 BLOTTING OF RNAs ONTO NYLON MEMBRANES BY THE CAPILLARY METHOD

The general procedures are outlined in Figures 10.2 and 10.3. Protocols are the same as for DNA transfer, which are described in detail in Chapter 7.


## 10.6 PREPARATION OF ISOTOPIC OR NONISOTOPIC DNA/RNA PROBES

### 10.6.1 PROTOCOL A. PREPARATION OF DNA PROBES

Detailed protocols are described in Chapter 7.



**FIGURE 10.2** Standard assembly for upward capillary transfer of RNAs from an agarose gel onto a nylon membrane filter.



**FIGURE 10.3** Standard assembly of downward capillary transfer of RNAs from an agarose gel onto a nylon membrane filter.

### 10.6.2 PROTOCOL B. PREPARATION OF RNA PROBES BY TRANSCRIPTION *IN VITRO*

A number of plasmid vectors have been developed for subcloning of cDNA. These vectors have polycloning sites downstream from powerful bacteriophage promoters, SP6, T7, or T3 in the vector. The cDNA of interest can be cloned at the polycloning site between promoters SP6 and T7 or T3, forming a recombinant plasmid. The cDNA inserted can be transcribed *in vitro* into single-strand sense RNA or antisense RNA from a linear plasmid DNA with promoters SP6, T7, or T3. During the process of *in vitro* transcription, one of the rNTPs is radioactively labeled and can be incorporated into the RNAs. These are the labeled RNAs. The labeled RNA probes usually have a high specific activity, and are much “hotter” than single-strand DNA (ssDNA) probes. As compared with DNA labeling, the yield of the RNA probe is usually very high because the template can be repeatedly transcribed. RNA probes can be easily purified from a DNA template merely by the use of RNase-free DNase I treatment. The greatest advantage of an RNA probe over a DNA probe is that the RNA probe can produce much stronger signals in a variety of different hybridization reactions.

1. Preparation of linear DNA template for transcription *in vitro*. The plasmid is linearized by an appropriate restriction enzyme in order to produce “run-off” transcripts. To make RNA transcripts from the DNA insert, recombinant plasmid DNA should be digested by an appropriate restriction enzyme that cuts at one site that is very close to one end of the insert.

(a) On ice, set up a plasmid linearization reaction:

Recombinant plasmid DNA ( $\mu\text{g}/\mu\text{l}$ )	5 $\mu\text{g}$
Appropriate restriction enzyme 10 $\times$ buffer	2.5 $\mu\text{l}$
Appropriate restriction enzyme	3 u/ $\mu\text{g}$ DNA
Add dd.H <sub>2</sub> O to a final volume of	25 $\mu\text{l}$

(b) Incubate at the appropriate temperature for 2 to 3 h.

- (c) Extract DNA with 1 volume of TE-saturated phenol/chloroform and mix well by vortexing. Centrifuge at 11,000 *g* for 5 min at room temperature.
  - (d) Carefully transfer the top, aqueous phase to a fresh tube and add 1 volume of chloroform/isoamyl alcohol (24:1). Mix well and centrifuge as in step (c).
  - (e) Transfer the top, aqueous phase to a fresh tube. Add 0.1 volume of 2 M NaCl solution and 2 volumes of chilled 100% ethanol to the supernatant. Precipitate the DNA at  $-20^{\circ}\text{C}$  for 30 min.
  - (f) Centrifuge at 12,000 *g* for 5 min, aspirate the supernatant, and briefly rinse the pellet with 1 ml of 70% ethanol. Dry the DNA pellet for 10 min under vacuum and dissolve the linearized plasmid in 15  $\mu\text{l}$  dd.H<sub>2</sub>O.
  - (g) Take 2  $\mu\text{l}$  of the sample to measure the concentration of the DNA at  $A_{260}$  nm and  $A_{280}$  nm. Store the sample at  $-20^{\circ}\text{C}$  until use.
2. Blunt the 3' overhang ends using the 3'  $\rightarrow$  5' exonuclease activity of Klenow DNA polymerase.

Note: *Although this is optional, we recommend that the 3' protruding ends be converted into blunt ends because some of the RNA sequence is complementary to vector DNA. Therefore, enzymes such as KpnI, SacI, PstI, bglI, SacII, PvuI, Sfi, and SphI should not be used to linearize plasmid DNA for transcription in vitro.*

3. Carry out synthesis of RNA via *in vitro* transcription.
- (a) Set up a reaction as follows:

5 $\times$ transcription buffer	8 $\mu\text{l}$
0.1 M DTT	4 $\mu\text{l}$
rRNasin ribonuclease inhibitor	40 units
<u>Linearized template DNA (0.2–1.0 <math>\mu\text{g}/\mu\text{l}</math>)</u>	<u>2 <math>\mu\text{l}</math></u>
Add dd.H <sub>2</sub> O to a final volume of	15.2 $\mu\text{l}$

- (b) Add Klenow DNA polymerase (5 u/ $\mu\text{g}$  DNA) to the reaction and incubate at  $22^{\circ}\text{C}$  for 15 to 20 min.
- (c) To the reaction, add the following components:

Mixture of ATP, GTP, CTP, or UTP (2.5 mM each)	8 $\mu\text{l}$
120 mM UTP or CTP	4.8 $\mu\text{l}$
$[\alpha\text{-}^{32}\text{P}]\text{UTP}$ or $[\alpha\text{-}^{32}\text{P}]\text{CTP}$ (50 $\mu\text{Ci}$ at 10 mCi/ml)	10 $\mu\text{l}$
SP6 or T7 or T3 RNA polymerase (15–20 u/ $\mu\text{l}$ )	2 $\mu\text{l}$

- (d) Incubate the reaction at 37 to  $40^{\circ}\text{C}$  for 1 h.
- (e) Remove DNA template using DNase I, using 1 u/ $\mu\text{g}$  DNA template. Incubate for 15 min at  $37^{\circ}\text{C}$ .
- (f) Extract RNA with 1 volume of TE-saturated phenol/chloroform. Mix well by vortexing for 1 min and centrifuging at 11,000 *g* for 5 min at room temperature.

- (g) Carefully transfer the top, aqueous phase to a fresh tube and add 1 volume of chloroform/isoamyl alcohol (24:1). Mix well by vortexing and centrifuge at 11,000 g for 5 min.
- (h) Carefully transfer the upper, aqueous phase to a fresh tube, add 0.5 volume of 7.5 ammonium acetate solution and 2.5 volumes of chilled 100% ethanol. Precipitate RNA at  $-80^{\circ}\text{C}$  for 30 min.
- (i) Centrifuge at 12,000 g for 10 min. Carefully discard the supernatant and briefly rinse the RNA with 1 ml of 70% ethanol and dry the pellet under vacuum for 15 min.
- (j) Dissolve the RNA probe in 20 to 50  $\mu\text{l}$  of TE buffer and store at  $-20^{\circ}\text{C}$  until use.
4. Calculate the percentage of incorporation and the specific activity of the RNA probe.
- (a) Estimate the cpm used in the transcription reaction. For instance, if 50  $\mu\text{Ci}$  of NTP is used, the cpm is  $50 \times 2.2 \times 10^6 \text{ cpm}/\mu\text{Ci} = 110 \times 10^6 \text{ cpm}$  in 40  $\mu\text{l}$  reaction, or  $2.8 \times 10^6 \text{ cpm}/\mu\text{l}$ .
- (b) Perform a trichloroacetic acid (TCA) precipitation assay using 1:10 dilution in dd.H<sub>2</sub>O as described previously.
- (c) Calculate the percentage of incorporation.

$$\% \text{ incorporation} = \text{TCA precipitated cpm} / \text{total cpm} \times 100$$

- (d) Calculate the specific activity of the probe. For example, if 1  $\mu\text{l}$  of a 1:10 dilution is used for TCA precipitation,  $10 \times \text{cpm}$  precipitated =  $\text{cpm}/\mu\text{l}$  incorporated. In 40  $\mu\text{l}$  of reaction,  $40 \times \text{cpm}/\mu\text{l}$  is the total cpm incorporated. If 50  $\mu\text{Ci}$  of labeled UTP at 400  $\mu\text{Ci}/\text{nmol}$  is used, then  $50/400 = 0.125 \text{ nmol}$  of UTP is added to the reaction mixture. If there is 100% incorporation and UTP represents 25% of the nucleotides in the RNA probe,  $4 \times 0.125 = 0.5 \text{ nmol}$  of nucleotides is incorporated, and  $0.5 \times 330 \text{ ng}/\text{nmol} = 165 \text{ ng}$  of RNA are synthesized. Then, the total ng RNA probe =  $\% \text{ incorporation} \times 165 \text{ ng}$ . For example, if 1:10 dilution of the labeled RNA sample has  $2.2 \times 10^5 \text{ cpm}$ , the total cpm incorporated is  $10 \times 2.2 \times 10^5 \text{ cpm} \times 40 \mu\text{l}$  (total reaction) =  $88 \times 10^6 \text{ cpm}$ .

$$\% \text{ incorporation} = 88 \times 10^6 \text{ cpm} / 110 \times 10^6 \text{ cpm} (50 \mu\text{Ci}) = 80\%$$

$$\text{Total RNA synthesized} = 165 \text{ ng} \times 0.80 = 1.32 \text{ ng RNA}$$

$$\begin{aligned} \text{Specific activity of the probe} &= 88 \times 10^6 \text{ cpm} / 0.132 \mu\text{g} \\ &= 6.7 \times 10^8 \text{ cpm}/\mu\text{g RNA} \end{aligned}$$

*Note: An alternative way is to synthesize RNA without using an isotope. The synthesized RNA can be labeled using nonradioactive approaches as described in Chapter 7.*

### Reagents needed

- RNase-free DNase I
- 2 M NaCl solution
- 7.5 M ammonium acetate solution
- Ethanol (100%, 70%)
- TE-saturated phenol/chloroform
- Chloroform/isoamyl alcohol
- 24:1 (v/v)
- TE buffer
- *5× Transcription buffer*
  - 200 mM Tris-HCl, pH 7.5
  - 30 mM MgCl<sub>2</sub>
  - 10 mM spermidine
  - 50 mM NaCl
- *NTPs stock solutions*
  - 10 mM ATP in dd.H<sub>2</sub>O, pH 7.0
  - 10 mM GTP in dd.H<sub>2</sub>O, pH 7.0
  - 10 mM UTP in dd.H<sub>2</sub>O, pH 7.0
  - 10 mM CTP in dd.H<sub>2</sub>O, pH 7.0
- *Radioactive NTP solution*
  - [ $\alpha$ -<sup>32</sup>P]UTP or [ $\alpha$ -<sup>32</sup>P]CTP
  - (400 Ci/nmol)

## 10.7 HYBRIDIZATION AND DETECTION OF SIGNALS

The general procedures are the same as for DNA hybridization and detection, which are described in detail in Chapter 7.

## 10.8 ANALYSIS OF mRNA EXPRESSION BY A SEMIQUANTITATIVE PCR APPROACH

The disadvantage of northern blot hybridization or of *in situ* hybridization of mRNA is the difficulty in obtaining a desired result(s) when analyzing nonconstitutively expressed, cell- or tissue-specific genes with low abundance mRNAs or when limiting amounts of mRNA are available due to their degradation. These drawbacks, however, can be overcome by the use of quantitative PCR. The same amount of total RNAs or mRNAs from different samples is reverse transcribed into cDNAs under the same conditions. A particular cDNA of interest in total cDNAs in each of the samples is then amplified by PCR using specific primers. An equal amount of the amplified cDNA from each sample is then analyzed by dot blotting or Southern blotting using the target sequence between primers as a probe. In this case, different amounts of mRNA expressed by a specific gene under different conditions will generate different amounts of cDNA. By comparing the hybridized signals of different samples, the different levels of gene expression can be detected with ease.

Meanwhile, a control mRNA (usually an appropriate housekeeping gene transcript) such as actin mRNA is reverse transcribed and amplified by PCR, using specific primers, under the exact same conditions in order to monitor equivalent reverse transcription and an equivalent amplification by PCR.

1. Synthesize the first strand cDNAs from the isolated total RNAs or mRNAs using reverse transcriptase and oligo(dT) as a primer. This is described in detail in Chapter 3.
2. Design primers for amplification of specific cDNA PCR.
  - (a) Design oligonucleic acid primers based on conserved amino acid sequences in two different regions of a specific cDNA. For instance, two oligonucleotide primers can be designed as follows for the two amino acid sequence regions of invertase, NDPNG and DPCEW.

Forward primer 5'-AAC(T)GAT(C)CCIAA(C)TGGI-3' derived from  
NDPNG  
Reverse primer 3'-GGTGAGCGTCCCTAG-5' derived from  
DPCEW

Note: *I* stands for the third position of the codon, which can be any of TCAG. The primers can generate a product of 554 bp.

For amplification of actin cDNA, the primers can be designed as follows:

Forward primer 5'-ATGGATGACGATATCGCTG-3'  
Reverse primer 5'-ATGAGGTAGTCTGTCAGGT-3'

Note: *These primers can generate a product of 568 bp.*

3. Carry out PCR amplification.
  - (a) In a 0.5-ml microcentrifuge tube on ice, add the following items in the order listed for one sample amplification:

10× amplification buffer	10 μl
Mixture of four dNTPs (1.25 mM each)	17 μl
Forward primer (100–110 pmol) in dd.H <sub>2</sub> O	4 μl
Reverse primer (100–110 pmol) in dd.H <sub>2</sub> O	4 μl
<u>cDNA synthesized</u>	<u>6 μl (0.1–1 μg)</u>
Add dd.H <sub>2</sub> O to final volume	100 μl

For no cDNA control:

10× amplification buffer	10 μl
Mixture of four dNTPs (1.25 mM each)	17 μl
Forward primer (100–110 pmol) in dd.H <sub>2</sub> O	4 μl
<u>Reverse primer (100–110 pmol) in dd.H<sub>2</sub>O</u>	<u>4 μl</u>
Add dd.H <sub>2</sub> O to final volume	100 μl

- (b) Add 2.5 units of high fidelity of *Taq* DNA polymerase (5 units/μl) to each of the samples and mix well.



- (c) Overlay the mixture with 30  $\mu$ l of light mineral oil (Sigma or equivalent) to prevent evaporation of the sample.
- (d) Carry out PCR amplification for 35 to 40 cycles in a PCR cycler, which is programmed as follows:

Cycle	Denaturation	Annealing	Polymerization
First	3 min at 94°C	2 min at 55°C	3 min at 70°C
Subsequent	1 min at 94°C	2 min at 55°C	4 min at 70°C
Last	1 min at 94°C	2 min at 55°C	10 min at 70°C

Note: *The condition for amplification should be exactly the same for every sample—actin cDNA as well as no cDNA.*

- (e) Starting after 10 cycles, carefully insert a pipette tip through the oil and remove 15  $\mu$ l of reaction mixture from each of the samples and from controls every 5 cycles at the end of appropriate cycle (at 70°C extension phase). Place tubes at 4°C until use.


Note: *Sampling should be done in 2 min for all samples. There should be six samplings for each of the samples in 40 cycles. Oil should be avoided as much as possible.*

4. Use the 15  $\mu$ l cDNA from each of the samples and the controls to carry out dot blot hybridization using the appropriate <sup>32</sup>P-labeled internal oligonucleotides or the target sequence (e.g., cDNA fragment) between the two primers used as a probe.
  - (a) Denature DNA at 95°C for 10 to 15 min and immediately chill on ice. Spin down and add 1 volume of 20 $\times$  SSC to the sample. An alternative way is the alkaline denaturing method: add 0.2 volume of 2 M NaOH solution to the sample, incubate at room temperature for 15 min and add 1 volume of neutralization buffer containing 0.5 M Tris-HCl (pH 7.5) and 1.5 M NaCl. Incubate at room temperature for 15 min.
  - (b) Cut a piece of nylon or nitrocellulose membrane filter and place the filter on top of a vacuum blot apparatus. Turn on the vacuum slightly to obtain an appropriate suction that holds the membrane filter onto the apparatus.  
 Tips: *If the vacuum is too weak, diffusion of the loaded samples is usually a problem. However, the vacuum cannot be too strong; if the vacuum is too great, the efficiency of blotting decreases. Using an appropriate vacuum speed, a trace of each well will be visible on the membrane.*
  - (c) Spot samples (about 2  $\mu$ l/loading without vacuum or 5  $\mu$ l/loading under vacuum) onto the membrane filter that is prewetted with 10 $\times$  SSC and air-dried. Partially dry the filter between each spot.
  - (d) After spotting is complete, dry the filter under vacuum and place it onto a 3MM Whatman filter paper saturated with denaturing solution with the DNA side up. Incubate for 5 to 10 min.
  - (e) Transfer the membrane filter, DNA side up, to a piece of 3MM Whatman filter paper presaturated with neutralizing solution for 2 to 5 min.
  - (f) Air dry the membrane filter at room temperature for 20 min.


- (g) Wrap the filter with Saran Wrap™ and place DNA-side down onto a transilluminator (312 nm wavelength is recommended) for 4 to 6 min for UV cross-linking.
  - (h) Bake the filter in an oven at 80°C for 2 h under vacuum. Proceed to hybridization.
5. Carry out hybridization as described in Chapter 7.
  6. Measure the signal intensities of dot spots with a densitometer. For the cDNA controls, no signals should be visible. For actin cDNA, the signal intensities should increase with amplified cycles, but no differences should be seen for any cell- or tissue-type or all developmental stages, or treated- and untreated tissues. In contrast, if the expression of a specific gene is nonconstitutive but inducible with cell- or tissue-specific or chemical treatments, clear signal patterns of amplified cDNA dot blot hybridization can be seen. The signal for each sample should be stronger with amplified cycles (Figure 10.4).
  7. If it is necessary to determine the size of PCR products, the cDNAs can be analyzed using 1.0% to 1.4% agarose gel electrophoresis and Southern blot hybridization using the target sequence as an internal probe (Figure 10.5).

### Reagents needed

- *First strand 5× buffer*  
 250 mM Tris–HCl, pH 8.3 (42°C)  
 50 mM MgCl<sub>2</sub>  
 250 mM KCl  
 2.5 mM spermidine  
 50 mM DTT  
 5 mM each of dATP, dCTP, dGTP, dTTP



**FIGURE 10.4** Dot blot hybridization showing expected semiquantitative PCR products.



**FIGURE 10.5** Southern blot hybridization showing expected semiquantitative PCR products.

- *10× Amplification buffer*  
 100 mM Tris-HCl, pH 8.3  
 500 mM KCl  
 15 mM MgCl<sub>2</sub>  
 0.1% BSA

### Troubleshooting Guide

1. *After electrophoresis, distribution of RNA species stained by EtBr is near the very bottom in some lanes instead of a long smear ranging from the top to the bottom of the lanes.* This is due to obvious RNA degradation by RNase during RNA isolation, or RNA storage or electrophoresis. Ensure that RNAs are handled without RNase contamination.
2. *Two rRNA bands are not sharp, but instead, are quite diffused.* The voltage used for electrophoresis is too low and the gel is run for too long a time. To obtain the best results (sharp bands), a gel should run at an appropriate voltage.
3. *After transfer is complete, obvious RNA staining remains in the agarose gel.* RNA transfer is not efficient or complete. Try to carefully set up RNA transfer and allow blotting to proceed for a longer time.
4. *The blotted membrane shows some trace of bubbles.* Obviously, this problem is due to bubbles generated between the gel and the membrane. Carefully follow instructions when assembling the blotting apparatus.
5. *No signal is detected at all.* This is the worst situation in northern blot hybridization. RNAs may not be effectively denatured and/or dsDNA probes may not be denatured before hybridization. When this happens, it is not surprising at all to see zero hybridization signals. Keep in mind that ssDNA probes and denatured RNAs are crucial for hybridization.

6. *Hybridized signals are quite weak on the film or the filter.* The activities of DNA probes may be low or hybridization efficiency is not good. To overcome this, allow hybridization to proceed for a longer and/or increased exposure time to the x-ray film or develop longer on the filter.
7. *Detected signals are not sharp bands; rather, long smears appear in each lane.* This problem is most likely caused by nonspecific binding. Try to carry out hybridization and washing under high stringency conditions.
8. *Black background occurs on the x-ray film as revealed by chemiluminescence detection.* Multiple factors may be responsible for such a common problem. The membrane filter may have dried out during hybridization or during the washing process. Excess detection solution is not wiped out before exposure. Exposure time may be too long. The solution to this problem is to make sure that the filter be kept wet and that excess detection reagents are completely removed by wiping. Try to reduce exposure time for x-ray film.
9. *A highly purple/blue background occurs on the filter as shown by colorimetric detection.* Excess detection reagents may be used or the color is allowed to develop too long. Try using an appropriate amount of detection reagents and pay close attention to the color development. As soon as major bands become visible, stop development immediately by rinsing the filter with distilled water several times.
10. *Unexpected bands show up on the x-ray film or the membrane filter.* This problem is most likely caused by nonspecific binding between probes and the DNA species. To solve or prevent such a problem, one may increase blocking time for the blotted membrane and elevate stringency conditions for both hybridization and washing processes.

## REFERENCES

1. Wu, W. 1995. Electrophoresis, blotting and hybridization. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke, 87–122. Boca Raton, FL: CRC Press.
2. Wu, W., and M. J. Welsh. 1996. Expression of the 25-kDa heat-shock protein (HSP27) correlates with resistance to the toxicity of cadmium chloride, mercuric chloride, cis-platinum(II)-diammine dichloride, or sodium arsenite in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Toxicology and Applied Pharmacology* 141: 330–339.
3. Welsh, M. J., W. Wu, M. Parvinen, and R. R. Gilmont. 1996. Variation in expression of HSP27 messenger ribonucleic acid during the cycle of the seminiferous epithelium and co-localization of HSP27 and microfilaments in Sertoli cells of the rat. *Biology of Reproduction* 55: 141–151.
4. Wu, W. L., I. Song, R. Karupiah, and P. B. Kaufman. 1993. Kinetic induction of oat shoot pulvinus invertase mRNA by gravistimulation and partial cDNA cloning by the polymerase chain reaction. *Plant Molecular Biology* 21(6): 1175–1179.
5. Wu, W. L., J. P. Mitchell, N. S. Cohn, and P. B. Kaufman. 1993. Gibberellin (GA<sub>3</sub>) enhances cell wall invertase activity and mRNA levels in elongating dwarf pea (*Pisum sativum*) shoots. *International Journal of Plant Science* 154(2): 278–288.

6. Wu, L., I. Song, D. Kim, and P. B. Kaufman. 1993. Molecular basis of the increase in invertase activity elicited by gravistimulation of oat-shoot pulvini. *Journal of Plant Physiology* 142: 179–183.
7. Ausubel, F. M., R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl. 1995. *Current Protocols in Molecular Biology*. New York, NY: Greene Publishing Associates and Wiley-Interscience, John Wiley & Sons.
8. Krumlauf, R. 1991. Northern blot analysis of gene expression. In *Gene Transfer and Expression Protocols*, ed. E. J. Murray. Clifton, NJ: Humana Press Inc.
9. Sambrook, J., E. F. Fritsch, and T. Maniatis. 1989. *Molecular Cloning: A Laboratory Manual*, 2nd edn. Cold Spring Harbor, NY: Cold Spring Harbor Press.



---

# 11 Analysis of Gene Expression at Proteomic Level via Western Blotting

## 11.1 INTRODUCTION

Proteins are translated from mRNA species and are considered the final products of gene expression. Proteins facilitate the specific function of a gene, which makes gene expression meaningful.<sup>1-2</sup> Hence, protein expression is one of the most important components of modern molecular biology. An important approach for protein research is to analyze proteins by electrophoresis, a process in which a net charged molecule will move in an electric field. Sodium dodecyl sulfate polyacrylamide gel electrophoresis (SDS-PAGE), which was developed in the mid-1960s, is a widely used technique to separate proteins according to their net charges, sizes, and shapes.<sup>1,3-6</sup> To identify a specific protein from a protein mixture, one may need to use a powerful and commonly used technique—western blotting.

Western blot hybridization or immunoblotting is a procedure in which different types of proteins are separated by SDS-PAGE and immobilized onto a solid support either polyvinylidene difluoride (PVDF) or nitrocellulose membranes. The protein of interest on the blotted membrane is then detected by incubating the membrane with a specific antibody as a probe. Technically, western is not a person's name, nor does it refer to a geographic location. In fact, this technique was developed later than the Southern blot method, and so named western blotting. Because the technique mandates specific antibodies, either monoclonal or polyclonal antibodies, it is also called immunoblotting. Western blot technique is a sensitive, reliable, and quantitative method widely used in analysis of proteins. It can simultaneously provide information about the species, sizes, and expression levels of diversity proteins, which cannot be obtained by other alternative techniques.<sup>1-2,4-6</sup>


General factors should be considered when one performs western blot hybridization. The concentration of polyacrylamide gel will influence the separation of proteins. A general chart is displayed below, depending on the particular size of the protein of interest. Normally, the larger the size of a protein to be detected, the lower the percentage of polyacrylamide gel ought to be used in order to obtain a sharp band.

Polyacrylamide % (w/v)	Protein Size (kDa)
7%	20–200
10%	12–65
11%	8.0–35
14%	5.0–27
16%	3.0–15

During SDS-PAGE, proteins move through the gel matrix at a rate inversely proportional to the log of their molecular weight. Small proteins migrate faster than large molecules.

Transfer of proteins from a polyacrylamide gel onto a solid nitrocellulose or nylon membrane can be completed via the electrophoretic blot method. Compared with traditional nitrocellulose membranes, PVDF membranes are durable and tear-resistant. We highly recommend that PVDF be used as the solid transfer support.

Western blotting needs specific antibodies as probes. The specificity and activity of an antibody are absolutely essential to the success of western blot hybridization. There are two general types of antibodies: monoclonal antibodies raised in mice and polyclonal antibodies usually raised in rabbits.<sup>4</sup> A monoclonal antibody has a single antibody specificity, a single affinity, and a single immunoglobulin isotype. However, a preparation of polyclonal antibodies contains a variety of antibodies directed against the antigen of interest as well as nonspecific proteins. As a result, monoclonal antibody is more specific than polyclonal antibodies. Monoclonal antibodies are produced by a monoclonal population of cells derived from one cloned cell. Hence, all the antibodies are theoretically identical.



**FIGURE 11.1** Scheme of detection of specific protein by western blot hybridization.



A standard western blot hybridization mainly consists of four procedures: separation of proteins by SDS-PAGE, transfer of proteins onto a solid membrane, incubation of the membrane with specific antibodies, and detection of hybridized signal(s) (Figure 11.1). This chapter describes the step-by-step protocols used for successful western blotting.

## 11.2 PRINCIPLES

Knowing the principles of western blotting is extremely important for success. The primary principles of western blotting or immunoblotting start with separation of proteins by SDS-PAGE. SDS is a strong, negatively charged detergent that is composed of a hydrophilic head and a long hydrophobic tail ( $\text{CH}_3\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-CH}_2\text{-SO}_4^-\text{Na}^+$ ). SDS serves to denature proteins and make them negatively charged. To better understand how a protein molecule is denatured by detergent(s), it is necessary to briefly review the structures of proteins.


In general, functional proteins have four levels of structures. Primary structure is the amino acid sequence that is the backbone of a protein. Linear polypeptide chains undergo appropriate folding into the secondary structure of proteins by hydrogen bonds between main-chain NH and CO groups. In some proteins, disulfide bridges or bonds ( $\text{-S-S-}$ ) are formed between the sulfhydryl groups of two cysteine residues. The tertiary structure of protein architecture refers to the spatial folding following the secondary structure. Tertiary structure is the highest level of structure for most proteins. However, many proteins contain multiple peptide chains or subunits. The spatial arrangement of such subunits and the nature of their connections are called quaternary structure. Proteins with multiple subunits mandate the quaternary structure for functions. These unique structures make proteins much more stable. However, for SDS-PAGE analysis of proteins, proteins need to be disrupted to their primary structures using appropriate detergents. SDS is an anionic detergent that binds to hydrophobic regions of protein molecules and causes them to unfold into extended polypeptide chains. As a result, the individual proteins are dissociated from other proteins and rendered freely soluble in the SDS solution. In addition, a reducing agent  $\beta$ -mercaptoethanol ( $\text{SH-CH}_2\text{-CH}_2\text{-OH}$ ) is commonly used to break any S-S bonds in proteins.

During SDS-PAGE, the anions of SDS not only denature proteins but also coat polypeptides at a ratio of about one SDS for every two amino acid residues, which gives approximately equal charge densities per unit length and makes the polypeptides negatively charged. As a result, each protein molecule binds large numbers of the negatively charged SDS molecules that overwhelm the protein's intrinsic charge. This is exactly one of the principles of protein separation by SDS-PAGE. In an electric field, proteins wrapped with the negative SDS migrate toward the positive electrode. To enhance separation, polyacrylamide gels or PAGEs are widely used as supporting media and molecular sieves. The meshes and pore size of a PAGE can be readily made by the polymerization of acrylamide and a cross-linking reagent methylenebisacrylamide using appropriate concentrations. When a voltage is applied, proteins of the same size have the same amount of SDS molecules and the same shape due to complete unfolding by the SDS, and thus migrate at the same speed in a given pore size of a slab SDS-PAGE.


Smaller proteins move faster than larger proteins, which are retarded much more severely. As a result, proteins are fractionated into a series of discrete protein bands in order of their molecular weight (MW). There is a linear relationship between the log of the MW of a polypeptide and its  $R_f$ .  $R_f$  is the ratio of the distance from the top of the gel to a band divided by the distance from the top of the gel to the dye front. A standard curve is generated by plotting the  $R_f$  of each standard polypeptide or band marker as the abscissa and the  $\log_{10}$  of its MW as the ordinate. The MW of an unknown protein band can then be determined by finding its  $R_f$  that vertically crosses on the standard curve and reading the  $\log_{10}$  MW horizontally crossing to the ordinate. The antilog of the  $\log_{10}$  MW will be the actual MW of the protein. After electrophoresis, the SDS-PAGE gel can be stained with Coomassie blue (CB) solution. The major proteins or bands are then readily displayed by destaining the gel.

Inasmuch as the separated proteins are coated with negatively charged SDS, they can be readily transferred from the SDS-PAGE onto a solid membrane by electroblotting. The negatively charged proteins migrate toward the positive electrode and are retained on the membrane placed between the gel and the positive electrode (Figure 11.2). Various bands at different positions are exactly blotted at appropriate positions on the membrane. To check the efficiency of blotting, the blotted membrane can be stained by Ponsau S solution, and major bands are readily seen if the transfer is successful.

The major principle of western blotting is the interaction between a specific antibody and its target protein on the membrane (Figure 11.3). To understand how the binding of antibody–antigen occurs, it is helpful to be familiar with the structures of antibodies. An antibody is a Y-shaped molecule containing two heavy chains, two light chains, and two identical antigen-binding sites or bivalent at the tip of two arms. It is important to know that the binding sites are specific for a particular antigen (e.g., a protein). The antigen-binding sites make it possible for an antibody to cross-link the antigenic determinant(s) of the target antigen or a protein in terms of western blotting or immunoblotting. Many antigens have multiple antigenic determinants or epitopes, which enable the antigen to form linear chains or cyclic complexes with the antibody.



**FIGURE 11.2** Diagram of semidry electric blotting of proteins onto a membrane.




**FIGURE 11.3** Principles of western blot hybridization.

The antibody that directly binds to its antigen is named primary or first antibody. In western blot hybridization, a secondary antibody is needed, which usually interact with the first antibody (Figure 11.3). The secondary antibody is frequently conjugated with an enzyme, such as alkaline phosphatase or horseradish peroxidase. Once a complex of protein–primary antibody–secondary antibody is formed on a blotted membrane, it can be detected using substrates such as NBT and BCIP for alkaline phosphatase or luminol for horseradish peroxidase (Figure 11.4).

## 11.3 EXTRACTION OF CELLULAR PROTEINS

### 11.3.1 METHOD A. EXTRACTION OF TOTAL PROTEINS USING LAUROYLSARCOSINE BUFFER

Traditionally, proteins are extracted by lysing cells with SDS gel sample loading buffer followed by boiling. Although this procedure rapidly inactivates proteolytic



**FIGURE 11.4** Detection of actin from proteins extracted from mouse embryonic stem cells. Monoclonal antibodies against actin were used in western blotting.

enzymes and the protein samples can be immediately used for SDS-PAGE or 2-D gel electrophoresis, they are not suitable for quantitative analysis of the sample's protein concentration because the samples contain SDS and 2-mercaptomethanol. In the Bradford assay, these compounds significantly decrease the O.D. at  $A_{595}$  nm, so the concentration of proteins in the extracts cannot be accurately measured. An alternative procedure is to determine the concentration of the proteins bicinchoninic acid (BCA) assay.<sup>4</sup> The major drawbacks of this approach are that these procedures are time-consuming, and a portion of proteins are lost during the processes of trichloroacetic acid (TCA) precipitation as well as centrifugation. As a result, the protein concentration determined using this method is lower than what truly exists in the sample.

To solve this problem, a new extraction buffer has been developed.<sup>4</sup> The extracted proteins are suitable for quantitative analysis using the Bradford assay and for routine analysis of proteins by SDS-PAGE, 2-D gel electrophoresis, and immunoblotting. This method provides an economic, rapid, simple, and efficient approach for protein analysis. Cells in tissue culture dishes or flasks can be directly lysed with an extraction buffer containing 45 mM Tris-HCl (pH 6.8), 0.2% *N*-lauroylsarcosine (sodium salt; Sigma Chemical Co.), and 0.2 mM of phenylmethanesulfonyl fluoride (PMSF). Because of the instability of PMSF in aqueous solution, it is recommended to add this component to the buffer shortly before use.

### 1. Protein extraction from cultured cells

- (a) When the cells reach 50% to 100% confluence, aspirate the medium and add an appropriate volume of extraction buffer (1 to 1.5 ml/100 mm dish).
- (b) To lyse the cells, incubate for 5 min at room temperature with occasional agitation by hand. To confirm cell lysis, the dish or flask containing the cells can be observed by phase contrast microscopy.
- (c) Transfer the lysed mixture into a microcentrifuge tube (Eppendorf) and store at  $-20^{\circ}\text{C}$  until use. At this point, the sample can be utilized, without further processing, for protein concentration measurement by the Bradford assay and for quantitative analysis of proteins by 1-D or 2-D SDS-PAGE and immunoblotting.

### 2. Protein extraction from tissues

- (a) Completely homogenize 1 g tissues of interest in 2 ml of extraction buffer.
- (b) To lyse the cells, incubate the homogenate for 10 min at room temperature with occasional agitation by hand.
- (c) Centrifuge at 10,000 g for 2 min and carefully transfer the supernatant into a microcentrifuge tube and store at  $-20^{\circ}\text{C}$  until use. At this point, the sample can be utilized, without further processing, for protein concentration measurement by the Bradford assay and for quantitative analysis of proteins by 1-D or 2-D SDS-PAGE and immunoblotting.

### 11.3.2 METHOD B. DETERMINATION OF PROTEIN CONCENTRATION USING BRADFORD ASSAY

1. Label appropriate number of cuvettes for standard curve and protein samples.
2. To the cuvettes used for standard curve, add the following components in the order shown.
  - (a) BSA stock solution (1 mg/ml in dH<sub>2</sub>O): 0, 5, 10, 15, 20, 25, 20 to 40  $\mu$ l, respectively.
  - (b) The protein extraction buffer: 20 to 40  $\mu$ l for every cuvette, depending on the volume of protein sample used for measurement.
  - (c) dH<sub>2</sub>O: an appropriate volume was added to each cuvette to give a total volume of 0.1 ml.
  - (d) Bradford reagent solution: 0.9 ml to every cuvette, producing a total volume of 1 ml.
3. Transfer each protein sample (20 to 40  $\mu$ l) extracted from cultured cells or from tissues to a plastic cuvette. Add ddH<sub>2</sub>O to 0.1 ml, and then 0.9 ml of the Bradford reagent solution.
4. Carry out protein measurement at a wavelength of 595 nm in a UV-Vis spectrophotometer according to the manufacturer's instructions.

## 11.4 ANALYSIS OF PROTEINS BY SDS-PAGE AND WESTERN BLOTTING

### 11.4.1 PROTOCOL 1. PREPARATION OF SDS-SEPARATION GELS

1. Thoroughly clean glass plates and spacers with detergent and wash them in tap water. Rinse the plates and spacers with dd.H<sub>2</sub>O several times and air-dry.
2. Wear gloves and wipe dry the glass plates and spacers using clean paper prewet with 100% ethanol. Assemble the vertical slab gel unit such as the Protein II (BioRad) or the SE 600 Vertical Slab Gel Unit (Hoeffer) in the casting mode according to the instructions. Briefly, place one spacer (1.5 mm thick) on each side between the two glass plates and fix in place with clamps, forming a sandwich. Before tightly casting the sandwich, vertically place the sandwich on a very leveled bench for an appropriate adjustment. Make sure that glass plates and spacers are well matched to prevent any potential leaking. Repeat for the second sandwich if needed. Tightly cast the sandwich in the casting mode.

*Note: The glass plates should be in very good shape with no damage at the edges. If necessary, spray a little grease on the spacer areas at both the top and bottom ends of the sandwich to prevent leaking.*

3. Test potential leaking by filling appropriate volume of dd.H<sub>2</sub>O into the sandwich. If not, drain away the water by inverting the unit.
4. Prepare the separation gel mixture in a clean 100-ml beaker or flask in the order shown. This is sufficient for two pieces of standard size gels:

20 ml of 30% monomer solution  
 15 ml of separating gel buffer  
 0.6 ml of 10% SDS solution  
24.1 ml of dd.H<sub>2</sub>O  
 Mix after each addition.

Caution: *Acrylamide is neurotoxic. Gloves should be worn when handling the gel mixture.*

5. Add 0.25 ml of freshly prepared 10% ammonium persulfate (AP) solution and 20  $\mu$ l TEMED to the gel mixture. Briefly mix by gently swirling or using a pipette.
6. Immediately and carefully fill the mixture into the assembled sandwich up to about 4 cm from the top edge using a 10- to 15-ml pipette or a 50-ml syringe.
7. Take up approximately 1 ml of dd.H<sub>2</sub>O into a 1-ml syringe equipped with a 22-gauge needle and carefully load 0.5 ml of the water, starting from one top corner near the spacer, onto the surface of the acrylamide gel mixture. Load 0.5 ml of the water from the other top corner onto the gel mixture. The water will overlay the surface of the gel mixture to make the surface very even. Allow the gel to be polymerized for about 30 min at room temperature. A very sharp gel–water interface can be seen once the gel has polymerized.
8. Drain away the water layer by inverting the casting unit and rinse the surface once with 1 ml of gel overlay solution. Replace the solution with 1.5 ml of fresh gel overlay solution for at least 5 min. The gel can be kept at this point for 2 h to overnight before the next step.

#### 11.4.2 PROTOCOL 2. PREPARATION OF STACKING GELS

1. Prepare the stacking gel mixture in a clean 50-ml beaker or a 50-ml flask as follows:

2.66 ml of 30% monomer solution  
 5 ml of stacking gel buffer  
 0.2 ml of 10% SDS  
12.2 ml of dd.H<sub>2</sub>O  
 Mix after each addition.

2. Drain away the overlay solution on the separating gel by tilting the casted unit and rinse the surface with 1 ml of the stacking gel mixture prepared at step (a). Drain away the stacking gel mixture and insert a clean comb (1.5 mm thick with 14 or 30 wells) from the top into the glass sandwich.
3. Add 98  $\mu$ l of 10% AP solution and 10  $\mu$ l of TEMED to the stacking gel mixture. Gently mix and add the gel mixture into the sandwich from both upper corners next to the spacers using a pipette or an equivalent.

*Note: The stacking gel mixture may be filled into the sandwich before inserting the comb. However, air bubbles are readily generated and trapped around the teeth of the comb. It is recommended that the comb be inserted into the sandwich before filling the stacking gel mixture.*

4. Allow the stacking gel to polymerize. It usually takes approximately 30 min at room temperature.

### 11.4.3 PROTOCOL 3. ELECTROPHORESIS

#### 1. Loading of protein samples and protein standard markers onto the gel

- (a) While the stacking gel is polymerizing, prepare samples and standard markers. To completely denature proteins, add 1 volume of 2× sample loading buffer to each sample and standard markers in individual microcentrifuge tubes. Tightly cap the tubes and place them in boiling water for 4 min. Briefly spin down.

*Note: The loading buffer contains SDS and mercaptoethanol, which are strong detergents for denaturation of proteins. The amount of proteins loaded into one well should be 5 to 30 μg for CB staining and western blotting. The amount of protein standard markers for one well should be 2 to 10 μg.*

- (b) Carefully pull the comb straight up from the gel, and rinse every well with running buffer using a pipette. Drain away the buffer by tilting the casted sandwich. Repeat rinsing once.
- (c) If the apparatus Protein II (BioRad) is used, the sandwich can be directly casted in place according to manufacturer's instructions. An upper buffer chamber will be readily formed. If the SE 600 Vertical Slab Gel Unit (Hoeffer) is utilized, carefully cast the upper buffer chamber in place according to the instructions. Remove lower cams and cam tightly the sandwich to the bottom of the upper buffer chamber.

*Note: Apply a little grease on the spacer areas at the top corners of the sandwich to prevent leaking.*

- (d) Fill the upper chamber with an appropriate volume of running buffer.
- (e) Take up sample or markers into a pipette tip or a syringe equipped with a 22-gauge needle attached. Insert the tip or needle into the top of a well and load the sample into the well. Because of the 2× loading buffer added, the sample is heavier than the running buffer and can be seen sinking to the bottom of the well during loading.

*Note: The volume for each well should be less than 40 μl for a standard gel or less than 10 μl for a minigel. Overloading may cause samples to float out, resulting in contamination among wells. The markers are recommended to be loaded into the very left or right well or both wells.*

#### 2. Carrying out electrophoresis

- (a) Carefully insert the assembled unit with loaded samples into electrophoresis tank filled with 2 to 4 l of running buffer. Remove any bubbles trapped at the bottom of the sandwich using a glass Pasteur pipette hook or an equivalent tool.

*Note: The volume of running buffer in the tank should be sufficient to cover two-thirds of the sandwich. Otherwise, the heat generated during electrophoresis will not be uniformly distributed, causing distortion of the band patterns in the gel.*

- (b) Place the lid, or cover, on the apparatus and connect to a power supply. The cathode (negative electrode) should be connected to the upper buffer chamber and the anode (positive electrode) must be connected to the bottom buffer reservoir. Proteins negatively charged by SDS will migrate from the cathode to the anode.
- (c) Apply a constant power or current at 25 to 30 mA/1.5-mm thick standard size gel. Allow the gel to run for several hours or until the dye reaches about 1 cm from the bottom of the gel. If overnight run is desired, the current should be adjusted empirically.
- (d) Turn off the power and disconnect the power cables. Loosen and remove the clamps from the sandwiches. Place the gel sandwiches on the table or bench. Carefully remove the spacers and separate the two glass plates starting from one corner by inserting a spacer into the sandwich and simultaneously lifting the top glass plate. Make a small trim at the upper left or right corner of the gel to record the orientation using a razor blade. One gel will be stained to determine the MW and patterns of different protein bands. The other gel will be used for western blotting.

#### 11.4.4 PROTOCOL 4. STAINING AND DESTAINING OF SDS-PAGE USING A MODIFIED CB METHOD

1. Wear gloves and carefully transfer one of the gels into a glass or plastic tray containing 100 to 150 ml of CB staining solution and allow the gel to be stained for 30 min in a 50°C water bath with occasional agitation.
2. Replace the staining solution with 150 ml of rapid destaining solution. Allow destaining to take place for 60 to 80 min on a shaker with slow shaking. Change destaining solution once every 20 min.

Notes:

- (1) *Major protein bands should be visible after 20 min of destaining and all patterns of bands with a clear background will appear after 80 min of destaining. If desired, the destained gel can be photographed, dried, or kept in 50% diluted destaining solution in distilled water for up to 1 month.*
- (2) *The gel may be rapidly destained using 1% to 1.5% bleach solution in distilled water. Allow destaining to proceed for 30 min with agitating. Constantly monitor the destaining of the gel and immediately rinse the gel with a large volume of tap water once clear bands are visible. Change distilled water several times until the blue color of bands is stable. The drawback of this procedure is that, if overdestaining occurs, some bands may disappear.*
- (3) *The gel can be stained by the silver method, which is more sensitive than CB staining. Some weak bands seen in CB staining can become sharp bands after silver staining. However, because staining and destaining procedures are quite complicated and time-consuming, silver staining is not considered to be within the scope of this laboratory protocol.*



3. To accurately determine the MW of specific bands, measure the distance from the top of the gel to each of the bands in the protein standard marker lane and to specific bands in the protein sample lanes. Calculate the  $R_f$  for each band: divide the distance from the top of the gel to a specific band by the distance from the top of the gel to the dye front. Make a standard curve by plotting the  $R_f$  of each standard marker band as the abscissa and the  $\log_{10}$  of each MW as the ordinate. The MW of an unknown band in the protein sample can readily be determined by finding its  $R_f$  that vertically crosses the standard curve and the  $\log_{10}$  MW that horizontally crosses to the ordinate. The antilog of the  $\log_{10}$  MW is the actual MW of the protein band.

Note: *If accurate determination of protein bands is not necessary, the MW of an unknown band can be estimated by comparing the position of a specific band with those of standard marker bands.*

#### 11.4.5 PROTOCOL 5. TRANSFER OF PROTEINS FROM SDS-PAGE ONTO A NITROCELLULOSE OR PVDF MEMBRANE BY ELECTROBLOTTING

##### 11.4.5.1 Method A. Semidry Electroblotting<sup>7,8</sup>

1. After SDS-PAGE, soak the gel in 200 ml of transfer buffer for 10 min.
2. Cut a piece of PVDF or nitrocellulose membrane and 10 sheets of Whatman filter paper to the same size as the gel and soak them in transfer buffer for 4 min before blotting. If PVDF is used, briefly soak the membrane in methanol for 30 s before soaking in transfer buffer.
3. Assemble a blotting system in the order shown in Figure 11.2 using a Multiphor II electrotransfer apparatus (Pharmacia Biotech).
  - (a) Rinse the bottom plate (the negative electrode) in distilled water and place five sheets, one by one, of the soaked 3MM Whatman paper on the plate. Remove any bubbles underneath by rolling a pipette over the filter papers.
  - (b) Place the soaked membrane on the top of 3MM Whatman sheets. Gently press the membrane to remove any bubbles underneath.
  - (c) Carefully overlay the membrane with the gel, starting at one side of the gel, then slowly proceed to the other end. The marked side of the membrane should face the gel. Carefully remove any bubbles between the membrane and the gel, which can be done by gently pressing or rolling on the membrane.
  - (d) Gently overlay the gel with five sheets, one by one, of the presoaked 3MM Whatman paper.
  - (e) Prewet the top plate (the positive electrode) in distilled water and carefully place the plate on the top of the assembled unit.

*Do not distribute the assembled unit lying underneath to prevent from producing bubbles.*
  - (f) Place a bottle or beaker containing approximate 1000 ml water on the top plate to serve as a weight.

4. Connect the assembled unit to a power supply (positive to positive pole, negative to negative pole). Turn on the power and set it at a constant current. Allow blotting to proceed for 1 h at 1.2 mA/cm<sup>2</sup> membrane at room temperature.

Notes: (1) *If several gels are needed to be simultaneously transferred, place four sheets of 3MM Whatman paper between each gel and membrane, and adjust the current accordingly.* (2) *Air bubbles should be removed from each layer of the blot by carefully rolling a pipette over the surface. It is important not to move gel, membrane, and blotting paper until transfer is complete. Otherwise, bubbles will be generated and band positions are likely changed.*

#### 11.4.5.2 Method B. Liquid Transfer Using a Hoeffer TE 42 Blotting Apparatus

1. Soak the gel, membrane, and four pieces of 3MM Whatman paper sheets (relatively bigger than the gel) in 500 ml of transfer buffer for 15 min.
2. Fill a tray large enough to hold the cassette with transfer buffer to a depth of approximately 4 cm.
3. Place one-half of the cassette in the tray with the hook facing up and put one Dacron™ sponge on the cassette.
4. Place two sheets of the soaked 3MM Whatman paper on the sponge and remove any bubbles.
5. Overlay the soaked membrane on the paper sheets and remove any air bubbles between the layers.
6. Carefully place the soaked gel on the membrane and overlay the gel with two sheets of presoaked 3MM Whatman paper.  
Note: *Gloves should be worn. Gently press the filter papers to force out any trapped air bubbles that will locally block transfer of proteins onto the membrane.*
7. Overlay another Dacron sponge on the filter sheets and place the second half of the cassette on the top of the stack.
8. Hook the two halves together by sliding them toward each other so that the hooks are engaged with the opposite half.
9. Place the assembled cassette into the blotting chamber according to the instructions. Fill the chamber with transfer buffer that is sufficient to cover the cassette. Place a stir bar in the chamber.  
Note: *It is absolutely important to insert the cassette in the right place so that the membrane is between the gel and the anode (positive electrode).*
10. Place the whole chamber on a magnetic stirrer plate and turn on the stir bar at low speed. Connect the apparatus to the power supply, turn on the power, and set the current at 0.8 to 1 A.
11. Allow the transfer to take place for 60 to 75 min at 1 to 1.5 A.  
Note: *Because heat will be rapidly generated, the current should be monitored to be 1 to 1.5 A. Otherwise, it may burn the apparatus.*

#### 11.4.6 PROTOCOL 6. BLOCKING AND HYBRIDIZATION OF MEMBRANE FILTER USING SPECIFIC ANTIBODIES

1. While the transfer is taking place, prepare blocking solution (see materials).
2. After transfer is complete, stain the membrane in 1× Ponceu S solution (Sigma Chemicals) diluted in distilled water using 10 ml per 12 × 14 cm<sup>2</sup> membrane. Allow staining to take place for 5 to 8 min at room temperature and rinse the membrane in distilled water several times.

Note: *A successful transfer should show red bands. Staining will not interfere with the following steps.*

3. After rinsing, block the nonspecific binding sites on the membrane in blocking solution (100 ml per 12 × 14 cm<sup>2</sup> membrane) at room temperature for 50 min with slow shaking.

Note: *The membrane at this stage may be kept in the blocking solution for up to 48 h at 4°C. To check the efficiency of transferring, the blotted gel may be stained with CB and then destained. A successful blotting should have no visible bands left in the gel.*

4. Replace blocking solution with antibody solution containing both primary antibody (monoclonal or polyclonal antibodies against the protein of interest) and appropriate secondary antibodies diluted in Phosphate buffered saline (PBS) buffer. Allow incubation to proceed at room temperature for 70 to 100 min with slow shaking.

*Please pay attention to the following notes:*

- (1) *Traditionally, the membrane is separately incubated with primary antibodies, washed several times, and then incubated with secondary antibodies. In the author's experience, the membrane can be simultaneously incubated with both first and second antibodies with high efficiency of hybridization. This saves at least 1.5 h.*
  - (2) *The concentration of antibodies varies with the activity and specificity of antibodies. Therefore, different dilutions, in case of new antibodies, should be tested in order to obtain the optimal concentration for hybridization.*
  - (3) *If the first antibodies are monoclonal antibodies from mice, the secondary antibodies should be commercial goat anti-mouse IgA, IgG, IgM conjugated with alkaline phosphatase or with peroxidase or biotin-labeled. If the first antibodies are polyclonal antibodies from rabbits, the secondary antibodies should be goat anti-rabbit IgG conjugated with alkaline phosphatase or with peroxidase or biotin-labeled.*
  - (4) *The standard volume of antibody solution should be 30 to 40 ml per 12 × 14 cm<sup>2</sup> membrane.*
5. Transfer the hybridized membrane to a clean tray containing 200 ml/membrane of PBS. Allow washing to proceed for 60 min with slow shaking. Change PBS once every 20 min. Proceed to detection of hybridized signal(s).

Notes: (1) The antibody solution can be stored at 4°C and reused for three to four times. (2) It is optional to add 0.05% (v/v) Tween-20 to PBS to wash the membrane.

### 11.4.7 PROTOCOL 7. DETECTION OF HYBRIDIZED SIGNAL(S)

#### 11.4.7.1 Method A. Chemiluminescence Detection for Peroxidase-Conjugated or Biotin-Labeled Antibodies

1. Place a piece of Saran Wrap™ film on a bench and add 0.8 ml/filter (12 × 14 cm<sup>2</sup>) of ECL detection solution (Amersham Life Science) or its equivalent to the center of the Saran Wrap film.
2. Wear gloves and briefly damp the filter to remove excess washing solution and thoroughly wet protein binding side by lifting and overlaying the filter with the solution several times.
3. Wrap the filter with Saran Wrap film, leaving two ends of the Saran Wrap film unfolded. Place the wrapped filter on a paper towel and carefully press the wrapped filter, using another piece of paper towel, to wipe out excess detection solution through the unfolded ends of the Saran Wrap film. Excess detection solution will most likely cause a high background.
4. Completely wrap the filter and place it in an exposure cassette with protein binding side facing up. Tape the four corners of the filter.
5. In a dark room with a safe light on, overlay the filter with an x-ray film and close the cassette. Allow exposure to proceed at room temperature for 10 s to 15 h, depending on the intensity of the detected signal.
6. In a dark room, develop and fix the film in appropriate developer and fixer, respectively. If an automatic x-ray processor is available, development, fixation, washing, and drying of the film can be completed in 2 min. If a hybridized signal is detected, it appears as black band on the film (Figure 11.4).

Note: Multiple films may need to be exposed and processed until the signals are desirable. Exposure for more than 4 h may generate a high black background. In our experience, a good hybridization and detection should display sharp bands within 1.5 h. In addition, the film should be slightly overexposed to obtain a relatively dark background that will help identify the sizes of the band(s) compared with the marker bands.

#### 11.4.7.2 Method B. Colorimetric Detection for Alkaline Phosphatase-Conjugated Antibodies

1. Place the filter in color developing solution (10 ml/filter, 12 × 14 cm<sup>2</sup>) containing 40 μl of NBT stock solution and 30 μl of BCIP stock solution. NBT and BCIP stock solutions are commercially available.
2. Allow color to develop in a dark place at room temperature for 15 to 120 min or until a desired detection is obtained. Positive signals should appear as blue/purple color.

Congratulations on your successful western blot hybridization!

## 11.5 ANALYSIS OF PROTEINS BY 2-D GEL ELECTROPHORESIS

2-D gel electrophoresis consists of a first-dimension gel, which is isoelectric focusing (IEF) gel, and second dimension gel, or SDS-PAGE. IEF can separate proteins based on their isoelectric points ( $pI$  value), whereas SDS-PAGE separates proteins according to their molecular weight. Generally, 2-D is not necessary to be performed and 1-D gel or SDS-PAGE can provide sufficient information for protein expression. However, a detailed characterization of a specific protein such as protein purification and sequencing may mandate 2-D gel electrophoresis. The major disadvantage of 1-D gel electrophoresis using SDS-PAGE is that many proteins with the same molecular weight cannot separate. Instead, these proteins are shown in a single band in the gel. Normally, up to 30 to 40 bands can be seen in a single gel. In contrast, the major advantage of 2-D gel electrophoresis is that it can provide a remarkable amount of information about the  $pI$  values, molecular weight, and species of proteins in a sample. If all goes well, hundreds of protein molecules can be revealed.

Detailed and simplified instructions for performance of IEF gel are available from the Immobilize DryStrip Kit (Pharmacia). The protocols for the second dimension gel or SDS-PAGE are described above.

### Materials needed

- A microcentrifuge
  - Sterile microcentrifuge tubes (0.5 or 1.5 ml)
  - Pipettes or pipetman (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
  - Sterile pipette tips (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
  - Gel casting plates
  - Gel combs
  - Electrophoresis apparatus
  - DC power supply
  - Total protein samples
  - Specific primary antibody
  - Appropriate secondary antibody
  - PVDF or nitrocellulose membranes
  - 3MM Whatman filters
  - Multiphor II electro-semidry transfer apparatus (Pharmacia Biotech) or Hoeffer TE 42 electroliquid blotting apparatus
  - Shaker
  - Plastic trays
  - *Monomer solution (30% acrylamide)*
    - 116.8 g Acrylamide
    - 3.2 g *N,N*-Methylene-bis-acrylamide
- Dissolve after each addition in 300 ml dd.H<sub>2</sub>O. Add dd.H<sub>2</sub>O to a final volume of 400 ml. Wrap the bottle with foil and store at 4°C.
- Caution: *Acrylamide is neurotoxic. Gloves should be worn when working with this chemical.*

- *Separating gel buffer*  
72.6 g 1.5 M Tris  
Dissolve well in 250 ml dd.H<sub>2</sub>O  
Adjust pH to 8.8 with 6 N HCl  
Add dd.H<sub>2</sub>O to 400 ml  
Store at 4°C
- *Stacking gel buffer*  
24 g 0.5 M Tris  
Dissolve well in 200 ml dd.H<sub>2</sub>O  
Adjust pH to 6.8 with 6N HCl  
Add dd.H<sub>2</sub>O to 400 ml  
Store at 4°C
- *10% SDS*  
15 g SDS  
Dissolve well in 150 ml dd.H<sub>2</sub>O  
Store at room temperature
- *1% ammonium persulfate (AP)*  
0.2 g AP  
Dissolve well in 2 ml dd.H<sub>2</sub>O  
Store at 4°C for up to 5 days
- *Overlay buffer*  
25 ml Running gel buffer  
1 ml 10% SDS solution  
Add dd.H<sub>2</sub>O to 100 ml  
Store at 4°C
- *2× Denaturing buffer*  
5 ml Stacking gel buffer  
8 ml 10% SDS solution  
4 ml Glycerol  
2 ml β-Mercaptoethanol  
dd.H<sub>2</sub>O to 20 ml  
0.02 g Bromophenol blue  
Divide in aliquots and store at -20°C
- *Running buffer*  
12 g 0.25 M Tris  
57.6 g Glycine  
40 ml 10% SDS solution  
Add dd.H<sub>2</sub>O to 4 l
- *1% (w/v) Coomassie Blue solution*  
2 g Coomassie Blue R-250  
Dissolve well in 200 ml dd.H<sub>2</sub>O  
Filter using 3MM Whatman paper
- *Coomassie Blue staining solution*  
62.5 ml 1% CB solution  
250 ml Methanol

- 50 ml Acetic acid  
Add dd.H<sub>2</sub>O to final 500 ml
- *Rapid destaining solution*  
500 ml Methanol  
100 ml Acetic acid  
Add dd.H<sub>2</sub>O to final 1000 ml
- *Transfer buffer*  
39 mM glycine  
48 mM Tris  
0.04% SDS  
20% Methanol
- *Phosphate buffered saline*  
2.7 mM KCl  
1.5 mM KH<sub>2</sub>PO<sub>4</sub>  
136.9 mM NaCl  
15 mM Na<sub>2</sub>HPO<sub>4</sub>  
Adjust the pH to 7.2–7.4
- *Blocking solution*  
5% (w/v) nonfat dry milk or 1% to 2% (w/v) gelatin or 2% to 3% (w/v) bovine serum albumin (BSA) in PBS solution. Allow the powder to be completely dissolved by shaking for 30 min before use.
- *Predetection/color developing buffer*  
0.1 M Tris–HCl, pH 9.5  
0.1 M NaCl  
50 mM MgCl<sub>2</sub>
- *NBT stock solution*  
75 mg/ml nitroblue tetrazolium (NBT) salt in 70% (v/v) dimethylformamide
- *BCIP stock solution*  
50 mg/ml 5-bromo-4-chloro-3-indolyl phosphate (BCIP or X-phosphate), in 100% dimethylformamide
- *Others*  
Chemiluminescent substrates  
Appropriate primary antibodies  
Appropriate secondary antibodies

### Troubleshooting Guide

1. *After electroblotting, the blotted membrane show weak bands after Ponsou S staining whereas the blotted gel displays clear bands stained with CB.* Obviously, the efficiency of protein transfer is very low. Try to set an appropriate transfer and to increase transferring time.
2. *Protein bands are not sharp but are quite diffuse.* Current may be changed severely. Try to set up a constant power for electrophoresis.
3. *No signal at all is evident.* This is the worst situation in western blot hybridization and multiple factors may cause this problem. (a) Insufficient antigen

- (protein) was loaded into the gel. Try to increase the amount of proteins for each well. (b) Proteins may not be transferred at all onto the membrane. Make sure to stain the blotted membrane or use color protein markers as indicators. (c) The activity of primary or secondary or both antibodies are extremely low or do not work at all. Try to check the quality of antibodies by loading each of the antibodies in separate wells as controls in the same gel. If no signals are shown, it is most likely that western blot process has not been handled properly.
4. *Hybridized signals are quite weak.* The concentration of antigen is low or the activities of the antibodies may be low. To solve this problem, use an appropriate concentration of proteins or antibodies and increase the exposure time for x-ray film or develop membrane filter for a longer period.
  5. *A black background on x-ray film occurs using chemiluminescent detection.* Multiple factors may be responsible for this common problem. Membrane filter may have dried out during antibody incubation or washing process. Excess detection solution may not be wiped out before exposure. Exposure time may be allowed for too long. The solution is that the filter should be kept wet and excess detection reagents need to be wiped out. Try to reduce the exposure time for x-ray film.
  6. *A highly purple/blue background is evident on the filter using the colorimetric detection.* Excess detection reagents may be used or color develops too long. Try to apply an appropriate amount of detection reagents and pay close attention to color development. Once major bands become visible, stop development immediately by rinsing the filter with distilled water several times.
  7. *Nonspecific bands show up on x-ray film or membrane filter.* This problem is most likely caused by the nonspecificity of antibodies. Make sure that the antibodies used are specific. One option is to increase blocking reagents and blocking time to block the nonspecific binding sites on the blotted membrane and elevate washing conditions using 0.05% Tween-20 in PBS.

## REFERENCES

1. Wu, W., and M. J. Welsh 1996. Expression of the 25-kDa heat-shock protein (HSP27) correlates with resistance to the toxicity of cadmium chloride, mercuric chloride, *cis*-platinum(II)-diammine dichloride, or sodium arsenite in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Toxicology and Applied Pharmacology* 141: 330–339.
2. Wu, W., and M. J. Welsh 1996. A method for rapid staining and destaining of polyacrylamide gels. *BioTechniques* 20(3): 386–388.
3. Wu, W. 1995. Electrophoresis, blotting and hybridization. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and C. Leland, 87–122. Boca Raton, FL: CRC Press.
4. Bradford, M. M. 1976. A rapid and sensitive method for the quantitation of microgram quantities of protein utilizing the principle of protein-dye binding. *Analytical Biochemistry* 72: 248–254.



5. Towbin, J., T. Staehlin, and J. Gordon 1979. Electrophoretic transfer of proteins from polyacrylamide gels to nitrocellulose sheets: procedure and some applications. *Proceedings of the National Academy of Sciences of the United States of America* 76: 4350.
6. Knudsen, K. A. 1985. Proteins transferred to nitrocellulose for use as immunogens. *Analytical Biochemistry* 147: 285.
7. Johnson, D. A., J. W. Gautsch, J. R. Sportsman, and J. H. Elder 1984. Improved method for utilizing nonfat dry milk for analysis of proteins and nucleic acids transferred to nitrocellulose. *Gene Analysis Techniques* 1: 3.
8. Kyhse-Anderson, J. 1984. Electroblothing of multiple gels: a simple apparatus without buffer tank for rapid transfer of proteins from polyacrylamide to nitrocellulose. *Journal of Biochemical and Biophysical Methods* 10: 203.



---

# 12 Analysis of Cellular DNA or Abundance of mRNA by Radioactivity *in Situ* Hybridization

## 12.1 INTRODUCTION

Standard methods for analysis of genomic DNA or mRNA expression include Southern blot or northern blot hybridization. Although Southern or northern blot hybridization can provide quantitative information on amounts and sizes of DNAs or RNAs in specific tissues, they cannot provide spatial information on the distribution of DNA or RNA of interest within cells. Recently, a powerful and versatile technology was developed to perform this task—*in situ* hybridization.<sup>1-2</sup> This technique is a very useful tool to simultaneously detect and localize specific DNA or RNA sequences with spatial information about their subcellular locations or locations within small subpopulations of cells in tissue samples. *In situ* hybridization can identify sites of gene expression, tissue distribution of mRNA, and identification and localization of viral infections.<sup>3-5</sup>

There are two commonly used procedures for *in situ* hybridization and detection of cellular DNA or RNA<sup>6-7</sup>: (1) radioactivity *in situ* hybridization (RISH) using a radioactive probe<sup>6</sup> and (2) fluorescence *in situ* hybridization (FISH) utilizing non-radioactive probes.<sup>7</sup> Each has its own strengths and weaknesses. The RISH approach allows users to perform hybridizations at high temperatures (e.g., 65°C) and employ washing under high stringency conditions. As a result, a good signal-to-noise ratio can be obtained. However, the morphology of cells or tissues may not be well preserved. In contrast, with the FISH approach, good images of cellular structure can be preserved. This method, however, has two major disadvantages: (1) hybridization and washing procedures cannot easily be performed at high temperatures and/or under high stringency conditions; (2) during final color development, the process cannot be readily controlled. As a result, nonspecific background could be a concern. This chapter describes in detail the protocols for a successful *in situ* hybridization using isotopic probes. These methods have been well tested and have worked successfully in our laboratories.

## 12.2 TISSUE FIXATION, EMBEDDING, SECTIONING, AND MOUNTING OF SECTIONS ON SLIDES

### 12.2.1 PREPARATION OF SILANE-COATED GLASS SLIDES

The high quality of glass slides plays an essential role in preventing cells or tissue sections from falling off the slides during *in situ* hybridization. For this reason, regular glass slides should be precoated before they are used for *in situ* hybridization. Precoated glass slides are commercially available (e.g., Perkin-Elmer Corporation). Below, three commonly used methods are described.

#### 12.2.1.1 Method A. Silanization of Slides

1. Wash glass slides in 2 N HCl for 7 min using slide racks and glass staining dishes, and rinse the slides in dd.H<sub>2</sub>O for 2 × 1 min.
2. Immerse the slides in high-grade acetone for 1.5 min and air-dry.
3. Treat the slides in 2% organosilane solution (Aldrich Chemical Co.) diluted in high-grade acetone for 1.5 min with gentle agitation, then rinse the slides in high-grade acetone for 1.5 min.
4. Air-dry the slides and store them in a box at room temperature until use. The slides can be stored up to 4 years.

#### 12.2.1.2 Method B. Treatment of Slides with Poly-L-Lysine

1. Clean glass slides as described in steps 1 to 2 in Method A.
2. Immerse the slides in freshly prepared poly-L-lysine solution (Sigma; MW > 150,000, 1 mg/ml in dd.H<sub>2</sub>O) for 5 min.  
*Air bubbles should be avoided during submersion of slides.*
3. Air-dry the slides and store at 4°C for up to 7 days.

#### 12.2.1.3 Method C. Gelatin-Coating of Slides

1. Wash glass slides as described in steps 1 to 2 in Method A.
2. Coat the slides in 1% (w/v) gelatin in dd.H<sub>2</sub>O for 5 min at 4°C.
3. Air-dry the slides overnight at room temperature and store in a box at room temperature up to 4 weeks.

### 12.2.2 PREPARATION OF FIXATION SOLUTIONS

Selection of a fixative is critical to the preservation of cellular or tissue morphology during *in situ* hybridization. Based on our experience, 10% buffered-formalin solution (pH 7.0) is an excellent fixative; alternatively, paraformaldehyde (PFA) solution can also be used as a fixative as prepared below.

#### 12.2.2.1 Preparation of 4% (w/v) PFA Fixative (1 l)

1. Carefully weigh out 40 g PFA powder and add to 600 ml preheated dd.H<sub>2</sub>O (55 to 60°C); allow PFA to dissolve at the same temperature with stirring.

Caution: PFA is toxic and should be handled carefully. The preparation should be carried out in a fume hood on a heating plate. Temperature should not be above 65°C and the fixative should not be overheated.

2. Add 1 drop of 2 N NaOH solution to clear the fixative.
3. Remove from heat and add 333.3 ml (1/3 total volume) of 3× phosphate buffered saline (PBS) (8.1 mM KCl, 4.5 mM KH<sub>2</sub>PO<sub>4</sub>, 411 mM NaCl, 45 mM Na<sub>2</sub>HPO<sub>4</sub>, pH 7.2, autoclaved).
4. Adjust pH to 7.2 with 4 N HCl and bring final volume to 1 l dd.H<sub>2</sub>O.
5. Filter the solution to remove undissolved fine particles, cool to room temperature, and store at 4°C until use.

### 12.2.3 FIXATION OF CULTURED CELLS ON SLIDES

1. Briefly spin down suspended or cultured cells of interest and resuspend cells in serum-free medium at a density of 10<sup>7</sup> cells/ml.
2. Transfer 10 to 15 μl of the cells onto a precoated glass slide and allow cells to attach to the slide in a humid chamber for 40 min.  
*Three to five replicates should be set up for each cell line. Alternatively, cells can be grown directly on coated glass slides or on cover slips.*
3. Place the slides into slide racks and carefully immerse them in a glass staining dish containing a sufficient volume of 10% buffered-formalin or 4% PFA fixation solution.

4. Allow fixation to proceed at room temperature.

Note: Fixation is critical for a successful *in situ* hybridization. Fixation time varies with cell lines, ranging from 30 min to 10 hours. Therefore, the optimal fixation time should be determined empirically for each cell line.

5. Transfer the slide rack to a staining dish filled with 3× PBS and allow to incubate for 4 min to stop fixation.
6. Wash the slides 3 × 4 min with 1× PBS in fresh staining dishes.
7. Carry out complete dehydration by transferring the slide rack through a series of 6 min in ethanol dishes (50%, 70%, 95%, 100%, 100%, and 100%).
8. Completely dry the slides at room temperature and store in a box containing desiccant at -80°C until use.

Note: Slides must be completely dried before being placed in a freezer to prevent potential artifacts during freezing.

### 12.2.4 TISSUE FIXATION, EMBEDDING, SECTIONING, AND MOUNTING OF SECTIONS ON SLIDES

#### 12.2.4.1 Fixation

1. Label 10- or 20-ml snap-cap glass vials and the caps according to samples, and fill approximately 2/3 volume of each vial with freshly prepared 10% buffered-formalin or 4% PFA fixation solution.
2. Place freshly dissected tissues, organs, or embryos in the appropriate vials and allow fixation to proceed at 4°C for an optimal period.

Note: *Tissue fixation is a critical factor for the success of in situ hybridization. The desired fixation time varies with tissues. For good morphology and a good signal-to-noise ratio after in situ hybridization, an optimal time should be determined empirically. Based on our experience, a series of fixation times, ranging from 30 min to 15 h, should be set up for each sample.*

3. During sample fixation, melt an appropriate amount of paraffin wax in a clean glass beaker in a 60°C oven.
4. After fixation, carry out dehydration of samples by carefully removing the fixation solution from the vials and replacing it with 10 ml of 50% ethanol.
5. Perform complete dehydration by transferring the slides every 20 min through an ethanol series (50%, 70%, 95%, 100%, 100%, and 100%) and 2 × 15 min in xylene.

Note: *Tissue dehydration should be completed as much as possible. Otherwise, melted paraffin wax may not thoroughly penetrate the tissue, resulting in poor paraffin blocks.*


Caution: *Xylene is a toxic solvent and should be carefully handled. It is strongly recommended that any step(s) involving xylene be carried out in a hood. Used xylene should be collected in a special container for toxic waste disposal.*

#### 12.2.4.2 Embedding

1. Following step 5 above, carry out partial impregnation of the samples by quickly filling each vial with 4 ml of freshly mixed xylene and melted wax (1:1, v/v) using a hot glass Pasteur pipette. Allow incubation to proceed overnight at room temperature.
2. Melt the mixture in a 60°C oven and immediately replace the xylene/wax mixture with fresh melted wax. Allow impregnation of the samples to proceed at 60°C for 1 h.
3. Continue wax infiltration of the tissue samples by quickly replacing with fresh melted wax every 20 min using a hot glass Pasteur pipette. Repeat this step 10 times. The samples are ready for embedding.
4. Prepare embedding boats using aluminum foil or molds according to the manufacturer's instructions. Appropriate molds/boats are also commercially available.
5. Fill embedding molds with melted paraffin wax using a hot glass Pasteur pipette and quickly transfer samples to appropriate molds using a hot cutoff Pasteur pipette. Orient the samples within the mold with a hot drawn-out and sealed Pasteur pipette.

Note: *This step should be performed gently to avoid any bubbles that may become trapped inside the blocks. Place one sample in each block. Every embedding boat/mold should be clearly labeled for sample identification.*

6. Allow cast blocks to harden completely at room temperature or place boats/molds into cold water on a tray.
7. Remove the blocks from the embedding boats or molds and store the blocks in a dry place at room temperature until sectioning.



**FIGURE 12.1** Diagram of section ribbons with a trapezoidal shape and mounting on a coated glass slide.

*Note: It is important to store the blocks in a dry place. Otherwise, moisture may ruin the paraffin wax blocks. The blocks can be stored for years under these conditions.*

### 12.2.4.3 Sectioning and Mounting

1. Using a razor blade, carefully cut each of the paraffin wax blocks containing the embedded samples into a trapezoidal shape and continue to trim the sectioning surface until approximate 1 to 2 mm from the sample.
2. Place the trapezoid block in the holding clamp of a microtome with the wide edge of the trapezoid surface facing the knife.
3. Set up the thickness of sectioning at 4 to 10  $\mu\text{m}$  according to the manufacturer's instructions for a particular microtome and start to cut section ribbons.
4. Label previously coated glass slides according to sample blocks and add one to three drops of dd.H<sub>2</sub>O or 0.2% (w/v) gelatin subbing solution onto a slide. Place the slide onto a heating plate set at 50°C.
5. Carefully transfer the ribbon of sections (3 to 10 sections) onto the gelatin- or water-drop on the slide using a fine brush. Allow the ribbon of sections to stretch to remove any wrinkles until complete drying of the slide has occurred (Figure 12.1).
6. To firmly attach the sections to slides, place the slides at 40°C for 24 h.
7. Store the slides in a slide box with desiccant at -20°C until use.

## 12.2.5 CRYOSECTIONING

It has been demonstrated that frozen tissue sections are particularly suitable for RNA *in situ* hybridization, immunocytochemistry, and enzyme histochemistry. The major advantages of cryosectioning over traditional paraffin wax sectioning are that tissue embedding and sectioning are carried out under frozen conditions, and that activities of DNase, RNase, and protease are greatly inhibited. Therefore, potential degradation of DNA, RNA, or proteins is minimized, which is essential to *in situ* hybridization and enzyme histochemistry. For this reason, the present section describes in detail the protocols for tissue freezing, specimen preparation, sectioning, and fixation.

### 12.2.5.1 Preparation of Frozen Specimens

1. Chill all tools used for cryosectioning in the cryostat chamber for 15 min, including razor blades, brushes, and Pasteur pipettes. However, glass slides should not be prechilled.

2. Prechill a 50-ml Pyrex beaker or its equivalent in a container filled with liquid N<sub>2</sub> for 1 min and add a sufficient volume of CryoKwik to the beaker.
3. Label one end of a filter paper strip (3MM Whatman) with a pencil according to a specific sample and carefully place a specimen on the other end of the strip with forceps or a Pasteur pipette.
4. Carefully immerse the specimen in cold CryoKwik for 1 min and then transfer the specimen strip into a cryostat chamber. Alternatively, the specimen at this stage can be stored at -80°C until use.
5. Place a thin layer of OCT compound on the cutting chucks and place the specimen end of the strip onto the layer of OCT compound.
6. Cool the specimen/chuck mount within the cryostat with a precooled heat sink until the compound solidifies.
7. Tear off the filter paper and allow the specimen within the cryostat to reach the same temperature while the microtome is being chilled.
8. Carefully trim the specimen block to a trapezoid shape using a prechilled razor blade.

#### 12.2.5.2 Freeze Sectioning


1. Carefully mount the chuck containing the specimen in a microtome with the trapezoid surface parallel to the knife edge. Slowly retract the chuck until it clears the knife edge.
2. Set the section thickness at 8 to 10 μm in the microtome according to the manufacturer's instructions and prepare a smooth surface on the block by rapid speed cutting (e.g., one cut per second) until it is close to the specimen.
3. Before sectioning of sample, flip the plastic roll-plate down for collecting sections. The plate should just be touching the knife and lie parallel to the knife edge, but slightly behind the cutting edge of the knife.
4. Start sectioning by turning the crank. Once sections roll up at the cutting edge of the knife, lift the plastic roll plate and carefully expand the section onto the knife using a fine brush.
5. Transfer sections onto warm prelabeled and precoated glass slides by carefully overlaying the slide onto the section (Figure 12.2).
6. Repeat steps 4 and 5 until sectioning is complete.

#### 12.2.5.3 Fixation

Note: *Frozen sections should be immediately fixed except for doing enzyme histochemistry.*

1. Prepare a moisture chamber by adding a minimum volume of distilled water to an appropriate size tray and place a number of plastic or glass Pasteur pipettes on the bottom parallel to each other.
2. Place slides with sections on the pipettes in the moisture chamber and cover the sections with an appropriate volume of 4% PFA fixative or 10% buffered-formalin.





**FIGURE 12.2** Diagram of thin cryosectioning ribbons and mounting on a coated glass slide.

3. Cover the chamber and allow fixation to proceed for the desired time at room temperature.

*Note: An optimal fixation time should be determined empirically for each tissue sample. In general, a range from 20 min to 8 h should be tested.*

4. Carefully aspirate off the fixation solution and rinse with PBS for 6 min. Repeat washing with PBS three times.
5. Carry out dehydration by replacing PBS with a series of ethanol (40%, 50%, 75%, 95%, 100%, and 100%), 4 min each.
6. Air-dry the slides and store the slides in a slide box in an airtight container with desiccant at  $-80^{\circ}\text{C}$  until use.

*Note: Slides should be prewarmed to room temperature before use.*

### 12.3 *IN SITU* HYBRIDIZATION AND DETECTION USING ISOTOPIC PROBES

This part describes successful techniques for *in situ* hybridization using a radioactive probe. Procedures include dewaxing and rehydration/hydration of sections, protease digestion, DNase or RNase treatment, preparation of isotopic probes, hybridization, and detection of cellular DNA or RNA.

#### 12.3.1 DEWAXING OF SECTIONS

Paraffin wax sections prepared in Section 12.2 must be subjected to complete dewaxing to allow treatments with protease, DNase, or RNase as well as penetration of the probe into the tissue. Dewaxing of sections can be completed readily with xylene. For unembedded cultured cells and cryosections, dewaxing is not necessary.

1. Transfer sections from freezer to a slide rack and allow them to reach room temperature for a few minutes before use.
2. Fill three staining dishes with fresh xylene and two staining dishes with 100% ethanol.
3. Dewax the sections by placing the slide rack into a series of three changes of xylene prepared at step 2, for 3 min in each solution.
4. Wash the sections in two changes of 100% ethanol prepared at step 2, for 3 min each.
5. Air-dry the slides and proceed to protease digestion.

### 12.3.2 PROTEASE DIGESTION

Protease treatment is only applied to the sections to be used for *in situ* hybridization of DNA or RNA but not to those sections that are utilized for immunohistochemistry or enzyme histochemistry. An appropriate protease digestion of sections removes some of the proteins from the cellular network to make DNA or RNA more accessible for *in situ* hybridization. It subsequently enhances the hybridized signal of interest and reduces background as well.

1. Prepare a sufficient volume of protease solution as follows:
  - Proteinase K solution: 1 mg/ml in 50 mM Tris-HCl, pH 7.5.
  - Pepsin solution: 2 mg/ml in dd.H<sub>2</sub>O, pH ~2.0 (40 mg pepsin in 19 ml dd.H<sub>2</sub>O and 1 ml 2 N HCl).
  - Trypsin solution: 2 mg/ml in dd.H<sub>2</sub>O (40 mg pepsin in 19 ml dd.H<sub>2</sub>O and 1 ml 2 N HCl).

Notes: (1) *Protease solutions can be stored at -20°C for up to 2 weeks.* (2) *Although each of three protease solutions works equally well in our laboratories, we recommend that one use pepsin or trypsin solution. Proteinase K digestion is not readily controlled as compared with pepsin or trypsin. As a result, overdigestion of tissue usually occurs.* (3) *Proteinase K is relatively difficult to inactivate or wash away from the tissue. In contrast, it is easy to inactivate and wash pepsin or trypsin by simple adjustment of the pH from 2.0 to 7.2 to 7.5, which is the standard pH of PBS.*

2. Carefully overlay the tissue sections with an appropriate volume of the protease solution.

*Add protease solution onto tissue sections instead of immersing the slide rack into a staining dish containing a large volume of protease solution. Otherwise, protease covers the entire surface of the slides and it is not readily washed away after treatment.*
3. Carry out digestion of tissues at 37°C for 10 to 30 min.

Notes: *Protease digestion is a tricky step for the success of in situ hybridization. Insufficient protease digestion may result in a diminished and/or completely absent hybridization signal. If overdigestion occurs, the tissue morphology may be poor or be completely destroyed. To obtain a good signal-to-noise ratio and a good preservation of tissue morphology, it is recommended that one determine the optimal digestion time for each tissue sample. Different tissues may have different optimal digestion times. We usually set up a series of protease treatment times (5, 10, 15, and 30 min) for tissue sections fixed for 0.5 to 2, 3 to 5, 7 to 10, and 12 to 18 h, respectively. Each test should consist of two to three replicates. It is hoped that these trial tests will provide investigators with a useful guide to determine the optimal digestion time for specific in situ hybridizations.*

4. After protease digestion is complete, stop proteolysis by rinsing the slides in a staining dish containing PBS (pH 7.4) with 2 mg/ml glycogen. Perform three changes of fresh PBS, 1 min each. Alternatively, wash the slides for 1 min in a solution containing 100 mM Tris-HCl and 100 mM NaCl.

5. Postfix the specimens in freshly prepared 10% buffered-formalin solution or 4% PFA fixative for 6 min at room temperature.
6. Rinse the slides with PBS for three times, 1 min for each rinse.
7. Rinse the slides in 100% ethanol for 1 min and air-dry. At this stage, the sections will be subjected to different treatments, depending on *in situ* hybridization with cellular DNA or with RNA.

### 12.3.3 DNase TREATMENT FOR *IN SITU* HYBRIDIZATION OF RNA

This treatment serves to remove cellular DNA from tissue. We have found that genomic DNA may compete with RNA species of interest in hybridizing with a specific probe. Subsequently, DNase digestion can reduce nonspecific background for *in situ* hybridization of RNA.

1. Overlay the tissue sections with an appropriate volume of DNase solution that is RNase free and is commercially available (e.g., Boehringer Mannheim Corporation).
2. Allow digestion to proceed for 30 min at 37°C.
3. After digestion is complete, inactivate DNase by rinsing the slides in a staining dish containing a solution of 10 mM Tris-HCl (pH 8.0), 150 mM NaCl, and 20 mM EDTA for 5 min.
4. Wash the slides in TE buffer (pH 8.0) for 3 × 2 min and 1 min in 100% ethanol and air-dry. At this stage, the slides are ready for hybridization or can be stored in a slide box with desiccant at -80°C until use.

Note: *To prevent RNase contamination, all the tools used for in situ hybridization of cellular RNA should be completely cleaned and rinsed with DEPC-treated dd.H<sub>2</sub>O. All solutions should be treated with 0.1% (v/v) DEPC or prepared using DEPC-treated water. RNase contamination may completely ruin the experiment.*

### 12.3.4 RNase TREATMENT FOR *IN SITU* HYBRIDIZATION OF DNA

This treatment functions to degrade cellular RNA in the tissue inasmuch as RNA can compete with DNA species of interest in hybridizing with a specific probe. As a result, RNase digestion can enhance the hybridized signal by reducing nonspecific background for *in situ* hybridization of DNA.

1. Overlay the tissue sections with an appropriate volume of RNase solution (DNase-free).
2. Allow digestion to proceed for 30 min at 37°C.
3. After digestion is complete, inactivate RNase by rinsing the slides in a staining dish containing a solution of 10 mM Tris-HCl (pH 8.0), 150 mM NaCl, and 20 mM EDTA for 5 min.
4. Wash the slides in TE buffer (10 mM Tris-HCl, 1 mM EDTA, pH 8.0) for 3 × 2 min and 1 min in 100% ethanol, and air-dry. At this stage, the slides

are ready for hybridization or can be stored in a slide box with desiccant at  $-80^{\circ}\text{C}$  if the time schedule is not convenient.

### 12.3.5 PREPARATION OF RADIOACTIVE PROBES

#### 12.3.5.1 Synthesis of Probes for DNA Hybridization Using Random Primer Labeling of dsDNA

Random primer labeling kits are commercially available from companies such as Pharmacia, Promega Corporation, and Boehringer Mannheim Corporation. A kit usually includes a population of random hexanucleotides synthesized by an automated DNA synthesizer. Such a mixture of random primers contains all four bases in each position. The primers can be utilized to primer DNA synthesis *in vitro* from any denatured, closed circular, or linear dsDNA as template using the Klenow fragment of *Escherichia coli* DNA polymerase I. Inasmuch as this enzyme lacks 5' to 3' exonuclease activity, the DNA product is produced exclusively by primer extension instead of by nick translation. During the synthesis, one of the four dNTPs is radioactively labeled and incorporated into the new DNA strand. By primer extension, it is relatively easy to produce a probe with extremely high specific activity ( $10^8$  cpm/ $\mu\text{g}$ ) because more than 70% of the labeled dNTP can be incorporated into the new DNA strand. In a typical reaction, the amount of DNA template can be as low as 25 ng.

1. Place 1  $\mu\text{l}$  of DNA template (0.5 to 1.0  $\mu\text{g}/\mu\text{l}$  in dd.H<sub>2</sub>O or TE buffer) in a sterile microcentrifuge tube. Add an appropriate volume of dd.H<sub>2</sub>O or TE buffer (19 to 38  $\mu\text{l}$ ) to the tube to dilute the DNA template to 25 to 50 ng/ $\mu\text{l}$ .
2. Cap the tube and denature the dsDNA into ssDNA by boiling for 6 min, and quickly chilling the tube on ice H<sub>2</sub>O for 2 to 4 min. Briefly spin down.
3. Set up a labeling reaction by adding the following components, in the order listed below:

Denatured DNA template (25–50 ng)	1 $\mu\text{l}$
5 $\times$ labeling buffer	10 $\mu\text{l}$
Acetylated BSA (10 mg/ml) (optional)	2 $\mu\text{l}$
Three unlabeled dNTP mixture (500 $\mu\text{M}$ each)	2 $\mu\text{l}$
[ <sup>35</sup> S]dCTP or [ <sup>35</sup> S]dATP (1000–1500 Ci/mmol)	2.5–4 $\mu\text{l}$
<u>Klenow enzyme</u>	<u>5 units</u>
Add dd.H <sub>2</sub> O to final volume	50 $\mu\text{l}$

Note: The standard amount of DNA template for one reaction should be 25 to 50 ng. Because the specific activity of probe depends on the amount of the template, the lower the amount, the higher the specific activity of the probe. [<sup>35</sup>S]dCTP or [<sup>35</sup>S]dATP (1000 to 1500 Ci/mmol) should not be  $>5$   $\mu\text{l}$  used in the reaction to prevent potential high background.

Caution: [<sup>35</sup>S]dCTP and [<sup>35</sup>S]dATP are dangerous and should be handled carefully using an appropriate Plexiglas protector shield. Any gloves and waste buffer/solutions containing radioactive materials should be placed in special containers for isotopic disposal.

4. Mix well and incubate the reaction at room temperature for 60 min.
5. Stop the reaction by adding 5  $\mu$ l of 200 mM EDTA and place on ice for 2 min.
6. Determine the percentage of [ $^{35}$ S]dCTP incorporated into the DNA and purify the probe from unincorporated nucleotides using the protocols as described in the following subsection.

#### 12.3.5.1.1 Protocol 1. DE-81 Filter-Binding Assay

- (1) Dilute 1  $\mu$ l of the labeled mixture in 99  $\mu$ l (1:100) of 200 mM EDTA solution (pH 8.0). Spot 3  $\mu$ l of the diluted sample onto two pieces of Whatman DE-81 filter papers (2.3 cm diameter). Air-dry the filters.
- (2) Rinse one filter with 50 ml of 0.5 M sodium phosphate buffer (pH 6.8) for 5 min to remove unincorporated cpm. Repeat washing twice. The other filter will be utilized directly to obtain the total cpm of the sample.
- (3) Add an appropriate volume of scintillation fluid (~10 ml) to each vial containing one of the filters. Count the cpm in a scintillation counter according to the manufacturer's instructions.

#### 12.3.5.1.2 Protocol 2. TCA Precipitation

- (1) Dilute 1  $\mu$ l of the labeled reaction mixture in 99  $\mu$ l (1:100) of 200 mM EDTA solution and spot 3  $\mu$ l on a glass fiber filter or on a nitrocellulose filter for determination of the total cpm in the sample. Allow the filter to air-dry.
- (2) Add 3  $\mu$ l of the same diluted sample into a tube containing 100  $\mu$ l of 100  $\mu$ g/ml carrier DNA or acetylated BSA and 20 mM EDTA. Mix well.
- (3) Add 1.3 ml of ice-cold 10% trichloroacetic acid (TCA) and 1% (w/v) sodium pyrophosphate to the mixture. Incubate the tube on ice for 20 to 25 min to precipitate the DNA.
- (4) Filter the precipitated DNA on a glass fiber filter or on a nitrocellulose filter using vacuum. Rinse the filter with 5 ml of ice-cold 10% TCA 4 times under vacuum. Wash the filter with 5 ml of acetone (for glass fiber filters only) or 5 ml of 95% ethanol. Air-dry the filter.
- (5) Transfer the filter to two scintillation counter vials and add 10 to 15 ml of scintillation fluid to each vial. Count the total cpm and incorporated cpm in a scintillation counter according to the manufacturer's instructions.

#### 12.3.5.1.3 Protocol 3. Calculation of Specific Activity of the Probe

- (1) Calculate the theoretical yield:

$$\text{ng theoretical yield} = \frac{\mu\text{Ci dNTP added} \times 4 \times 330 \text{ ng/nmol}}{\text{Specific activity of the labeled dNTP } (\mu\text{Ci/nmol})}$$

- (2) Calculate the percentage of incorporation:

$$\% \text{ incorporation} = \frac{\text{cpm incorporated}}{\text{total cpm}} \times 100$$

(3) Calculate the amount of DNA produced:

$$\text{ng DNA synthesized} = \% \text{ incorporation} \times 0.01 \times \text{theoretical yield}$$

(4) Calculate the specific activity of the prepared probe:

$$\text{cpm}/\mu\text{g} = \frac{\text{total cpm incorporated (cmp incorporated} \times 33.3 \times 50)}{(\text{ng DNA synthesized} + \text{ng input DNA}) \times 0.001 \mu\text{g/ng}} \times 100$$

*The factor 33.3 is derived from the use of 3  $\mu\text{l}$  of 1:100 dilution for the filter-binding or TCA precipitation assay. The factor 50 is derived from the use of 1  $\mu\text{l}$  of the total 50  $\mu\text{l}$  reaction mixture for 1:100 dilution.*

*For example, given that 25 ng DNA is to be labeled and that 50  $\mu\text{Ci}$  [ $^{35}\text{S}$ ]dCTP (1000 Ci/mmole) is utilized in 50  $\mu\text{l}$  of a standard reaction, and assuming that  $4.92 \times 10^4$  cpm is precipitated by TCA and that  $5.28 \times 10^4$  cpm is the total cpm in the sample, the calculations are as follows:*

$$\begin{aligned} \text{Theoretical yield} &= \frac{50 \mu\text{Ci} \times 4 \times 330 \text{ ng/nmol}}{1000 \mu\text{Ci/nmol}} \\ &= 66 \text{ ng} \end{aligned}$$

$$\begin{aligned} \% \text{ incorporation} &= \frac{4.92 \times 10^4}{5.28 \times 10^4} \times 100 \\ &= 93\% \end{aligned}$$

$$\begin{aligned} \text{DNA synthesized} &= 0.93 \times 66 \\ &= 61.3 \text{ ng} \end{aligned}$$

$$\begin{aligned} \text{Specific activity} &= \frac{4.92 \times 10^4 \times 33.3 \times 50}{(61.3 \text{ ng} + 25 \text{ ng}) \times 0.001 \mu\text{g/ng}} \times 100 \\ &= 9.5 \times 10^8 \text{ cpm}/\mu\text{g DNA} \end{aligned}$$

#### 12.3.5.1.4 Protocol 4. Purification of a Radioactive Probe

It is recommended that one perform separation of a labeled probe from an unincorporated isotopic nucleotide so as to avoid a high background (e.g., unexpected black spots on the hybridization filter). Use of chromatography on Sephadex G-50 spin columns or Bio-Gel P-60 spin column is a very effective way for separation of a labeled DNA from unincorporated radioactive precursors such as [ $^{35}\text{S}$ ]dCTP or [ $^{35}\text{S}$ ]dATP. The oligomers will be retained in the column. This is particularly

useful when an optimal signal-to-noise ratio with 150 to 1500 bases in length probe is generated.

- (1) Suspend 2 to 4 g Sephadex G-50 or Bio-Gel P-60 in 50 to 100 ml of TEN buffer and allow equilibration to occur for at least 1 h. Store at 4°C until use. Alternatively, such columns can be purchased from commercial companies.
- (2) Insert a small amount of sterile glass wool into the bottom of a 1-ml disposable syringe using the barrel of the syringe to tamp the glass wool in place.
- (3) Fill the syringe with the Sephadex G-50 or Bio-Gel P-60 suspension up to the top.
- (4) Place the syringe containing the suspension in a 15-ml disposable plastic tube and place the tube in a swinging-bucket rotor in a bench-top centrifuge. Carry out centrifugation at 1600 *g* for 4 min at room temperature.
- (5) Repeat addition of the suspended resin to the syringe and continue centrifugation at 1600 *g* for 4 min until the packaged volume reaches 0.9 ml in the syringe and remains unchanged after centrifugation.
- (6) Add 0.1 ml of 1× TEN buffer to the top of the column and recentrifuge as described above. Repeat this step three times.
- (7) Transfer the spin column to a fresh 15-ml disposable tube and add the labeled DNA mixture to the top of the resin dropwise using a Pasteur pipette.
- (8) Centrifuge at 1600 *g* for 4 min at room temperature. Discard the column containing unincorporated radioactive nucleotides into a radioactive waste container. Carefully transfer the effluent (about 0.1 ml) from the bottom of the decapped microcentrifuge tube or of the 15-ml tube to a fresh microcentrifuge tube. The purified probe can be stored at -20°C until it is used for hybridization.

### 12.3.5.2 Preparation of [<sup>35</sup>S]UTP Riboprobe for RNA Hybridization by Transcription *in Vitro* Labeling

Recently, a number of plasmid vectors have been developed for subcloning the cDNA of interest. These vectors contain polycloning sites downstream from powerful bacteriophage promoters T7, SP6, or T3 in the vector. The cDNA of interest can be cloned at the polycloning site between promoters SP6 and T7 or T3, generating a recombinant plasmid. The cDNA can be transcribed *in vitro* into single-strand sense RNA or antisense RNA from a linear plasmid DNA with promoters SP6, T7, or T3. During the process of *in vitro* transcription, one of the rNTPs is radioactively labeled and can be incorporated into the RNA strand, which is the labeled riboprobe. The probe has a high specific activity and is much “hotter” than an ssDNA probe. Compared with DNA labeling, a higher yield of RNA probe can be obtained because the template can be repeatedly transcribed. RNA probes can be easily purified from DNA template merely with treatment of DNase I (RNase-free). The greatest merit of an RNA probe over a DNA probe is that the RNA probe can produce much stronger hybridization signals.

1. Prepare linear DNA template for transcription *in vitro*. The plasmid can be linearized by an appropriate restriction enzyme for producing “runoff” transcripts. The recombinant plasmid should be digested with an appropriate restriction enzyme that cuts at one site that is very close to one end of cDNA insert.

(a) Set up a plasmid linearization reaction mixture on ice.

Recombinant plasmid DNA ( $\mu\text{g}/\mu\text{l}$ )	5 $\mu\text{g}$
Appropriate restriction enzyme 10 $\times$ buffer	5 $\mu\text{l}$
<u>Appropriate restriction enzyme (10–20 u/<math>\mu\text{l}</math>)</u>	<u>20 units</u>
Add dd.H <sub>2</sub> O to a final volume of	50 $\mu\text{l}$

- (b) Allow digestion to proceed for 2 h at the appropriate temperature, depending on the particular enzyme.
  - (c) Carry out extraction by adding one volume of TE-saturated phenol/chloroform and mix well by vortexing. Centrifuge at 12,000 *g* for 5 min at room temperature.
  - (d) Transfer the top, aqueous phase to a fresh tube and add one volume of chloroform/isoamyl alcohol (24:1) to the supernatant. Mix well and centrifuge as in step (c).
  - (e) Carefully transfer the top, aqueous phase to a fresh tube. Add 0.1 volume of 2 M NaCl solution or 0.5 volume of 7.5 M ammonium acetate (optional), and 2.5 volumes of chilled 100% ethanol to the supernatant. Precipitate the linearized DNA at  $-80^{\circ}\text{C}$  for 30 min or at  $-20^{\circ}\text{C}$  for 2 h.
  - (f) Centrifuge at 12,000 *g* for 5 min, decant the supernatant, and briefly rinse the DNA pellet with 1 ml of 70% ethanol. Dry the pellet for 10 min under vacuum and dissolve the DNA in 15  $\mu\text{l}$  dd.H<sub>2</sub>O.
  - (g) Use 2  $\mu\text{l}$  of the sample to measure the concentration of the DNA by UV absorption spectroscopy at  $A_{260}$  nm and  $A_{280}$  nm. Store the DNA at  $-20^{\circ}\text{C}$  until use.
2. Blunt the 3' overhang ends by the 3' to 5' exonuclease activity of Klenow DNA polymerase. Even though this is optional, we recommend that the 3' protruding end be converted into a blunt end since some of the RNA sequence is complementary to that of vector DNA.

Note: *Enzymes such as KpnI, SacI, PstI, BglI, SacII, PvuI, Sfi, and SphI should not be utilized to linearize plasmid DNA for transcription in vitro.*

(a) Set up, on ice, an *in vitro* transcription reaction mixture as listed below:

5 $\times$ transcription buffer	8 $\mu\text{l}$
0.1 M DTT	4 $\mu\text{l}$
rRNasin ribonuclease inhibitor	40 units
<u>Linearized template DNA (0.2–1.0 g/<math>\mu\text{l}</math>)</u>	<u>2 <math>\mu\text{l}</math></u>
Add dd.H <sub>2</sub> O to a final volume of	15.2 $\mu\text{l}$

- (b) Add Klenow DNA polymerase (5 u/ $\mu\text{g}$  DNA) to the mixture above and incubate at  $22^{\circ}\text{C}$  for 15 min.



- (c) Add the following components to the reaction and mix well.

Mixture of ATP, GTP, UTP (2.5 mM each)	8 $\mu$ l
120 $\mu$ M UTP	4.8 $\mu$ l
[ <sup>35</sup> S]UTP (1000–1500 Ci/mmol)	10 $\mu$ l
SP6 or T7 or T3 RNA polymerase (15–20 u/ $\mu$ l)	2 $\mu$ l

- (d) Incubate the reaction at 37 to 40°C for 60 min.
- Remove the DNA template with *DNase* I.
    - Add *DNase* I (RNase-free) to a concentration of 1 u/ $\mu$ g DNA template.
    - Incubate for 20 min at 37°C.
  - Purify the RNA probe as described for DNA labeling or by phenol/chloroform extraction followed by ethanol precipitation.
  - Determine the percentage of incorporation and the specific activity of the RNA probe, which is similar to the method in preceding DNA labeling.
 

Note: *The specific activity of the probe can be calculated as follows. For example, if 1  $\mu$ l of a 1:10 dilution is utilized for TCA precipitation,  $10 \times \text{cpm precipitated} = \text{cpm}/\mu\text{l}$  incorporated. In 40  $\mu$ l of a reaction mixture,  $40 \times \text{cpm}/\mu\text{l}$  is the total cpm incorporated. If 50  $\mu$ Ci of labeled [<sup>35</sup>S]UTP at 1000  $\mu$ Ci/nmol is used, then  $50/1000 = 0.05$  nmol of UTP is added to the reaction. Assuming that there is 100% incorporation and that UTP represents 25% of the nucleotides in the RNA probe,  $4 \times 0.05 = 0.2$  nmol of nucleotides is incorporated, and  $0.2 \times 330$  ng/nmol = 66 ng of RNA is synthesized. Then, the total ng RNA probe = % incorporation  $\times$  66 ng. For instance, if a 1:10 dilution of the labeled RNA sample has  $2.2 \times 10^5$  cpm, the total cpm incorporated is  $10 \times 2.2 \times 10^5$  cpm  $\times$  40  $\mu$ l (total reaction) =  $88 \times 10^6$  cpm; hence, % incorporation =  $88 \times 10^6$  cpm/ $110 \times 10^6$  cpm (50  $\mu$ Ci) = 80%. Therefore, total RNA synthesized = 66 ng  $\times$  0.80 = 52.8 ng RNA. The specific activity of the probe =  $88 \times 10^6$  cpm/ $0.0528$   $\mu$ g =  $1.6 \times 10^9$  cpm/ $\mu$ g RNA.*

### 12.3.6 *IN SITU* HYBRIDIZATION

After treatment of specimens with DNase (see Section 12.2.3) or RNase (see Section 12.2.4) and preparation of a specific probe (see Section 12.2.5) are complete, one can proceed to *in situ* hybridization. In general, the procedure for DNA hybridization is similar to that of RNA hybridization except for differences indicated at specific steps.

- Carry out blocking of nonspecific sulfur-binding sites on tissue specimens before hybridization.
  - Remove slides from freezer and place them in a slide rack. Allow the slides to warm up to room temperature for a few minutes.
  - Immerse the slide rack in PBS buffer containing 10 mM DTT in a staining dish, and allow the specimens to equilibrate for 12 min at 45°C in a water bath.

- (c) Transfer the slide rack to a fresh staining dish containing a sufficient volume of freshly prepared blocking solution. Wrap the entire staining dish with aluminum foil and allow blocking of the specimens to proceed for 45 min at 45°C.

Note: *Blocking of nonspecific sulfur-binding sites on specimens can reduce the background considerably when using [<sup>35</sup>S]-labeled probes. However, it is not necessary for [<sup>32</sup>P]-labeled probes.*

Caution: *The blocking solution contains toxic iodoacetamide and N-ethylmaleimide, which should be handled carefully. Waste solutions should be placed in special containers for toxic waste disposal.*

- (d) Wash the slides 3 × 3 min in PBS buffer and 3 min in TEA buffer at room temperature.
  - (e) Block polar and charged groups on tissue specimens by transferring the slide rack to fresh TEA buffer containing 0.5% acetic anhydride.
  - (f) Incubate the specimens in 2× SSC for 5 min at room temperature.
  - (g) Dehydrate the tissue specimens through a series of ethanol (50%, 75%, 95%, 100%, 100%, and 100%), 3 min each at room temperature.
  - (h) Completely dry the slides by air-drying or in a desiccator and proceed to prehybridization or store at -80°C if the schedule is not convenient.
2. Perform prehybridization as follows:

- (a) Carefully overlay tissue specimens with an appropriate volume of prehybridization solution (15 to 20 μl/10 mm<sup>2</sup>) using a pipette tip.
- (b) Place the slides in a high-humidity chamber and allow prehybridization to proceed for 1 h at 50°C.
- (c) During prehybridization, prepare an appropriate volume of hybridization cocktail (see “Reagents needed” list).
- (d) After prehybridization is complete, carefully remove the prehybridization solution from the slides using a 3MM Whatman paper strip or a pipette tip.
- (e) Immediately overlay each specimen with freshly prepared hybridization cocktail containing the specific probe (15 to 20 μl/10 mm<sup>2</sup>). Cover the cocktail with a piece of plastic coverslip that is slightly larger than the tissue section.
- (f) Simultaneously denature both the probe and the target DNA or RNA by placing the slides on a hot plate for 3 to 4 min at 95 to 100°C for DNA hybridization or at 65 to 70°C for RNA hybridization.

Note: *DNA or RNA in the specimens can be denatured before prehybridization. Labeled probes can be denatured immediately before preparation of the hybridization cocktail.*

- (g) Quickly place the slides in a moisture chamber and carry out hybridization at 55 to 65°C for 2 to 4 h.

Notes: (1) *Any bubbles underneath the plastic coverslips should be removed by gently pressing the coverslip or with a toothpick.* (2) *To prevent uneven hybridization, slides should be kept level in the chamber.* (3) *The humidity chamber must be tightly covered or sealed before*

*being placed in a hybridization oven or an equivalent. If the specimens are dried during hybridization, a high background will occur.*

- (h) After hybridization, quickly place slides in a slide rack and insert the rack into a staining dish filled with washing solution containing 2× SSC and 2 mM β-mercaptoethanol. Wash the slides with three changes of fresh washing solution, each time for 15 min at 55°C with gentle shaking.

*Caution: Any used washing solution containing isotope should be collected in a isotope waste container for disposal. Any areas touched by the isotopic solution or slides should be surveyed afterward for potential contamination by following local guidelines.*

- (i) Continue to wash the slides twice, 5 min for each session, in a fresh washing solution containing 0.2× SSC and 2 mM β-mercaptoethanol at room temperature with gentle shaking.

*At this stage, unhybridized RNA in the tissue specimens can be removed by using an appropriate amount of RNase (DNase-free, Boehringer Mannheim Corporation) or a mixture containing 45 μg/ml RNase A, 2 μg/ml RNase T1 (Sigma Chemicals), 5 mM EDTA, and 250 mM NaCl in TE buffer, pH 7.5. RNase treatment should enhance the signal-to-noise ratio, thereby reducing background.*

- (j) Dehydrate the slides through a series of ethanol (50%, 75%, 95%, 100%, 100%, and 100%), at 3 min each.
- (k) Air-dry the slides. Proceed to emulsion autoradiography.

### 12.3.7 DETECTION OF HYBRIDIZED SIGNALS

For large organs or tissues, tape the slides to a film exposure cassette or a cardboard and expose the slides against the film at 4°C for 1 to 10 days before emulsion autoradiography. In general, slides are directly subjected to autoradiographic emulsion by use of the following method:

1. Add an appropriate volume of working NTB-2 emulsion (prethawed in a 45°C water bath) to a slide dipping chamber.
2. Slowly and carefully dip the slides into the dipping chamber and gently pull the slides out. Place the slides vertically in an appropriate rack and air-dry the slides for 2 h or in front of a fan for 20 min.
3. Place the slides in a light-tight slide box containing desiccant and seal the box with black tape. Thoroughly wrap the box with aluminum foil and allow exposure to proceed at 4°C for 1 to 10 days, depending on the intensity of the signal.

*Notes: (1) The exposure of slides mandates a <sup>32</sup>P-free environment. Thus, make sure to perform a radioactive survey of the refrigerator or cold room where the exposure takes place. (2) The slides must be completely dried before exposure because moisture results in fading of the images in the autoradiographic emulsion.*

4. In a darkroom with a safe light, add sufficient volumes of developer, water, and fixer to slide jars or staining dishes and allow the solution and water to warm up to 20°C.
5. Transfer the slide exposure box from the refrigerator or cold room to the darkroom and allow the box to warm up to 20°C.
6. Turn on an appropriate safe light in a light-tight darkroom, open the exposure box, and place the slides in a slide rack.
7. Carefully immerse the slides in developer for 2 to 4 min, quickly rinse the slides in water for 30 s, and immediately place the slides in fixer for 3 min.
8. Wash the slides in slowly running tap water for 30 min. Turn on the normal light, remove emulsion on the back side of the slide using a razor blade, and air-dry the slides in a dust-free place.
9. Carry out slight counterstaining of the slides in order to enhance the images using the hematoxylin/eosin staining procedure as described below.
  - (a) Prepare a series of solutions in slide staining dishes in the order below:  
1 dish: hematoxylin stain; 2 dishes: water; 1 dish: 0.1%  $\text{NH}_4\text{OH}$ ;  
2 dishes: water; 1 dish: eosin stain; 1 dish: 95% ethanol; 3 dishes: 100% ethanol; 3 dishes: xylene.
  - (b) Prewet the developed slides in water in a staining dish for 2 min.
  - (c) Stain the specimens in hematoxylin for 10 to 30 s and rinse the slides in water for  $2 \times 2$  min.
  - (d) Quickly dip the slides in 0.1%  $\text{NH}_4\text{OH}$  and rinse in water for  $2 \times 3$  min.
  - (e) Stain the specimens in eosin 10 to 30 s and quickly dip the slides nine times in 95% ethanol, then nine times in 100% ethanol.
  - (f) Dehydrate the specimens for 2 min in 100% ethanol, then 3 min in fresh 100% ethanol, followed by  $2 \times 2$  min in xylene.
  - (g) Place the slides flat and add a few drops of Permount™ to one end of the specimens and slowly overlay the specimens with a clean coverslip. Carefully remove excess Permount with 3MM Whatman paper filter strips.
  - (h) Seal the edges of the coverslip with melted wax or allow the slides to air-dry for 1 to 2 days.
  - (i) Observe and photograph the specimens using darkfield microscopy according to the manufacturer's instructions.

### Reagents needed

- *5× Labeling buffer*  
0.25 M Tris-HCl, pH 8.0  
25 mM  $\text{MgCl}_2$   
10 mM DTT, 1 mM HEPES buffer, pH 6.6  
26  $A_{260}$  units/ml random hexadeoxyribonucleotides
- *5× Transcription buffer*  
30 mM  $\text{MgCl}_2$   
0.2 M Tris-HCl, pH 7.5

- 10 mM spermidine  
50 mM NaCl
- *NTPs stock solutions*
    - 100 mM ATP in dd.H<sub>2</sub>O, pH 7.0
    - 10 mM GTP in dd.H<sub>2</sub>O, pH 7.0
    - 10 mM UTP in dd.H<sub>2</sub>O, pH 7.0
    - 10 mM CTP in dd.H<sub>2</sub>O, pH 7.0
  - *TE buffer (pH 8.0)*
    - 10 mM Tris-HCl
    - 1 mM EDTA
  - *Specimen blocking solution*
    - Warm an appropriate volume of PBS to 45°C, and then add 0.16% (w/v) DTT, 0.19% (w/v) iodoacetamide, and 0.13% (w/v) *N*-ethylmaleimide. Mix well and cover with aluminum foil before use.
    - Note: *This solution should be freshly prepared and used immediately. Because it contains toxic iodoacetamide and N-ethylmaleimide, gloves should be worn and caution should be taken.*
  - *PBS buffer*
    - 2.7 mM KCl
    - 1.5 mM KH<sub>2</sub>PO<sub>4</sub>
    - 136.9 mM NaCl
    - 15 mM Na<sub>2</sub>HPO<sub>4</sub>
    - Adjust the pH to 7.3
  - *20× SSC solution*
    - 0.3 M Na<sub>3</sub>Citrate (trisodium citric acid)
    - 3 M NaCl
    - Adjust the pH to 7.0 with HCl; autoclave
  - *50× Denhardt's solution*
    - 1% (w/v) Bovine serum albumin (BSA)
    - 1% (w/v) Ficoll (Type 400, Pharmacia)
    - 1% (w/v) Polyvinylpyrrolidone (PVP)
    - Dissolve well after each addition, adjust to the final volume with distilled water and sterile filter. Divide the solution into 50 ml aliquots and store at -20°C. Dilute 10-fold before use.
  - *Prehybridization solution*
    - 50% (v/v) Deionized formamide
    - 15 mM Tris-HCl, pH 8.0
    - 2 mM EDTA, pH 8.0
    - 2× SSC
    - 5× Denhardt's solution
    - 0.2% Denatured and sheared salmon sperm DNA for DNA hybridization or 0.2 mg/ml yeast tRNA and 0.2 mg/ml poly(A) for RNA hybridization.
  - *Hybridization cocktail*
    - Add [<sup>35</sup>S]dCTP- or [<sup>35</sup>S]UTP-labeled probe to an appropriate volume of fresh prehybridization solution.

- *Triethanolamine (TEA) buffer*  
100 mM TEA in dd.H<sub>2</sub>O, adjust the pH to 8.0.
- *Working emulsion solution*  
Thaw Kodak NTB-2 autoradiographic emulsion at 45°C and warm an equal volume of dd.H<sub>2</sub>O at the same temperature. Gently mix together Kodak NTB-2 solution and water, and wrap the container containing the working emulsion solution with aluminum foil prior to use.
- *Others*  
Developer  
Fixer  
Hematoxylin stain  
0.1% NH<sub>4</sub>OH (freshly prepared)  
Eosin stain  
*DNase* I (RNase-free)  
*RNase* I (DNase-free)  
SP6, or T7 or T3 RNA polymerase  
15 mg/ml yeast tRNA or poly(A) RNA as a carrier  
0.5 M Dithiothreitol (DTT)  
2 M NaCl solution  
7.5 M Ammonium acetate solution  
Ethanol (100%, 70%)  
TE-saturated phenol/chloroform  
Chloroform/isoamyl alcohol: 24:1 (v/v)  
Deionized formamide, ultrapure grade

### Troubleshooting Guide

1. *Individual sections fall apart during sectioning with no ribbons being formed.* Overfixation of tissues could have occurred. Try a shorter fixation time. An optimal fixation time should be determined.
2. *Sections crumble and are damaged during stretching.* Underfixation of tissues has occurred. Use a longer fixation time and determine the optimal time empirically.
3. *Sections have holes.* It is due to incomplete tissue dehydration and improper impregnation with wax. Perform complete dehydration of fixed tissues followed by thorough impregnation with melted paraffin wax.
4. *Holes occur in frozen sections.* Ice crystals are formed in the tissues during freezing or in the cryostat. Make sure to correctly freeze the tissue. Do not touch the frozen sections with fingers or relatively warm tools during mounting of the specimens in the microtome or during brushing the sections from the cutting knife.
5. *Sections are not of uniform thickness and/or have lines throughout.* The cutting surface of the specimen block is not parallel to the edge of the knife. The knife is dull. Take great care during mounting the specimens in the microtome and use a sharpened knife.

6. *Morphology of tissue is poorly preserved.* Tissues are stretched or shrunken. Make sure not to press or stretch the tissue during dissection and embedding.
7. *The specific activity of labeled probe is  $<10^5$  cpm/ $\mu$ g DNA or RNA.* [ $^{35}$ S] dCTP for DNA or [ $^{35}$ S]UTP for RNA has passed its half-life time. The activity of DNA or RNA polymerase is low or may be inhibited. Try to use fresh isotope and ensure that the labeling reaction is set up under the optimal conditions, including high quality of DNA.
8. *A low signal is evident.* Tissue is underdigested with protease. The specific activity of the enzyme is low. Determine the optimal digestion time of the specimens. Make sure that the probe is good.
9. *A high background occurs.* Tissue is overfixed. Protease digestion of the tissues is not sufficient. Set up a series of fixation times. Try to use an optimal digestion.
10. *A good signal is evident but poor morphology occurs.* Tissue overdigestion occurs. Counterstaining of the tissue is not sufficient. Tissue should be properly digested with an appropriate protease. Counterstain the sections slightly longer.

## REFERENCES

1. Berger, C. N. 1986. *In situ* hybridization of immunoglobulin-specific RNA in single cells of the  $\beta$ -lymphocyte lineage with radiolabeled DNA probes. *EMBO Journal* 5: 85–93.
2. Zeller, R., K. D. Bloch, B. S. Williams, R. J. Arceci, and C. E. Seidman. 1987. Localized expression of the atrial natriuretic factor gene during cardiac embryogenesis. *Genes & Development* 1: 693–698.
3. Brahic, M., and A. T. Haase. 1978. Detection of viral sequences of low reiteration frequency by *in situ* hybridization. *Proceedings of the National Academy of Sciences of the United States of America* 75: 6125–6129.
4. Lawrence, J. B., and R. H. Singer. 1985. Quantitative analysis of *in situ* hybridization methods for the detection of actin gene expression. *Nucleic Acids Research* 13: 1777–1799.
5. Singer, R. H., J. B. Lawrence, and C. Villnave. 1986. Optimization of *in situ* hybridization using isotopic and nonisotopic methods. *BioTechniques* 4: 230–250.
6. Trembleau, A., D. Roche, and A. Calas. 1993. Combination of non-radioactive and radioactive *in situ* hybridization with immunohistochemistry: A new method allowing the simultaneous detections of two mRNAs and one antigen in the same brain tissue section. *Journal of Histochemistry and Cytochemistry* 41: 489–498.
7. Zeller, R., S. Watkins, M. Rogers, J. H. M. Knoll, O. Bagasra, and J. Hanson. 1995. *In situ* hybridization and immunohistochemistry. In *Current Protocols in Molecular Biology*, ed. F. M. Ausubel, R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl, 14.0.3–14.8.24. New York, NY: John Wiley & Sons.





---

# 13 Localization of DNA or Abundance of mRNA by Fluorescence *in Situ* Hybridization

## 13.1 INTRODUCTION

Fluorescence *in situ* hybridization (FISH) is a method used for the detection of DNA or RNA of interest within cells.<sup>1-3</sup> The basic principle of FISH is that DNA or RNA in the prepared specimens is hybridized with a probe labeled nonisotopically with biotin or digoxigenin or a fluorescent dye. The hybridized signals are then detected by fluorescence or enzymatic methods using a fluorescence or light microscope. The detected signal and image can then be recorded on light-sensitive film. The striking feature of using a fluorescence probe is that the hybridized image can be readily analyzed using a powerful confocal microscope or an appropriate image analysis system with a CCD camera.

Compared with radioactivity *in situ* hybridization (RISH) (described in Chapter 12), FISH offers greater sensitivity than RISH. In addition to offering positional information, FISH makes it possible to obtain better morphology of cells or tissues. The major drawback for RISH is that it depends on the use of radioactive probes, which are well known as being toxic to human beings. To carry out RISH, one has to be very cautious in handling radioactive materials, including toxic waste disposal. In other words, one is under some “stress” while performing RISH. As a result, the nonradioactive approach such as FISH has become a widely used technique for the localization of a specific DNA or mRNA in a specific cell- or tissue type.<sup>2-9</sup>

This chapter offers detailed protocols for the FISH technology. There are similarities between FISH and RISH. In fact, many procedures are exactly the same. These identical procedures are not redescribed in this chapter but simply referred to in specific sections in Chapter 12. In general, techniques described for the use of *in situ* hybridization have been successfully used in our laboratories. Excellent results can be obtained once the optimal conditions are determined.

## 13.2 CELL OR TISSUE FIXATION, TISSUE EMBEDDING, SECTIONING, AND MOUNTING

These procedures are discussed in detail in Section 12.2 (Chapter 12).

### 13.3 DEWAXING OF SECTIONS, PROTEASE DIGESTION, AND DNase OR RNase TREATMENT OF SPECIMENS FOR *IN SITU* HYBRIDIZATION

These procedures are discussed in Section 12.3.

### 13.4 PREPARATION OF NONISOTOPIC PROBES USING ONE OF THE FOLLOWING METHODS, DEPENDING ON SPECIFIC PROBE AND DETECTION STRATEGIES

#### 13.4.1 METHOD A. RANDOM PRIMER DIGOXIGENIN LABELING OF dsDNA

The basic principle of biotin or digoxigenin labeling is that, in a random labeling reaction, random hexanucleotide primers anneal to denatured DNA template. A new strand of DNA complementary to template DNA is catalyzed by the Klenow enzyme. During the incorporation of four nucleotides, one of them is prelabeled by digoxigenin such as biotin-dUTP or DIG-dUTP. After hybridization of the probe with the target DNA or RNA sequence in specimen, an anti-digoxigenin antibody conjugated with an alkaline phosphatase will bind to the bound biotin-dUTP or digoxigenin-dUTP. The hybridized signal will then be detected using colorimetric substrates nitroblue tetrazolium (NBT) and 5-bromo-4-chloro-3-indolyl phosphate (BCIP) or X-Phosphate, which give a purple/blue color.

1. Add an appropriate amount of dsDNA of interest as a template into a microcentrifuge tube. Denature the DNA by boiling for 10 min and quickly chill the tube on ice for 4 min. Briefly spin down and place it on ice until use.
2. Set up a standard labeling reaction as follows:

Denatured DNA template (50 ng–10 µg)	5 µl
10× Hexanucleotide primers mixture	2.5 µl
10× dNTPs mixture	2.5 µl
dd.H <sub>2</sub> O to	13.5 µl
<u>Klenow enzyme (2 units/µl)</u>	<u>1.5 µl</u>
Total volume	25 µl

3. Incubate at 37°C for 2 to 12 h.

*Note: The amount of labeled DNA depends on the amount of DNA template and on the length of incubation at 37°C. Based on our experience, the longer the incubation within a 12-h period, the more DNA is labeled.*

4. After the labeling is complete, add 2.5 µl of 0.5 M EDTA solution to terminate the reaction.
5. Add 0.15 volumes of 3 M sodium acetate buffer (pH 5.2) and 2.5 volumes of chilled 100% ethanol to the mixture. Allow DNA to precipitate at –80°C for 1 h.
6. Centrifuge at 12,000 g for 6 min at room temperature, and carefully aspirate the supernatant. Briefly rinse the DNA pellet with 1 ml of 70% ethanol and dry the pellet under vacuum for 10 to 15 min.

7. Dissolve the labeled DNA in 50  $\mu$ l dd.H<sub>2</sub>O or TE buffer. Store at  $-20^{\circ}\text{C}$  until use.

Notes: (1) Labeled dsDNA must be denatured before it is used for hybridization. This can be done by boiling the DNA for 10 min then quickly chilling it on ice for 3 min. (2) After hybridization, the probe contained in the hybridization buffer can be stored at  $-20^{\circ}\text{C}$  and reused up to four times. (3) The yield of the labeled DNA can be estimated by dot blotting of serial dilutions of commercially labeled control DNA and labeled sample DNA on a nylon membrane filter. After hybridization and detection, the spot intensities of the control and the labeled DNA can be compared.

### 13.4.2 METHOD B. NICK TRANSLATION LABELING OF dsDNA WITH BIOTIN-11-dUTP OR DIGOXIGENIN-11-dUTP

Nick translation labeling is a widely used method for labeling DNA probes. The primary principle of nick translation labeling is that single-stranded nicks in dsDNA are first created by *DNase I*. *Escherichia coli* DNA polymerase I with 5' to 3' exonuclease activity removes stretches of ssDNA in the direction of 5'-3'. Almost simultaneously, the DNA polymerase I catalyzes the synthesis of a new strand DNA from 5'-3', in which a prelabeled deoxyribonucleotide such as DIG-11-dUTP or biotin-11-dUTP is incorporated into the new strand DNA, producing DNA probes.

1. Set up a labeling reaction mixture on ice as follows:

dsDNA template (2–10 $\mu$ g)	2–5 $\mu$ l
10 $\times$ biotin or DIG DNA labeling mixture	2.5 $\mu$ l
10 $\times$ reaction buffer	2.5 $\mu$ l
<i>DNase I</i> /DNA polymerase I mixture	2.5 $\mu$ l
Add dd-H <sub>2</sub> O to a final volume of	25 $\mu$ l

2. Incubate at  $15^{\circ}\text{C}$  for 70 min. Stop the reaction by adding 2.5  $\mu$ l of 0.4 M EDTA solution to the reaction and heating to  $65^{\circ}\text{C}$  for 10 min.
3. Precipitate and dissolve the labeled DNA as described in Method A (Section 13.4.1).

### 13.4.3 METHOD C. RIBOPROBE OR RNA LABELING

A cDNA of interest is cloned at the polycloning site between promoters SP6 and T7 or T3 of an appropriate plasmid or lambda vector. The cDNA can be transcribed *in vitro* into single-strand antisense RNA from a linear DNA template with promoters SP6, T7, or T3. During the process of *in vitro* transcription, one of the rNTPs, non-radioactively prelabeled as biotin-11-UTP or DIG-11-UTP, can be incorporated into the RNA strand, generating the labeled riboprobe. Compared with DNA labeling, a higher yield of RNA probe can be obtained because the template can be repeatedly transcribed. RNA probes can be easily purified from DNA template merely by treatment of *DNase I* (RNase-free) treatment. Riboprobes are now widely utilized for mRNA *in situ* hybridization.

1. Linearize plasmid DNA by an appropriate restriction enzyme for producing “runoff” transcripts.

- (a) Set up a plasmid linearization reaction as follows.

Recombinant plasmid DNA	10 µg
Appropriate restriction enzyme 10× buffer	2.5 µl
Acetylated BSA (1 mg/ml) (optional)	2.5 µl
<u>Appropriate restriction enzyme (10–20 u/µl)</u>	<u>10 units</u>
Add dd.H <sub>2</sub> O to a final volume of	25 µl

Note: *The recombinant plasmid DNA containing cDNA of interest should be digested with an appropriate restriction enzyme that cuts at one site that is very close to one end of the cDNA insert.*

- (b) Allow digestion to proceed for 2 h at the appropriate temperature, depending on the specific enzyme used.
- (c) Extract DNA by adding 1 volume of TE-saturated phenol/chloroform and mix well by vortexing. Centrifuge at 12,000 g for 5 min at room temperature.
- (d) Transfer the top, aqueous phase to a fresh tube and add 1 volume of chloroform/isoamyl alcohol (24:1) to the supernatant. Mix well and centrifuge as in step (c).
- (e) Carefully transfer the top, aqueous phase to a fresh tube.
- Note: *Phenol/chloroform extraction steps (c) to (e) can be replaced by simple filtration using a protein-binding filter (e.g., Millipore Corporation). Transfer the linearized mixture into a filter cup with a polyvinylidene difluoride membrane fixed at the bottom. Place the cup into a sterile microcentrifuge tube and centrifuge at 12,000 g for 30 s. Proteins are retained on the membrane but DNA in the supernatant is filtered to the bottom of the centrifuge tube. The filter cup can be discarded.*
- (f) Add 0.1 volume of 2 M NaCl solution (optional) and 2.5 volumes of chilled 100% ethanol to the supernatant. Precipitate the linearized DNA at –80°C for 30 min or at –20°C for 2 h.
- (g) Centrifuge at 12,000 g for 5 min, decant the supernatant, and briefly rinse the DNA pellet with 1 ml of 70% ethanol. Dry the pellet for 10 min under vacuum and dissolve the DNA in 10 µl dd.H<sub>2</sub>O.
2. Blunt the 3'-overhang ends of the DNA by the 3' to 5' exonuclease activity of Klenow DNA polymerase (optional).

Note: *It should be noted that enzymes such as KpnI, SacI, PstI, BglI, SacII, PvuI, Sfi, and SphI should not be utilized to linearize plasmid DNA for transcription in vitro.*

3. Perform *in vitro* transcription and labeling as follows:

- (a) Set up a reaction mixture on ice:

Purified and linearized plasmid DNA template containing the insert of interest	2 µg
10× NTP labeling mixture with biotin- or DIG-UTP	4 µl
10× transcription buffer	2.5 µl

RNA polymerase (T7, SP6, or T3)	4 $\mu$ l
Add DEPC-treated dd.H <sub>2</sub> O to a final volume of	25 $\mu$ l

- (b) Incubate at 37°C for 2 h.
- (c) To remove the DNA template, add 20 units of *DNase* I (RNase-free) and incubate at 37°C for 15 min. Inactivate *DNase* I by adding 4  $\mu$ l of 0.5 M EDTA solution.
- (d) Precipitate and dissolve the RNA probe as described in Method A (Section 13.4.1).

### Reagents needed

- *10 $\times$  Random hexanucleotide mixture*
  - 0.5 M Tris-HCl, pH 7.2
  - 1 mM Dithioerythritol (DTE)
  - 100 mM MgCl<sub>2</sub>
  - 2 mg/ml BSA
  - 62.5 A<sub>260</sub> units/ml of random hexanucleotides
- *10 $\times$  Labeling dNTP mixture*
  - 1 mM dATP
  - 1 mM dCTP
  - 1 mM dGTP
  - 0.60 mM dTTP
  - 0.35 mM biotin-dUTP or DIG-dUTP
  - pH 6.5
- *Klenow DNA polymerase I*
  - 2 units/ $\mu$ l, Labeling grade
- *10 $\times$  Reaction buffer*
  - 0.5 M Tris-HCl, pH 7.5
  - 0.1 M MgCl<sub>2</sub>
  - 10 mM DTE
- *DNase I/DNA polymerase I mixture*
  - 0.08 milliunits/ $\mu$ l *DNase* I/0.1 unit/ $\mu$ l DNA polymerase I in 50 mM Tris-HCl, pH 7.5, 10 mM MgCl<sub>2</sub>, 1 mM DTE, and 50% (v/v) glycerol.
- *TE buffer*
  - 10 mM Tris-HCL, pH 8.0
  - 1 mM EDTA
- *3 M sodium acetate buffer, pH 5.2*
- *Ethanol (100%, 70%)*
- *10 $\times$  Transcription buffer*
  - 0.4 M Tris-HCl, pH 8.0
  - 100 mM DTT
  - 60 mM MgCl<sub>2</sub>
  - 20 mM spermidine
  - 0.1 M NaCl
  - 1 unit of RNase inhibitor

- *10× NTP Labeling mixture*
  - 0.1 M Tris–HCl, pH 7.5
  - 10 mM ATP
  - 10 mM CTP
  - 10 mM GTP
  - 6.5 mM UTP
  - 3.5 mM biotin–UTP or DIG–UTP
- *Diethylpyrocarbonate (DEPC)-treated water*
  - 0.1% DEPC in dd.H<sub>2</sub>O. Incubate at 37°C overnight followed by autoclaving.
- *EDTA solution*
  - 0.5 EDTA in dd.H<sub>2</sub>O, pH 8.0
- *RNA polymerase*
  - 20 units/μl of T7, or SP6, or T3

### 13.5 *IN SITU* HYBRIDIZATION OF SPECIMENS

After treatment of specimens with DNase or RNase and preparation of specific probes are complete, one can proceed to *in situ* hybridization. In general, the procedure for DNA hybridization is similar to that of RNA hybridization except for differences indicated at specific steps.

1. Carry out prehybridization as follows:
  - (a) Carefully overlay tissue specimens with an appropriate volume of prehybridization solution (15 to 20 μl/10 mm<sup>2</sup>) using the tip of a pipette or a plastic coverslip cut slightly larger than tissue section.
  - (b) Place the slides in a moist chamber and allow prehybridization to proceed for 1 h at 37°C.
  - (c) During prehybridization, prepare hybridization cocktail (see “Reagents needed”).
  - (d) After prehybridization is complete, carefully remove the prehybridization solution from the slides with a 3MM Whatman paper strip or the tip of a pipette.
2. Perform hybridization and washing as follows:
  - (a) Immediately overlay each specimen with freshly prepared hybridization cocktail containing the specific probe (15 to 20 μl/10 mm<sup>2</sup>). Cover the cocktail with a plastic coverslip cut slightly larger than the tissue section.
  - (b) Simultaneously denature both probe and target DNA or RNA by placing the slides on a hot plate or an equivalent for 3 to 4 min at 95 to 100°C for DNA hybridization or at 55 to 65°C for RNA hybridization.
 

Notes: (1) DNA or RNA in the specimens can be denatured before prehybridization. (2) Labeled probes can be denatured immediately before preparation of hybridization cocktail. (3) The concentration of probe is critical for the success of *in situ* hybridization using a nonradioactive probe. A concentration of 2 μg/ml DNA probe or 1 μg/ml RNA probe is

- recommended. The efficiency of RNA probes is higher than that of DNA probes because some of the denatured ssDNA probes can be renatured to dsDNA under hybridization conditions. If a high background occurs, the concentration of the probe can be reduced 5- to 10-fold.*
- (c) Quickly place the slides in a high humidity chamber and carry out hybridization 37°C for 2 to 4 h.
- Notes: (1) Any bubbles underneath the plastic coverslips should be removed by gently pressing the coverslip or by using a toothpick. (2) To prevent uneven hybridization, slides should be kept level in the chamber. (3) The humidity chamber must be tightly covered or sealed before being placed in a hybridization oven or an equivalent. If the specimens are dried during hybridization, a high background will occur. (4) The relatively high concentration of formamide (50%) and low salt concentration (e.g., 2× SSC) in the hybridization cocktail solution are essential and have two functions in general. One is to facilitate denaturing of target DNA or RNA and probe at 100°C, about 35 to 40°C above the  $T_m$  of homologous hybridized DNA. The other is to prevent potentially nonspecific binding of the probe while not interfering with probe-target annealing at 100°C. (5) Inasmuch as RNA–RNA hybrids have a relatively higher  $T_m$  than DNA–DNA hybrids, it is recommended that, before hybridization, both RNA probe and the target RNA be heated at 65 to 70°C to denature any secondary structure in RNA molecules. In addition, hybridization temperature should be set up at 45 to 50°C for RNA–mRNA *in situ* hybridization, and 40 to 45°C for DNA–RNA *in situ* hybridization.
- (d) After hybridization, quickly place slides in a slide rack and insert the rack into a staining dish filled with washing solution containing 2× SSC and 2.5% BSA. Wash the slides with three changes of fresh washing solution, 15 min each at 45°C with gentle shaking.
- (e) Continue to wash the slides twice, 5 min each time, in fresh washing solution containing 0.2× SSC, 2.5% BSA, and 0.05% Tween 20 in PBS at room temperature with gentle shaking.
- Note: *Do not allow the specimens to become dry before detection. At this stage, unhybridized RNA of the tissue specimens can be removed using an appropriate amount of RNase (DNase free) or a mixture containing 45 µg/ml RNase A, 2 µg/ml RNase T1 (Sigma Chemicals), 5 mM EDTA, and 250 mM NaCl in TE buffer, pH 7.5. RNase treatment could enhance the signal-to-noise ratio, reducing the background.*

### 13.6 ENZYMATIC DETECTION OF HYBRIDIZED SIGNALS USING COLORIMETRIC SUBSTRATES NBT AND BCIP

1. Overlay the specimens with an appropriate volume of streptavidin–alkaline phosphatase (AP) conjugate solution (for biotin probes) or anti-DIG–alkaline phosphatase solution (for DIG probes) at an appropriate dilution.
2. Place the slides in an aluminum foil-wrapped high humidity chamber and incubate for 20 to 30 min at 37°C or 1 h at room temperature.

3. Carefully remove the solution from the specimens and carry out washing in PBS containing 0.05% Tween-20 in a slide dish for  $3 \times 5$  min at  $42^{\circ}\text{C}$  with gentle agitation.
4. Place the slides in a slide rack and wash the slides in an appropriate volume of enzymatic predetection solution for 2.5 min.
5. Replace predetection solution with fresh enzymatic detection solution containing NBT and BCIP as substrates.
6. Place the slides in a container and wrap the container with aluminum foil. Allow color to develop at room temperature for 20 to 120 min. Check results once every 4 min under a microscope.  
*Note: Color development should be time controlled. Overdevelopment may lead to higher background. For this reason, it is recommended to stop the color development as soon as the primary color becomes visible, assuming that the probe-target binding that results in the strongest signal is the primary color.*
7. Wash the slides in PBS for  $3 \times 3$  min and counterstain the specimens in nuclear fast red solution for 5 min if desired.  
*Note: Nuclear staining is omitted for RNA-RNA in situ hybridization if the specimens are pretreated with DNase I.*
8. Partially dry the slides and mount the specimens with glass coverslips using Permount<sup>TM</sup>.
9. View and photograph with a phase-contrast microscope.

### 13.7 FLUORESCENCE DETECTION OF HYBRIDIZED SIGNALS

1. Following step (e) in Section 13.5, carefully drain excess washing solution from the specimens but do not air-dry the slides.
2. According to a specific fluorescent probe used in hybridization, add biotin detection solution or a biotin/digoxigenin detection solution onto the hybridized slide ( $30 \mu\text{l}/\text{specimen}$ ). Cover the solution with a piece of Parafilm cut slightly larger than the specimen.
3. Place the slides in a container and wrap the container with aluminum foil. Place the wrapped container in a moist chamber at  $37^{\circ}\text{C}$  for 50 min.
4. Wash the slides in  $2\times$  SSC in a dark place for  $2 \times 10$  min.
5. If desired, carry out counterstaining of nuclear DNA by adding 4',6-diamidino-2-phenylindole (DAPI) staining solution onto the slides ( $30 \mu\text{l}/\text{specimen}$ ). Cover the solution with a piece of Parafilm cut slightly larger than the specimen.
6. Allow staining to occur for 5 min at room temperature and briefly rinse the specimens in  $2\times$  SSC.
7. View and photograph the specimens using a fluorescence microscope with an appropriate filter.

*Note: EKtar-1000 and Ektachrome-400 color films are recommended for prints and slides, respectively. Kodak Technical Pan 2415 film can be used for black and white prints. If dual- or triple-band pass filter sets*



are utilized, the exposure time may be set at 20 to 100 and 2 to 10 s, respectively.

### Reagents needed

- *20× SSC solution*
  - 0.3 M Na<sub>3</sub>citrate (trisodium citric acid)
  - 3 M NaCl
  - Adjust the pH to 7.0 with HCl. Autoclave.
- *Prehybridization solution*
  - 50% (v/v) Deionized formamide
  - 15 mM Tris-HCl, pH 8.0
  - 2 mM EDTA, pH 8.0
  - 2 mg/ml BSA (nuclease-free)
  - 20% (w/v) Dextran sulfate (mol. wt. 500,000)
  - 2× SSC
- *Hybridization cocktail*
  - Add an appropriate amount of nonradioactively labeled probes to an appropriate volume of fresh prehybridization solution.
- *Enzymatic predetection solution*
  - 100 mM Tris-HCl, pH 9.5
  - 100 mM NaCl
  - 50 mM MgCl<sub>2</sub> (freshly added)
- *PBS buffer*
  - 2.7 mM KCl
  - 1.5 mM KH<sub>2</sub>PO<sub>4</sub>
  - 136.9 mM NaCl
  - 15 mM Na<sub>2</sub>HPO<sub>4</sub>
  - Adjust the pH to 7.3.
- *NBT stock solution*
  - 75 mg/ml in dimethylformamide
  - Dissolve well and store in a dark place.
- *BCIP stock solution*
  - 50 mg/ml in dimethylformamide
  - Dissolve well and store in a dark place.
- *Enzymatic detection solution containing NBT/BCIP*
  - 100 mM Tris-HCl, pH 9.5
  - 100 mM NaCl
  - 50 mM MgCl<sub>2</sub> (freshly added)
  - 330 µg/ml of NBT (freshly diluted from NBT stock solution)
  - 170 µg/ml of BCIP (freshly diluted from NBT stock solution)
- *Streptavidin-alkaline phosphatase conjugate solution*
  - 1% (w/v) BSA (nuclease-free)
  - 0.05% (v/v) Tween 20
  - 3.5 µg/ml Streptavidin-alkaline phosphatase conjugate (freshly added)
  - Dissolve well after each addition in PBS.

- *DAPI stock solution*  
Dissolve 0.1 mg/ml of DAPI in distilled water containing 4 µg/ml methanol. Store the stock solution in an aluminum-wrapped tube at -20°C up to 1 year.
- *DAPI staining solution*  
Freshly dilute DAPI stock solution for 1000× in PBS and store in a dark place before use.
- *Biotin detection solution*  
Dilute fresh rhodamine-avidin D or fluorescein-avidin DCS to final concentration of 2 µg/ml in 2× SSC containing 1% (w/v) BSA.
- *Biotin/digoxigenin detection solution*  
Freshly dilute fluorescein-avidin DCS and rhodamine-conjugated Fab fragment of sheep anti-digoxigenin to final concentration of 2 µg/ml each in 2× SSC containing 1% (w/v) BSA.

### Troubleshooting Guide

1. *Individual sections fall apart during sectioning with no ribbons being formed.* Overfixation of tissues could have occurred. Try a shorter fixation time. An optimal fixation time should be determined.
2. *Sections crumble and are damaged during stretching.* Underfixation of tissues has occurred. Use a longer fixation time and determine the optimal time empirically.
3. *Sections have holes.* This is due to incomplete tissue dehydration and improper impregnation with wax. Perform complete dehydration of fixed tissues followed by thorough impregnation with melted paraffin wax.
4. *Holes occur in frozen sections.* Ice crystals are formed in the tissues during freezing or in the cryostat. Make sure to correctly freeze the tissue. Do not touch the frozen sections with fingers or relatively warm tools during mounting of the specimens in the microtome or during brushing the sections from the cutting knife.
5. *Sections are not of uniform thickness and/or have lines throughout.* The cutting surface of the specimen block is not parallel to the edge of the knife. The knife is dull. Take great care during mounting the specimens in the microtome and use a sharpened knife.
6. *Morphology of tissue is poorly preserved.* Tissues are stretched or shrunk. Make sure not to press or stretch the tissue during dissection and embedding.
7. *No hybridization signal is shown in the specimens.* Probes and/or target DNA or RNA sequences are not really denatured before hybridization. Make sure to completely denature both the probe and the target DNA or RNA in the specimens.
8. *The intensity of the fluorescence signal in specimens is too bright with a low signal-to-noise ratio.* The amount of fluorescein probes and/or biotin- or digoxigenin-detection solution is overloaded. Overhybridization thus occurs.

Try to reduce the probe and detection solutions to 5- to 10-fold. Control the hybridization time to 2 to 4 h.

9. A high background is shown in enzymatic detection sections. Inasmuch as color can be seen everywhere in specimens, it is difficult to tell which signal is the correct signal. Color development goes for too long or the specimens may be partially or completely dried during hybridization and/or washing procedures. Try to monitor color development once every 3 to 4 min and terminate color formation as soon as the primary color signal appears. Probe-target sequence binding should reveal first visible color before potential background develops later on. Make sure not to allow specimens to become dry.

## REFERENCES

1. Berger, C. N. 1986. *In situ* hybridization of immunoglobulin-specific RNA in single cells of the  $\beta$ -lymphocyte lineage with radiolabeled DNA probes. *EMBO Journal* 5: 85–93.
2. Zeller, R., K. D. Bloch, B. S. Williams, R. J. Arceci, and C. E. Seidman. 1987. Localized expression of the atrial natriuretic factor gene during cardiac embryogenesis. *Genes & Development* 1: 693–698.
3. Brahic, M., and A. T. Haase. 1978. Detection of viral sequences of low reiteration frequency by *in situ* hybridization. *Proceedings of the National Academy of Sciences of the United States of America* 75: 6125–6129.
4. Lawrence, J. B., and R. H. Singer. 1985. Quantitative analysis of *in situ* hybridization methods for the detection of actin gene expression. *Nucleic Acids Research* 13: 1777–1799.
5. Singer, R. H., J. B. Lawrence, and C. Villnave. 1986. Optimization of *in situ* hybridization using isotopic and nonisotopic methods. *BioTechniques* 4: 230–250.
6. Lichter, P., A. L. Boyle, T. Cremer, and D. D. Ward. 1991. Analysis of genes and chromosomes by nonisotopic *in situ* hybridization. *Genetic Analysis Techniques and Applications* 8: 24–35, 1991.
7. Speel, E. J. M., B. Schutte, J. Wiegant, F. C. Ramaekers, and A. H. N. Hopman. 1992. A novel fluorescence detection method for *in situ* hybridization, based on the alkaline phosphatase-fast red reaction. *Journal of Histochemistry and Cytochemistry* 40: 1299–1308.
8. Trembleau, A., D. Roche, and A. Calas. 1993. Combination of non-radioactive and radioactive *in situ* hybridization with immunohistochemistry: A new method allowing the simultaneous detection of two mRNAs and one antigen in the same brain tissue section. *Journal of Histochemistry and Cytochemistry* 41: 489–498.
9. Zeller, R., S. Watkins, M. Rogers, J. H. M. Knoll, O. Bagasra, and J. Hanson. 1995. *In situ* hybridization and immunohistochemistry. In *Current Protocols in Molecular Biology*, ed. F. M. Ausubel, R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl, 14.0.3–14.8.24. New York, NY: John Wiley & Sons.



---

# 14 *In Situ* PCR Hybridization of Low Copy Genes and *in Situ* RT-PCR Detection of Low Abundance mRNAs

## 14.1 INTRODUCTION

Simultaneous detection and localization of DNA or RNA by *in situ* hybridization have been demonstrated in recent years.<sup>1-3</sup> As described in Chapters 12 and 13, the power of *in situ* hybridization allows the DNA or RNA of interest to be detected in intact cells or specific tissues. Unfortunately, this technique has a sensitivity limitation. In fact, it merely works well for analysis of high abundance nucleic acids, but can hardly detect low copy gene/DNA or low abundance RNA. In general, traditional Southern or northern blot hybridization also does not detect low abundance nucleic acids. To overcome this limitation, *in situ* polymerase chain reaction (PCR) and *in situ* reverse transcription (RT)-PCR methods have been developed for the detection of low copy genes/DNAs and low abundance mRNAs, respectively.<sup>4-6</sup> These technologies are a virtual combination of PCR and *in situ* hybridization, which have become very powerful tools and are widely used in many disciplines.<sup>3-12</sup>

Clearly, there is a major difference between *in situ* PCR and regular solution PCR, even though the basic mechanism of DNA amplification is similar. Solution PCR is carried out in a tube and requires extraction of DNA/RNA from cells or tissues to be tested. As a result, one cannot correlate PCR data with the histological or pathological features of the sample being examined. In contrast, *in situ* PCR can directly amplify target DNA sequences within intact cells or specimens, which enables one to know exactly what particular cell- or tissue type contains the amplified DNA or cDNA. With *in situ* PCR hybridization techniques, a virus infection or a few copies of mRNA can be rapidly detected and localized.

The primary principles of *in situ* PCR hybridization are that low copy DNA or RNA is first amplified within intact cells by the extremely sensitive PCR, and that the amplified signals are then readily detected after regular *in situ* hybridization using a specific probe. With regard to *in situ* RT-PCR hybridization, the basic difference is that mRNA is reversely transcribed into cDNA before proceeding with PCR amplification using specific primers. It is important to realize how PCR products are

precisely retained inside the cells with little or no diffusion. It has been speculated that the trapping of amplified DNA or cDNA in cellular compartments depends on the fixative used for fixation.<sup>7-8</sup> Perhaps both ethanol and acetone fixation cannot induce cross-linking between proteins and nucleic acids, resulting in migration of PCR products out of cells. Formalin (i.e., formaldehyde), however, can extensively polymerize proteins and cross-link nucleic acids. Following appropriate formalin fixation, a “barrier” may be created to prevent the amplified products from migrating out of the cell. In addition, there is a possibility that the positively charged amino acids contained in the fixed protein meshwork may interact with the negatively charged PCR products, which inhibit the amplified DNA or cDNA from diffusion from its sites of origin. Nonetheless, not 100% of PCR products can remain in their original sites.<sup>3,6,8-16</sup>

This chapter describes protocols for successful *in situ* PCR hybridization. It consists of three parts: *in situ* PCR hybridization, *in situ* RT-PCR hybridization, and direct *in situ* PCR with incorporation of DIG-11-dUTP or biotinylated-dUTP. The methods covered here are improved or modified from previous methodologies. All procedures have been well tested and work successfully in our laboratories.

## 14.2 DETECTION OF A LOW COPY GENE BY *IN SITU* PCR HYBRIDIZATION

As outlined in Figure 14.1, the general procedures include design of primers; cell/tissue fixation; tissue embedding, sectioning, and mounting on slides; protease digestion; RNase treatment; *in situ* PCR amplification and *in situ* hybridization and detection.




FIGURE 14.1 Scheme of *in situ* PCR hybridization of DNA.

### 14.2.1 DESIGN OF SPECIFIC PRIMERS FOR *IN SITU* PCR AMPLIFICATION OF TARGET DNA SEQUENCES

Like solution PCR in a tube, the design of primers is essential for the success of *in situ* PCR in cells or tissues. The length,  $T_m$  value, GC content, and specificity of the primers mandate careful planning and analysis. The DNA sequences to be amplified can be determined by searching for appropriate publications or databases from GenBank. To amplify a target DNA sequence, two primers should be designed and synthesized: the sense or forward primer and the antisense or reverse primer. The primers are designed so that one is complementary to each strand of the DNA double helix and are located at opposite sides of the region to be amplified. In other words, forward primer directs the synthesis of a DNA strand toward the reverse primer, and vice versa, generating double-stranded DNA flanked by the two primers (Figure 14.2).

The authors routinely use a computer program Oligo™ Version 4.0 or Cprimer f (Internet) to design and analyze oligonucleotide primers for amplification of partial- and full-length HSP27 cDNA. The major advantages of these programs are as follows: (1) they allow a search for the most suitable regions in the target DNA sequences for the design of primers; (2) verify the specificity of the primers; (3) display the AT and GC contents and  $T_m$  values of the primers; and (4) allow checking for potential intrahairpin structure and interstrand base pairing of the primers (Figure 14.3).

In our experience, the following points should be noted when designing primers for *in situ* PCR and *in situ* RT-PCR.

- DNA target length to be amplified should be a relatively small fragment (0.3 to 2.0 kb). Although some new *Taq* polymerases such as the Expand™ PCR System (Boehringer Mannheim Corporation) enables DNA > 10 kb to be amplified, it is suitable for solution PCR in a tube but not desirable for *in situ* PCR. Often, the larger the fragment to be amplified, the greater the potential to create artifacts of PCR products.
- The length for both forward/sense and reverse/antisense primers should be 17- to 25-mer or bases. Primers less than 14-mer may have a low efficiency




FIGURE 14.2 Diagram of DNA amplification by PCR.




FIGURE 14.3 Scheme of *in situ* RT-PCR.

of annealing to template or they may cause failure of PCR amplification. On the other hand, primers > 30-mer in length may bring about nonspecific annealing to templates, resulting in unexpected PCR products.

- The GC content of a primer should be 45% to 58%. A primer with GC rich (>60%) will significantly increase the  $T_m$  value of the primer, which will affect the annealing temperature.
- To facilitate complementary-strand annealing between the primer and the DNA template, a primer should be designed so that it contains two to three GC-type bases at its 3' end and one G or C base at its 5' end. Bases C and G have three hydrogen bonds compared with A or T that contain two hydrogen bonds.
- Perhaps the most critical caution when designing primers is whether an intrastrand hairpin structure or interstrand complementary base pairs will be formed. According to the computer programs Oligo Version 4.0 and CPrimer f (Internet) and based on the author's experience, no more than three intraprimer base pairs or no more than four interprimer base pairs are allowed. In particular, the 3' ends of forward and reverse primers must not be complementary to each other. Any intraprimer secondary structures or primer-primer dimers will cause a failure in the annealing between primers and DNA templates. In this case, there will be no PCR products. Therefore, it is absolutely important to design primers that contain no secondary structures and no interstrand primer-dimers.
- In general, the melting temperature or  $T_m$  of a primer should be <68°C. Primers with  $T_m > 75^\circ\text{C}$  are usually difficult to anneal to a DNA template or they are difficult to melt once secondary structures are formed. If the



computer program CPrimer f or Oligo Version 4.0 or Cprimer f is used, the  $T_m$  of primers can be calculated and displayed by the programs. If the programs are not available, one can estimate the  $T_m$  by the formula:

$$T_m \text{ of a primer} = (2^\circ\text{C} \times \text{AT bases}) + (4^\circ\text{C} \times \text{GC bases})$$

More accurately, one can consider the salt concentration when calculating  $T_m$  using the following formula:

$$T_m \text{ of a primer} = 81.5^\circ\text{C} + 16.6 (\log M) + 0.41(\%GC) - 500/n$$

where  $T_m$  is the melting temperature of the primer,  $M$  is the molarity of the salt in the buffer, and  $n$  is the length of the primer.

### 14.2.2 SYNTHESIS AND TESTING OF THE DESIGNED PRIMERS

Once specific primers have been properly designed, they can be synthesized by an appropriate DNA oligonucleotide synthesizer. Purification of the primers is optional. We routinely use synthesized primers and successfully obtain PCR products. At this point, it may be assumed that the primers can be directly applied to *in situ* PCR. To ensure the quality of primers, however, the authors strongly recommend that the designed primers be tested for the specificity and integrity of PCR products simultaneously or before *in situ* PCR. The testing can be done by regular solution PCR in a tube using genomic DNA from the cells/tissues to be used for *in situ* PCR. The PCR products should be analyzed by agarose gel electrophoresis. A good pair of primers should generate one band with an expected size. No bands or multiple bands with unexpected sizes indicate that the designed primers are not suitable for *in situ* PCR, which should be redesigned and synthesized. In our laboratories, even though the expected PCR products are obtained, we sometimes partially or completely sequence the PCR products to make sure that the right target sequences have been amplified. Inasmuch as nonspecific or mispairing of primers is a commonly potential phenomenon, PCR products with any artifacts will cause misinterpretation of PCR results. Once the quality of primers and the integrity of PCR products have been verified, one can proceed to *in situ* PCR.

### 14.2.3 CARRYING OUT FIXATION OF CELLS OR TISSUES, TISSUE EMBEDDING, SECTIONING, AND MOUNTING OF SECTIONS ON SLIDES

These activities are discussed in Section 12.2.

*Note: For in situ PCR hybridization, three separate drops of cell suspension or tissue sections should be placed on the same slide. One drop of cells or tissue section will be subjected to DNase and RNase digestion before in situ PCR. After in situ PCR hybridization, this will serve as a negative control because all cells should show no PCR products. Another section or a drop of cells will not be subjected to DNase and RNase treatment. This will serve as a positive control because all cells should have PCR products and hybridization signals. The third drop of cells or*

section will serve as a target-specific test, which will be digested with RNase but not with DNase.

#### 14.2.4 DEWAXING OF SECTIONS (IF NECESSARY), PROTEASE DIGESTION, AND DNASE OR RNASE TREATMENT OF SPECIMENS

These procedures are discussed in Section 12.3.

#### 14.2.5 PREPARATION OF RADIOACTIVE PROBES FOR RISH OR NONRADIOACTIVE PROBES FOR FISH

Preparation of radioactive probes for RISH is described in Section 12.3.5, and that of nonradioactive probes for FISH is described in Section 13.4.

#### 14.2.6 PERFORMANCE OF *IN SITU* PCR

1. Prepare an appropriate volume of PCR reaction cocktail mixture (50  $\mu$ l per section). The following cocktail is a total of 500  $\mu$ l for 10 sections.

10 $\times$ Amplification buffer with MgCl <sub>2</sub>	50 $\mu$ l
Mixture of four dNTPs (2.5 mM each)	50 $\mu$ l
Sense or forward primer (20 $\mu$ M in dd.H <sub>2</sub> O)	25 $\mu$ l
Antisense or reverse primer (20 $\mu$ M in dd.H <sub>2</sub> O)	25 $\mu$ l
<i>Taq</i> DNA polymerase	50 units
Add dd.H <sub>2</sub> O to final volume	500 $\mu$ l

Note: *PCR kits containing 10 $\times$  amplification buffer, dNTPs, and Taq polymerase are available from Boehringer Mannheim and Perkin-Elmer Corporation. MgCl<sub>2</sub> concentration plays a role in the success of PCR amplification, which should be adjusted accordingly. In our experience, 4.0 to 4.5 mM MgCl<sub>2</sub> is an optimal concentration to obtain an intense signal.*

2. Add the PCR cocktail to the slides prepared at step 4 (50  $\mu$ l/section). Carefully cover each slide and overlay cells or tissue sections with the cocktail using an appropriate size of coverslip. If necessary, add mineral oil to seal all the edges of the coverslip to prevent evaporation during the PCR process.

Note: *The assembly of slides for in situ PCR varies with the specific instrument. The procedures should be carried out according to the manufacturer's instructions. We use GeneAmp In Situ PCR System 1000 (Perkin-Elmer Corporation) that can simultaneously carry out 10 slides for in situ PCR without using mineral oil. Brief instructions for assembly of slides in the order shown below are as follows:*

- Place the slides with cells or tissue sections on the platform of the Assembly Tool.
- Fully expand the Amplicover Clip and put it against a magnetic holder in the arm of the Assembly Tool provided.

- Place the AmpliCover Disc in the Clip and add the PCR cocktail to the center of the cell sample or tissue section on a glass slide (50  $\mu$ l/section). Note: *To prevent formation of bubbles, the cocktail should be placed in a single drop instead of being evenly distributed on the whole cell sample or tissue section. In addition, do not touch the cells or tissue section with a pipette tip when loading the PCR cocktail so as to avoid any damage to the tissue sections.*
  - Place the arm down and turn the knob and simultaneously clamp the AmpliCover Clip onto the slide according to the instructions. Note: *The cells or tissue sections overlaid with the PCR cocktail should now be completely sealed. To eliminate mispriming between primers and DNA template, we recommend that one use a hot-start approach at 70°C. The cocktail should not be added onto the sections until a slide temperature of 70°C has been reached. Briefly preheat the assembly tool to 70°C. Place the slide with sections on the tool for about 1 min before adding the PCR cocktail to the tissue sections, or one may not add Taq polymerase into the PCR cocktail. After the cells or tissue sections on slides are overlaid with the PCR cocktail (about 2/3 of the total volume) lacking Taq polymerase, ramp to 70°C or 3 to 5°C above the  $T_m$  of primers, quickly add an appropriate amount of Taq polymerase diluted in dd.H<sub>2</sub>O (about 1/3 of the total volume) onto the sample and assemble the slides for in situ PCR according to the instructions.*
  - Load the assembled slides, one by one, into the slide block of the GeneAmp In Situ PCR System 1000<sup>R</sup>.
3. Perform 25 cycles of PCR amplification as follows, which should be preprogrammed according to the manufacturer's instructions.

Cycle	Denaturation	Annealing	Extension
First	94°C, 3.5 min	55°C, 2 min	72°C, 2.5 min
2–24	94°C, 1 min	55°C, 2 min	72°C, 2.5 min
25	94°C, 1 min	55°C, 2 min	72°C, 7.0 min

For the final step, hold at 4°C until the slides are removed.

Tips: (1) *This PCR profile may be appropriately adjusted according to specific primer conditions. The annealing temperature should be approximately 2°C above the  $T_m$  of the primers. Annealing of primers and DNA template at a temperature too far below the  $T_m$  will generate unexpected PCR products due to false priming. However, annealing at a temperature too far above the  $T_m$  may cause no priming and no results.*

(2) *Special tips are recommended for a high fidelity of amplification of large DNA fragments (8 to 25 kb). Primers with at least 30 bases or 30-mer in length should be designed. High quality of Taq polymerase with proof-reading capability should be utilized, which is commercially available. The PCR profile should be programmed as follows:*

Cycle	Denaturation	Annealing	Extension
First	94°C, 3.5 min	60°C, 1 min	70°C, 4.5 min
2–24	94°C, 40 s	60°C, 1 min	70°C, 4.5 min with an additional extension of 10 s per cycle
25	94°C, 40 s	60°C, 1 min	70°C, 15 min

*For the final step, hold at 4°C until the slides are removed.*

*To avoid mispriming and/or artifacts such as base misreading/miscomplementing, it is strongly recommended that primers be 17 to 24 bases, and that the DNA length to be amplified should not be longer than 2.0 kb. In my experience, amplification of large DNA molecules is not necessary with regard to in situ PCR or RT-PCR.*

*(3) One should also pay attention to the correct linking between each of files or cycles before performing in situ RT-PCR of cell samples or tissue sections, particularly when using a new PCR instrument such as GeneAmp In Situ PCR System 1000 (Perkin-Elmer Corporation). It is extremely important to check through each smooth linking between each of the files before using samples. The easiest way is to program the instrument for testing as follows:*

Cycle	Denaturation	Annealing	Extension
First	94°C, 5 s	60°C, 6 s	70°C, 7 s
2–4	94°C, 5 s	60°C, 6 s	70°C, 7 s
5	94°C, 5 s	60°C, 6 s	70°C, 10 s

*Final step, hold at 4°C.*

*Once programming has been completed, the running mode can be tested. If each step is linked smoothly, the system should work fine with actual samples. Hence, one may start to program the instrument at the appropriate temperatures and cycles. In GeneAmp In Situ PCR System 1000 (Perkin-Elmer Corporation), there are four files for programming. We usually utilize File 1 and File 4. File 1 is a soaking file used for setting up a temperature for a specified period or indefinitely. File 4 is for programming at different temperatures, incubation times, and cycles. For hot-start, we routinely use File 1 to set up a temperature at 70°C without specifying a time so that this soaking temperature can be terminated once all the slides have been placed inside the instrument. One can program a soaking file by turning on the instrument, pressing **File**, pressing 1, and then pressing **Enter**. Next is to press **Step** to edit the file: set up a temperature (e.g., 70°C) followed by pressing 0 for other temperatures or time parameters except to store the file by giving a specific number and remembering that number. If one wishes to specify a soaking time (e.g., 5 min), the user can automatically link the soaking file number to the first file number (e.g., File 10) programmed for PCR. If the soaking file is not linked to any file numbers, one can simply terminate the soaking file by quickly pressing **Stop** twice, pressing **File**, pressing the first file number (e.g., 10), pressing **Enter**, and then pressing **Cycle** to start running PCR of samples.*

Now, let us program files for PCR with **Bold Font Style** according to the order shown below. Remember that if Link File number is N, the Store File number should be assigned as N-1. Let us assign the first file number to be stored as 10. For instance, if we wish to set up 70°C, 5 min for hot-start, 94°C, 3 min for the first denaturation temperature and time, 24 cycles of 94°C, 40 s (denaturation), 55°C, 1 min (annealing), 72°C, 2 min (extension), and 4°C hold until the samples are taken out from the instrument, we can program and link file number as **10→11→12→13→14**. For running, one simply presses **File→10→Enter→Cycle**.

Step 1. Press **File→4→Enter→Step** to edit file→**70°C, 5 min→0** to other temperature and time parameters→Cycle number? **1** No extension→Link to file? **11→Run-Store-Print? Store→Enter→store file number? 10→Enter**.

Step 2. Press **File→4→Enter→Step** to edit file→**94°C, 3 min** for the first temperature and time in Seg. 1→**0** to other temperature and time parameters→**No extension→1** for cycle number→Link to file number? **12→Enter→Run-Store-Print? Store→Enter→Store file number? 11→Enter**.

Step 3. Press **File→4→Enter→Step** to edit file→**94, 40 s** for the first temperature and time in Seg. 1→**55°C, 1 min** for Seg. 2→**72°C, 2 min→0** to other temperature and time parameters→**No extension→24** for cycle numbers→link to file number? **13→Enter→Run-Store-Print? Store→Enter→store file number? 12→Enter**.

Step 4. Press **File→4→Enter→Step** to edit file→**72°C, 7 min** for the first temperature and time in Seg. 1→**0** to other temperature and time parameters→**No extension→1** for cycle number→link to file number? **14→Enter→Run-Store-Print? Store→Enter→store file number? 13→Enter**.

Step 5. Press **File→1→Enter→Step** to edit file→**4°C→0** to other temperature and time parameters→**Run-Store-Print? Store→Enter→store file number? 14→Enter**.

4. After PCR amplification has been completed, remove the clips and cover the disks or coverslips. Place the slides in xylene for 5 min and in ethanol for 5 min, and then air-dry. Proceed to the next step.

## 14.2.7 PERFORMANCE OF *IN SITU* HYBRIDIZATION AND DETECTION BY RISH OR BY FISH

RISH is described in Sections 12.3.6 and 12.3.7, whereas FISH is described in Sections 13.5–13.7.

### Materials needed

- *Thermal cycler*  
GeneAmp *In Situ* PCR System 1000 (Perkin-Elmer Corporation) or the PTC-100 (MJ Research) that can simultaneously perform solution PCR in a tube and *in situ* PCR on glass slides, or other equivalent thermal cycler.

- *PCR kits*  
Available from Boehringer Mannheim and Perkin-Elmer Corporation.
- *10× Amplification buffer*  
0.1 M Tris-HCl, pH 8.3  
0.5 M KCl  
25 mM MgCl<sub>2</sub>  
0.1% BSA
- *Stock dNTPs*  
dATP 10 mM  
dTTP 10 mM  
dATP 10 mM  
dTTP 10 mM
- *Working dNTPs solution*  
10 μl dATP (10 mM)  
10 μl dTTP (10 mM)  
10 μl dATP (10 mM)  
10 μl dTTP (10 mM)
- *Taq polymerase*

### 14.3 DETECTION OF LOW ABUNDANCE mRNA BY *IN SITU* RT-PCR HYBRIDIZATION

The greatest value of the *in situ* PCR technique is its use as a powerful tool for detection of rare copy or low abundance mRNA, which is not possible with traditional northern blotting or standard *in situ* hybridization. In general, mRNA with few copies can be transcribed into cDNA using a reverse transcriptase. The cDNA is then amplified by PCR followed by standard *in situ* hybridization and detection of signals by appropriate methods. This entire procedure is referred to as *in situ* RT-PCR hybridization. In other words, the expression of extremely low abundance mRNA species can first be amplified at their original sites and then readily detected in intact cells or tissues. The general procedures and principles of *in situ* RT-PCR hybridization are outlined in Figures 14.4 and 14.5, respectively.

*In situ* RT-PCR is similar to *in situ* PCR as described in Section 14.2 except that a reverse transcription or RT is required at the first step. Because the very mobile RNA molecules are involved in RT-PCR, the procedure should be carried out with much care. Solutions, buffers, dd.H<sub>2</sub>O, glass slides, coverslips, plasticware, and glassware need to be treated with 0.1% diethylpyrocarbonate (DEPC) or made from DEPC-treated water. Chemicals should be RNase-free and gloves should be worn when performing RT-PCR. This section describes step-by-step protocols for the success of *in situ* RT-PCR hybridization with emphasis on the RT process.

#### 14.3.1 CARRYING OUT CELL OR TISSUE FIXATION, TISSUE EMBEDDING, SECTIONING, AND MOUNTING OF SECTIONS ON SLIDES

These procedures are described in Section 12.2.




FIGURE 14.4 Principles of *in situ* RT-PCR, hybridization and detection.




FIGURE 14.5 Principles of direct *in situ* RT-PCR and detection.

Note: For *in situ* RT-PCR hybridization, three separate drops of cell suspension or tissue sections should be placed on the same slide. The first cell drop or tissue section will be subjected to DNase and RNase digestion overnight before *in situ* RT-PCR. After *in situ* PCR hybridization, this will serve as a negative control because no PCR products are generated. The second drop of cells or tissue section will not be digested with either DNase or RNase treatment, which will serve as a positive control because all cells should have PCR products and hybridization signals. The third drop of cells or tissue section will serve as RT reaction, which will be treated with DNase but not RNase.

### 14.3.2 DEWAXING OF SECTIONS, PROTEASE DIGESTION, AND DNASE OR RNASE DIGESTION OF SPECIMENS

These activities are discussed in Section 12.3.

Note: Digestion of specimens with either DNase or RNase or both should be clearly marked and/or recorded according to the design stated in the note at step 1. Protease and DNase treatment will eliminate potential mispriming artifacts during the RT process.

### 14.3.3 PERFORMANCE *IN SITU* REVERSE TRANSCRIPTION REACTION ON SECTIONS<sup>17</sup>

Target mRNA can be selectively transcribed into cDNA using a specific primer that anneals to the 3' portion near the target region of the mRNA. In case multiple probes are used for multiple hybridization and detection, the authors recommend that oligo(dT) primers be used to transcribe all the mRNA species into cDNAs. Oligo(dT) primers will anneal to the 3' poly(A) tails of mRNA molecules and facilitate the synthesis of the first strand cDNAs. The cDNA pool allows the user to selectively amplify or carry out hybridization in the sample. Avian myeloblastosis virus (AMV) reverse transcriptase and Moloney murine leukemia virus (MoMuLV) reverse transcriptase are commonly used for RT reactions. RT kits are commercially available. A standard reaction volume for one slide is 25  $\mu$ l. The following cocktail is a total volume of 100  $\mu$ l for four slides.

1. Prepare the RT cocktail as follows:

10 $\times$ RT buffer for AMV or MoMuLV	10 $\mu$ l
dNTPs mixture (2.5 mM each)	10 $\mu$ l
RNasin (40 units/ $\mu$ l) as RNase inhibitor	2.8 $\mu$ l
Oligo(dT) primers (20 $\mu$ M)	4.8 $\mu$ l
<u>AMV or MoMuLV reverse transcriptase</u>	<u>50 units</u>
Add DEPC-treated dd.H <sub>2</sub> O to a final volume of	100 $\mu$ l

2. Add 25  $\mu$ l of the cocktail mixture to each slide and carefully overlay the cells or tissue sections with the cocktail using a clean coverslip.
3. Incubate the slides at 42°C in a high humidity chamber for 60 min.
4. Stop the RT reaction by heating at 80°C for 2 min, ethanol wash for 5 min, and partial air-drying.



**Reagents needed**

- *10× AMV or MoMuLV buffer*
  - 0.1 M Tris-HCl, pH 8.3
  - 0.5 M KCl
  - 25 mM MgCl<sub>2</sub>
- *Stock dNTPs*
  - dATP 10 mM
  - dTTP 10 mM
  - dATP 10 mM
  - dTTP 10 mM
- *Working dNTPs solution*
  - 10 μl dATP (10 mM)
  - 10 μl dTTP (10 mM)
  - 10 μl dATP (10 mM)
  - 10 μl dTTP (10 mM)

**14.3.4 PERFORMANCE OF RNASE (DNASE-FREE) DIGESTION OF SPECIMENS TO ELIMINATE POTENTIAL MISPRIMING BETWEEN PCR PRIMERS AND mRNA MOLECULES**

This is an optional procedure.

**14.3.5 PREPARATION OF RADIOACTIVE PROBES FOR RISH OR NONRADIOACTIVE PROBES FOR FISH**

Preparation of radioactive probes is described in Section 12.3.5 and that of nonradioactive probes for FISH is described in Section 13.4.

**14.3.6 DESIGN OF SPECIFIC PRIMERS FOR *IN SITU* PCR**

This procedure is discussed in Section 14.2.

**14.3.7 CARRYING OUT *IN SITU* PCR**

This procedure is discussed in Section 14.2.

**14.3.8 PERFORMANCE OF *IN SITU* HYBRIDIZATION AND DETECTION BY RISH OR BY FISH**

Performance of *in situ* hybridization and detection by RISH is described in Sections 12.3.6 and 12.3.7, whereas performance of *in situ* hybridization and detection by FISH is described in Sections 13.5–13.7.

#### 14.4 *IN SITU* PCR OR RT-PCR DETECTION OF DNA OR mRNA BY DIRECT INCORPORATION OF DIGOXIGENIN-11-dUTP OR BIOTIN-dUTP WITHOUT HYBRIDIZATION

*In situ* PCR or RT-PCR hybridization as described in Sections 14.2 and 14.3 mandates hybridization after PCR amplification, which is a relatively time-consuming and costly activity. This section, however, presents a rapid and simple approach for *in situ* PCR or *in situ* RT-PCR with direct incorporation of DIG-dUTP or biotin-dUTP. After a brief washing, the amplified sample can be directly used for detection of the target sequences, thus eliminating probes and hybridization.

Basically, the *in situ* PCR or RT-PCR procedure with direct incorporation is virtually the same as described in Sections 14.2 and 14.3 except that a labeled dUTP as a reporter molecule is used. Therefore, the procedures and notes mentioned in Sections 14.2 and 14.3 except for the preparation of PCR reaction cocktail (50  $\mu$ l per slide). The following cocktail is a total volume of 500  $\mu$ l for 10 sections.

10 $\times$ Amplification buffer	50 $\mu$ l
Mixture of four dNTPs (2.5 mM each)	50 $\mu$ l
Digoxigenin-11-dUTP	2.0 $\mu$ l
Sense or forward primer (20 $\mu$ M in dd.H <sub>2</sub> O)	25 $\mu$ l
Antisense or reverse primer (20 $\mu$ M in dd.H <sub>2</sub> O)	25 $\mu$ l
2% bovine serum albumin (BSA) or 0.02% gelatin solution in dd.H <sub>2</sub> O	25 $\mu$ l
<u>Taq DNA polymerase</u>	<u>50 units</u>
Add dd.H <sub>2</sub> O to final volume of	500 $\mu$ l

Add the cocktail onto the samples and perform *in situ* PCR as described in Section 14.2. For detection of the amplified sequences, anti-DIG-dUTP and anti-biotin-dUTP antibodies conjugated with alkaline phosphatase or peroxidase can be used (see the detection method for FISH in Chapter 13).

#### Troubleshooting Guide

1. *Individual sections fall apart during sectioning with no ribbons being formed.* Overfixation of tissues could have occurred. Try a shorter fixation time. An optimal fixation time should be determined.
2. *Sections crumble and are damaged during stretching.* Underfixation of tissues has occurred. Use a longer fixation time and determine the optimal time empirically.
3. *Sections have holes.* This is due to incomplete tissue dehydration and improper impregnation with wax. Perform complete dehydration of fixed tissues followed by thorough impregnation with melted paraffin wax.
4. *Holes occur in frozen sections.* Ice crystals are formed in the tissues during freezing or in the cryostat. Make sure to freeze the tissue correctly. Do not touch the frozen sections with bare fingers or relatively warm tools during

mounting of the specimens in the microtome or while brushing the sections from the cutting knife.

5. *Sections are not of uniform thickness and/or have lines throughout.* The cutting surface of the specimen block is not parallel to the edge of knife. The knife is dull. Take great care during mounting of the specimens in the microtome and use a sharpened knife.
6. *Morphology of tissue is poorly preserved.* Tissues are stretched or shrunk. Make sure not to press or stretch the tissue during dissection and embedding.
7. *After in situ PCR hybridization, no signals are detected in the cells, including the positive control. But there are no problems with the primers and the Taq polymerase, and PCR amplification worked well.* Double-stranded DNA probes and target DNA sequences may not be denatured before hybridization. Both dsDNA and probes must be denatured into ssDNA before hybridization. This is a key factor for hybridization.
8. *The intensity of fluorescence signal in specimens is too bright with a low signal-to-noise ratio.* The amount of fluorescein probes and/or biotin- or digoxigenin-detection solution is overloaded. Overhybridization thus occurs. Try to reduce the probe and detection solutions to 5- to 10-fold. Control the hybridization time to 2 to 4 h.
9. *A high background is shown in enzymatic detection sections. Inasmuch as color can be seen everywhere in specimens, it is difficult to ascertain which signal is the correct signal.* Color development goes for too long or the specimens may be partially or completely dried during hybridization and/or washing procedures. Try to monitor color development once every 3 to 4 min and terminate color formation as soon as the primary color signal appears. Probe-target sequence binding should reveal the first visible color before the potential background develops later. Make sure not to allow specimens to become dry.
10. *Positive signals are shown in the negative control.* DNase and RNase digestion of specimens are not complete. Therefore, primers can still anneal to target nucleic acids, initiating PCR amplification. Allow DNase and RNase treatment to proceed overnight or longer.

## REFERENCES

1. Haase, A. T., E. F. Retzel, and K. A. Staskus. 1990. Amplification and detection of lentiviral DNA inside cells. *Proceedings of the National Academy of Sciences of the United States of America* 37: 4971–4975.
2. Bagasra, O., and R. J. Pomerantz. 1993. HIV-1 provirus is demonstrated in peripheral blood monocytes *in vivo*: A study utilizing an *in situ* PCR. *AIDS Research and Human Retroviruses* 9: 69–76.
3. Don, R. H., P. T. Cox, B. J. Wainwright, K. Baker, and J. S. Mattick. 1991. Touchdown PCR to circumvent spurious priming during gene amplification. *Nucleic Acids Research* 19: 4008–4010.

4. Embleton, M. J., G. Gorochov, P. T. Jones, and G. Winter. 1992. In-cell PCR from mRBA amplifying and linking the rearranged immunoglobulin heavy and light chain V-genes within single cells. *Nucleic Acids Research* 20: 3831–3837.
5. Greer, C. E., S. L. Peterson, N. B. Kiviat, and M. M. Manos. 1991. PCR amplification from paraffin-embedded tissues: Effects of fixative and fixation times. *American Journal of Clinical Pathology* 95: 117–124.
6. Heniford, B. W., A. Shum-Siu, M. Leonberger, and F. J. Hendler. 1993. Variation in cellular EGF receptor mRNA expression demonstrated by *in situ* reverse transcription polymerase chain reaction. *Nucleic Acids Research* 21: 3159–3166.
7. Patterson, B. K., M. Till, P. Otto, and C. Goolsby. 1993. Detection of HIV-1 DNA and messenger RNA in individual cells by PCR-driven *in situ* hybridization and flow cytometry. *Science* 260: 976–979.
8. Lawrence, J. B., and R. H. Singer. 1985. Quantitative analysis of *in situ* hybridization methods for the detection of actin gene expression. *Nucleic Acids Research* 13: 1777–1799.
9. Singer, R. H., J. B. Lawrence, and C. Villnave. 1986. Optimization of *in situ* hybridization using isotopic and nonisotopic methods. *BioTechniques* 4: 230–250.
10. Lichter, P., A. L. Boyle, T. Cremer, and D. D. Ward. 1991. Analysis of genes and chromosomes by nonisotopic *in situ* hybridization. *Genetic Analysis Techniques and Applications* 8: 24–35.
11. Speel, E. J. M., B. Schutte, J. Wiegant, F. C. Ramaekers, and A. H. N. Hopman. 1992. A novel fluorescence detection method for *in situ* hybridization, based on the alkaline phosphatase-fast red reaction. *Journal of Histochemistry and Cytochemistry* 40: 1299–1308.
12. Trembleau, A., D. Roche, and A. Calas. 1993. Combination of non-radioactive and radioactive *in situ* hybridization with immunohistochemistry: A new method allowing the simultaneous detections of two mRNAs and one antigen in the same brain tissue section. *Journal of Histochemistry and Cytochemistry* 41: 489–498.
13. Nunovo, G. J., A. Forde, P. MacConnell, and R. Fahrenwald. 1993. *In situ* detection of PCR-amplified HIV-1 nucleic acids and tumor necrosis factor cDNA in cervical tissues. *American Journal of Pathology* 143: 40–48.
14. Nuovo, G. J. 1994. RT *in situ* PCR with direct incorporation of digoxigenin-11-dUTP: Protocol and applications. *Biochemica* 11(1): 4–6.
15. Nuovo, G. J. 1994. *PCR In situ Hybridization: Protocols and Applications*. New York, NY: Raven Press.
16. Zeller, R., S. Watkins, M. Rogers, J. H. M. Knoll, O. Bagasra, and J. Hanson. 1995. *In situ* hybridization and immunohistochemistry. In *Current Protocols in Molecular Biology*, ed. F. M. Ausubel, R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl, 14.0.3–14.8.24. New York, NY: John Wiley & Sons.
17. Staecker, H., M. Cammer, R. Rubinstein, and T. R. Van De Water. 1994. A procedure for RT-PCR amplification of mRNAs on histological specimens. *BioTechniques* 16: 76–80.

---

# 15 Isolation and Characterization of Genes from Genomic DNA Libraries

## 15.1 INTRODUCTION

Gene isolation plays a major role in current molecular biology.<sup>1</sup> To isolate the gene of interest, it may be necessary to construct a genomic DNA library. The quality and integrity of a genomic DNA library greatly influence the identification of a specific gene. An excellent library should contain all the DNA sequences of the entire genome. The probability of “fishing” out a DNA sequence depends on the size of DNA fragments, which can be calculated as

$$N = \frac{\ln(1 - P)}{\ln(1 - f)}$$

where  $N$  is the number of recombinants required,  $P$  is the desired probability of fishing out a DNA sequence, and  $f$  is the fractional proportion of the genome in a single recombinant. For instance, given a 99% probability to isolate an interesting DNA sequence from a library that is constructed with 18-kb fragments of a  $4 \times 10^9$  base pairs genome, the required recombinants are

$$\begin{aligned} N &= \frac{\ln(1 - 0.99)}{\ln\left[1 - (1.8 \times 10^4 / 4 \times 10^9)\right]} \\ &= 1 \times 10^6 \end{aligned}$$

The average size of DNA fragments selected for cloning depends on cloning vectors. Three types of vectors are widely used for the construction of genomic DNA libraries: bacteriophage lambda vectors; cosmids; and yeast artificial chromosomes (YACs). Lambda vectors can hold 14- to 25-kb DNA fragments. Recombinants of  $3 \times 10^{6-7}$  are usually needed to achieve a 99% probability of isolating a specific clone, and the screening procedure of the library is relatively complicated. Cosmids, on the other hand, can accept 35 to 45 kb of DNA fragments. Approximately  $3 \times 10^5$  recombinant cosmids are sufficient for a 99% probability of identifying a particular

single-copy sequence of interest. However, it is difficult to construct and maintain a genomic DNA library in cosmids compared with bacteriophage lambda vectors. YAC vectors are useful for cloning of 50- to 10,000-kb DNA fragments. This is especially powerful when one wishes to clone and isolate extra-large genes (e.g., human factor VIII gene, 180 kb in length; the dystrophin gene, 1800 kb in length) in a single recombinant YAC of a smaller size library.

This chapter describes in detail the protocols for the construction and screening of a bacteriophage  $\lambda$  library.<sup>1-7</sup>

## 15.2 SELECTION OF LAMBDA VECTORS

Traditionally, the widely used bacteriophage  $\lambda$  DNA vectors are EMBL3 and EMBL4 (Figure 15.1). Both types of vectors contain a left arm (20 kb), a right arm (9 kb), and a central stuffer (14 kb) that can be replaced with a foreign genomic DNA insert (9 to 23 kb). The difference between two  $\lambda$  DNA vectors is the orientation of the multiple cloning site (MCS).

Recently, new  $\lambda$  DNA vectors such as LambdaGEM-11 and LambdaGEM-12 have been developed (Figure 15.2), which are modified from EMBL3 and EMBL4. The sizes of arms and capacity of cloning foreign DNA inserts are the same as vectors EMBL3 and 4. However, more restriction enzyme sites are designed in the MCS. Additionally, there are two RNA promoters, T7 and SP6, at the polylinker ends in opposite orientations.

## 15.3 ISOLATION OF HIGH MOLECULAR WEIGHT OF GENOMIC DNA

1. For cultured cells, aspirate culture medium and rinse the cells twice in PBS. Add 10 ml/60 mm culture plate (with approximately  $10^5$  cells) of DNA isolation buffer to the cells and allow cells to be lysed for 5 min at room




FIGURE 15.1 Structures of vectors EMBL 3 and EMBL 4.




FIGURE 15.2 Structures of vectors lambda GEM-11 and lambda GEM-12.

temperature with shaking at 60 rev/min. For tissues, grind 1 g tissue in liquid N<sub>2</sub> to fine powder and transfer the powder into a tube containing 15 ml of DNA isolation buffer. Allow cells to be lysed for 10 min at room temperature with shaking at 60 rev/min.

2. Incubate at 37°C for 5 h or overnight to degrade proteins and extract genomic DNA.
3. Allow the lysate to cool to room temperature and add 3 volumes of 100% ethanol precold at -20°C to the lysate. Gently mix it and allow DNA to precipitate at room temperature with slow shaking at 60 rev/min. Precipitated DNA, appearing as white fibers, should be visible in 20 min.
4. Fish out the DNA using a sterile glass hook or spin down the DNA. Rinse the DNA twice in 70% ethanol and partially dry the DNA for 40 to 60 min at room temperature to evaporate the ethanol. The DNA can be directly subjected to restriction enzyme digestion without being dissolved in TE buffer or dd.H<sub>2</sub>O. We usually overlay the precipitated DNA with an appropriate volume of restriction enzyme digestion cocktail and incubate the mixture at an appropriate temperature for 12 to 24 h. The digested DNA is mixed with an appropriate volume of DNA loading buffer and is ready for agarose gel electrophoresis.

### Reagents needed

- *DNA isolation buffer*
  - 75 mM Tris-HCl, pH 6.8
  - 100 mM NaCl
  - 1 mg/ml protease K (freshly added)
  - 0.1% (w/v) *N*-Lauroylsarcosine

## 15.4 PARTIAL DIGESTION OF GENOMIC DNA USING SAU3AI

It is necessary to partially digest the high molecular weight of genomic DNA with a four-base cutter, *Sau3AI*, before ligation with appropriate vectors.

### 15.4.1 DETERMINATION OF THE OPTIMAL PARTIAL DIGESTION OF GENOMIC DNA WITH SAU3AI

To determine the amount of enzyme used to digest the high molecular weight of DNA into 20- to 30-kb fragments, small-scale reactions, or pilot experiments, should be carried out.

1. Prepare 1× *Sau3AI* buffer on ice:

10× <i>Sau3AI</i> buffer	0.2 μl
Add dd.H <sub>2</sub> O to a final volume of	2.0 μl

2. Perform *Sau3AI* dilutions in 10 individual microcentrifuge tubes on ice:

Tube #	<i>Sau3AI</i> (3 u/μl) Dilution	Dilution Factors
1	2 μl <i>Sau3AI</i> + 28 μl 1× <i>Sau3AI</i> buffer	1/15
2	10 μl of 1/15 dilution + 90 μl 1× <i>Sau3AI</i> buffer	1/150
3	10 μl of 1/150 dilution + 10 μl 1× <i>Sau3AI</i> buffer	1/300
4	10 μl of 1/150 dilution + 30 μl 1× <i>Sau3AI</i> buffer	1/600
5	10 μl of 1/150 dilution + 50 μl 1× <i>Sau3AI</i> buffer	1/900
6	10 μl of 1/150 dilution + 70 μl 1× <i>Sau3AI</i> buffer	1/1200
7	10 μl of 1/150 dilution + 90 μl 1× <i>Sau3AI</i> buffer	1/1500
8	10 μl of 1/150 dilution + 110 μl 1× <i>Sau3AI</i> buffer	1/1800
9	10 μl of 1/150 dilution + 190 μl 1× <i>Sau3AI</i> buffer	1/3000
10	10 μl of 1/150 dilution + 290 μl 1× <i>Sau3AI</i> buffer	1/4500

3. Set up 10 individual small-scale digestion reactions on ice in the order listed below:

Components	Tube Number									
	1	2	3	4	5	6	7	8	9	10
Genomic DNA (1μg/μl)	1(μl)	1	1	1	1	1	1	1	1	1
10× <i>Sau3AI</i> buffer	5(μl)	5	5	5	5	5	5	5	5	5
dd.H <sub>2</sub> O (μl)	39	39	39	39	39	39	39	39	39	39
<i>Sau3AI</i> dilution in the same order as those in step 2	5(μl)	5	5	5	5	5	5	5	5	5
Final volume (μl)	50	50	50	50	50	50	50	50	50	50

Note: The final *Sau3AI* concentration used in tubes 1 to 10 should be 1, 0.1, 0.05, 0.025, 0.015, 0.0125, 0.01, 0.0085, 0.005, and 0.0035 unit/μg DNA, respectively.



4. Incubate the reactions at the same time at 37°C for 30 min. Place the tubes on ice and add 2  $\mu$ l of 0.2 M EDTA buffer (pH 8.0) to each tube to stop the reactions.
5. While the reactions are being performed, prepare a large size of 0.4% agarose gel in 1 $\times$  TBE buffer.
6. Add 10  $\mu$ l of 5 $\times$  DNA loading buffer to each of the 10 tubes containing the digested DNA prepared in step 4.
7. Carefully load 30  $\mu$ l of each sample onto the wells in the order of 1 to 10. Load DNA markers (e.g.,  $\lambda$ DNA *Hind*III markers) to the left or the right well of the gel to estimate the sizes of digested DNA.
8. Carry out electrophoresis of the gel at 4 to 8 V/cm until the bromphenol blue reaches the bottom of the gel.
9. Photograph the gel under UV light and find the well that shows the maximum intensity of fluorescence in the desired DNA size range of 20 to 30 kb.

#### 15.4.2 LARGE-SCALE PREPARATION OF PARTIAL DIGESTION OF GENOMIC DNA

1. Based on the optimal conditions established above, carry out a large-scale digestion of 50  $\mu$ g of high-molecular-weight genomic DNA using half-units of *Sau*3AI/ $\mu$ g DNA that produced the maximum intensity of fluorescence in the DNA size range of 20 to 30 kb. The DNA concentration, time, and temperature should be exactly the same as those used for the small-scale digestion. For instance, if tube #7 (0.01 unit of *Sau*3AI/ $\mu$ g DNA) in the small-scale digestion of the DNA shows a maximum intensity of fluorescence in the size range of 20 to 30 kb, the large-scale digestion of the same DNA can be carried out on ice as follows.

Genomic DNA (1 $\mu$ g/ $\mu$ l)	50 $\mu$ l
10 $\times$ <i>Sau</i> 3AI buffer	250 $\mu$ l
dd.H <sub>2</sub> O	1.95 ml
Diluted <i>Sau</i> 3AI	250 $\mu$ l
(0.005 u/ $\mu$ g) prepared as tube #9	
Final volume of	2.5 ml

2. Incubate the reactions at 37°C in a water bath for 30 min. Stop the reaction by adding 20  $\mu$ l of 0.2 M EDTA buffer (pH 8.0) to the tube and place it on ice until use.
3. Add 2 to 2.5 volumes of chilled 100% ethanol to precipitate at -70°C for 30 min.
4. Centrifuge at 12,000 *g* for 10 min at room temperature. Carefully decant the supernatant and briefly rinse the DNA pellet with 5 ml of 70% ethanol. Dry the pellet under vacuum for 8 min. Dissolve the DNA in 50  $\mu$ l of TE buffer. Take 5  $\mu$ l of the sample to measure the concentration at  $A_{260}$  nm and store the DNA sample at -20°C before use.

**Reagents needed**

- *10× Sau3AI buffer*  
0.1 M Tris-HCl, pH 7.5  
1 M NaCl  
70 mM MgCl<sub>2</sub>
- *5× Loading buffer*  
38% (w/v) Sucrose  
0.1% Bromphenol blue  
67 mM EDTA
- *5× TBE buffer*  
Tris base 54 g  
Boric acid 27.5 g  
20 ml of 0.5 M EDTA, pH 8.0
- *TE buffer*  
10 mM Tris-HCl, pH 8.0  
1 mM EDTA, pH 8.0
- *Ethanol (100%, 70%)*

### 15.5 PARTIAL FILL-IN OF RECESSED 3'-TERMINI OF GENOMIC DNA FRAGMENTS

Because partially filled-in *XhoI* sites of  $\lambda$  vectors are commercially available, the partially digested DNA fragments should be partially filled-in in order to be ligated with the vectors. The advantage of these reactions is to prevent DNA fragments from self-ligation, thus eliminating the need for size fractionation of genomic DNA fragments.

1. On ice, set up a standard reaction as follows:

Partially digested genomic DNA	20 $\mu$ g
10 $\times$ fill-in buffer containing dGTP and dATP	10 $\mu$ l
Klenow fragment of <i>E. coli</i> DNA	4 $\mu$ l
<u>polymerase I (5 units/<math>\mu</math>l)</u>	
Add dd.H <sub>2</sub> O to final volume	0.1 ml

2. Incubate the reaction at 37°C for 30 to 60 min.
3. Extract and precipitate as described above. Dissolve the DNA pellet in 20  $\mu$ l of dd.H<sub>2</sub>O. Take 2  $\mu$ l of the sample to measure the concentration of DNA. Store the sample at -20°C until use.

**Reagents needed**

- *10× Fill-in buffer*  
500 mM Tris-HCl, pH 7.2  
0.1 M MgSO<sub>4</sub>  
1 mM DTT

10 mM dATP  
10 mM dGTP

## 15.6 LIGATION OF DNA INSERTS TO VECTORS

### 15.6.1 SMALL-SCALE LIGATION OF PARTIALLY FILLED-IN GENOMIC DNA FRAGMENTS AND PARTIALLY FILLED-IN LAMBDA GEM-12 ARMS

1. Set up, on ice, a sample and control reactions as follows:

*Sample reaction:*

Components	Tube #1	2	3	4	5
Insert DNA (0.3 µg/µl, 0.1 µg = 0.01 pmol)	0	4	3	2	0.5 (µl)
Vector DNA (0.5 µg/µl, 1 µg = 0.035 pmol)	2	2	2	2	2 (µl)
10× ligase buffer	1	1	1	1	1 (µl)
dd.H <sub>2</sub> O	6	2	3	4	5.5 (µl)
T4 DNA ligase (10–15 Weiss units/µl)	1	1	1	1	1 (µl)
Total volume	10	10	10	10	10 (µl)

*Positive control reaction:*

λGEM-12 <i>Xho</i> I half-site arms (0.5 µg)	2 µl
Positive control insert (0.5 µg)	2 µl
10× Ligase buffer	1 µl
dd.H <sub>2</sub> O	4 µl
(10–15 Weiss units/µl)	1 µl
Total volume	10 µl

2. Incubate the ligation reactions overnight at 4°C for *Xho*I half-site arms.

Notes: (1) A positive control is necessary in order to check the efficiency of ligation, packaging, and titration. If the efficiency is very low, for example, pfu/ml is  $<10^4$ ; this means that either the vectors do not work well or some procedures are not carried out properly. In general, the positive control is pretested by the company and pfu/ml =  $10^7$ . (2) A ligation of vector arms only is to check the background produced by the vector arms. Usually, pfu/ml is  $<10^{2-3}$ . A higher pfu number (e.g.,  $10^{4-5}$ ) indicates that the vectors' self-ligation is very high, which will lower the efficiency of ligation between the vector arms and the insert DNA.

### Reagents needed

- 10× Ligase buffer
  - 0.3 M Tris-HCl, pH 7.8
  - 0.1 M MgCl<sub>2</sub>
  - 0.1 M DTT
  - 10 mM ATP

### 15.6.2 PACKAGING OF THE LIGATED DNA

1. Thaw three commercial Packagene extracts (50  $\mu$ l/extract) on ice.  
*Note: Do not thaw the extract at 37°C.*
2. Immediately divide each extract into two tubes (25  $\mu$ l/tube) on ice.
3. Add 4  $\mu$ l of each of the ligated mixture in step (2) (Section 15.6.1) into appropriate tubes, each containing 25  $\mu$ l of packaging extract. To test the quality of the packaging extract, add 0.5  $\mu$ g of the provided positive packaging DNA into a 25  $\mu$ l packaging extract.
4. Incubate the reactions at 22 to 24°C (room temperature) for 3 to 4 h.
5. Add phage buffer to each packaged tube up to 0.25 ml and add 10 to 12  $\mu$ l of chloroform. Mix well by inversion and allow the chloroform to settle to the bottom of the tube. Store the packaged phages at 4°C until use or for up to 4 weeks with a consequent several-fold drop of the titer.

*Note: When the packaged phage solution is used for titration or screening, do not mix the chloroform at the bottom of the tube into the solution. Otherwise, the chloroform may kill or inhibit the growth of the bacteria.*

#### Reagent needed

- *Phage buffer*  
20 mM Tris-HCl, pH 7.5  
100 mM NaCl  
10 mM MgSO<sub>4</sub>

### 15.6.3 TITRATION OF PACKAGED PHAGE ON LURIA-BERTANI PLATES

1. Partially thaw appropriate bacterial strain such as *E. coli* LE 392, or KW 251 on ice. Pick up a tiny bit of the bacteria using a sterile wire transfer loop, and inoculate the bacteria on the surface of a Luria-Bertani (LB) plate. Invert the plate and incubate at 37°C overnight. Multiple bacterial colonies will grow up.
2. Prepare a fresh bacterial culture by picking a well-isolated colony from the LB plate using a sterile wire transfer loop and inoculate it into a culture tube containing 5 ml of LB medium supplemented with 50 ml of 20% maltose and 50 ml of 1 M MgSO<sub>4</sub> solution. Shake at 160 rev/min at 37°C for 6 to 9 h or until the OD<sub>600</sub> has reached 0.6.
3. Dilute each of the packaged recombinant phage samples to 1000 $\times$ , 5000 $\times$ , and 10,000 $\times$  in phage buffer.
4. Add 20  $\mu$ l of 1 M MgSO<sub>4</sub> solution and 2.8 ml of melted top agar to each of 36 sterile glass test tubes. Cap the tubes and immediately place the tubes in a 50°C water bath for at least 30 min before use.
5. Mix 0.1 ml of the diluted phage with 0.1 ml of fresh bacterial cells in a microcentrifuge tube. Allow the phage to adhere to the bacteria at 37°C for 30 min.
6. Add the incubated phage-bacterial mixture into specific tubes in a water bath. Vortex gently and immediately pour onto the centers of LB plates;

next, quickly overlay the surface of each LB plate by gently tilting the plate. Cover the plates and allow the top agar to harden for 15 min at room temperature. Invert the plates and incubate them in an incubator at 37°C overnight or for 16 h.

7. Count the number of plaques in each plate and calculate the titer of the phage (pfu) for the sample and the control.

Plaque-forming units (pfu) per milliliter = number of plaques/plate  $\times$  dilution times  $\times$  10

The “10” refers to the 0.1 ml, on per milliliter basis, of the packaging extract used for one plate. For example, if there are 200 plaques on a plate made from a 1/5000 dilution, the pfu per milliliter of the original packaging extract will be:  $200 \times 5000 \times 10 = 1 \times 10^7$ .

8. Compare the titers (pfu/ml) from different samples, determine the optimal ratio of vector arms and genomic DNA inserts, and carry out a large-scale ligation and a packaging reaction using the optimum conditions.

### Solutions needed

- *Phage buffer*
  - 20 mM Tris-HCl, pH 7.4
  - 0.1 M NaCl
  - 10 mM MgSO<sub>4</sub>
- *LB medium (per liter)*
  - 10 g Bacto-tryptone
  - 5 g Bacto-yeast extract
  - 5 g NaCl
  - Adjust to pH 7.5 with 0.2 N NaOH and autoclave.
  - 20% (v/v) maltose
  - 1 M MgSO<sub>4</sub>
- *LB plates*
  - Add 15 g of Bacto-agar to 1 l of freshly prepared LB medium and autoclave. Allow the mixture to cool to about 60°C and pour 30 ml of the mixture into each 85- or 100-mm diameter Petri dishes in a sterile laminar flow hood. Remove any air bubbles with a pipette tip and let the plates cool for 5 min before covering them. Allow the agar to harden for 1 h and store the plates at room temperature for up 10 days or at 4°C in a bag for 1 month.
- *TB top agar*
  - Add 3.0 g agar to 500 ml freshly prepared LB medium and autoclave. Store at 4°C until use. For plating, melt the agar in a microwave oven. When the solution has cooled to 60°C, add 0.1 ml of 1 M MgSO<sub>4</sub> per 10 ml of the mixture.
- *S buffer*
  - Phage buffer + 2% (w/v) gelatin

### 15.6.4 LARGE-SCALE LIGATION OF THE PARTIALLY FILLED-IN VECTOR ARMS AND PARTIALLY FILLED-IN GENOMIC DNA FRAGMENTS

1. Based on the pfu/ml of the small-scale ligations, choose the optimal conditions for large-scale ligation. For example, if tube #4 in the small-scale ligation shows the maximum pfu/ml, then a large-scale ligation can be set up as follows:

Partially filled-in DNA inserts (0.3 µg/µl, 0.1 µg = 0.01 pmol)	10 µl
Partially filled-in vector arms ( <i>Xho</i> I half-site arms, 0.5 µg/µl, 1 µg = 0.035 pmol)	10 µl
10× ligase buffer	5 µl
dd.H <sub>2</sub> O	20 µl
T4 DNA ligase (10–15 Weiss units/µl)	5 µl
Total volume	50 µl

2. Incubate the reaction at 4°C for 12 to 24 h.
3. Carry out packaging *in vitro* of ligated DNA using packagene extracts thawed on ice. Add 9 µl of the ligated mixture to each of two extracts (50 µl/extract).
4. Incubate at 22 to 24°C for 5 to 8 h.
5. Add phage buffer to each tube up to 0.5 ml. Add 25 µl of chloroform to each tube, mix well, and store at 4°C until use or for up to 4 weeks. At this stage, a genomic DNA library has been established.
6. Carry out titration as described above.

Note: A good genomic library should have a pfu number up to  $10^{7-8}$ /ml. If pfu  $< 10^4$ , it is considered a poor library and should not be used for screening.

## 15.7 SCREENING OF GENOMIC DNA LIBRARY AND ISOLATION OF SPECIFIC CLONES

### 15.7.1 METHOD A. SCREENING OF A GENOMIC LIBRARY WITH $\alpha$ -<sup>32</sup>P-LABELED PROBE

1. Partially thaw the specific bacterial strain, *Escherichia coli* LE392 on ice. Pick up a tiny amount of the bacteria using a sterile wire transfer loop and streak out the *E. coli* on an LB plate. Invert the plate and inoculate in an incubator at 37°C overnight.
2. Prepare a fresh bacterial culture by picking up a single colony from the LB plate using a sterile wire transfer loop and inoculate into a culture tube containing 50 ml of LB medium supplemented with 0.5 ml of 20% maltose and 0.5 ml of 1 M MgSO<sub>4</sub> solution. Shake at 160 rev/min at 37°C overnight or until the OD<sub>600</sub> has reached 0.6. Store the culture at 4°C until use.

3. Add 20  $\mu$ l of 1 M  $\text{MgSO}_4$  solution and 2.8 ml of melted LB top agar to each of sterile glass test tubes. Cap the tubes and immediately place them in a 50°C water bath for at least 30 min before use.
4. Based on the titration data, dilute the lambda DNA library with phage buffer. Set up 20 to 25 plates for primary screening of the genomic DNA library. For each of the 100-mm diameter plates, mix 0.1 ml of the diluted phage containing  $2 \times 10^5$  pfu of the genomic library with 0.2 ml of fresh bacterial cells in a microcentrifuge tube. Allow the phage to adhere to the bacteria in an incubator at 37°C for 30 min.
5. Add the phage–bacterial mixture into the tubes in the water bath. Vortex gently and immediately pour onto the center of each LB plate, then quickly overlay the entire surface of each LB plate by gently tilting the plate. Cover the plates and allow the top agar to harden for 15 min at room temperature. Invert the plates and incubate in an incubator at 37°C overnight.
6. Chill the plates at 4°C for 1.5 h.

7. Transfer the plates to room temperature. Carefully overlay each plate with a dry nitrocellulose filter disk or a nylon membrane disk (prewetting treatment is not necessary) from one side of the plate slowly to the other side. Allow the phage DNA to mobilize onto the facing side of the membrane filters for 3 to 5 min. If a duplicate is needed, a second filter may be overlaid on the plate for 4 to 7 min.

Notes: (1) Air bubbles should be avoided when overlaying the membrane filters onto the LB plates. After overlay of filters, quickly mark the top side and position of each filter in a triangular pattern by punching the filter through the bottom agar layer with a 20-gauge needle containing some India ink. (2) We recommend to use positively charged nylon membrane disks because they can tightly bind the negative phosphate groups of the DNA. Nylon membranes are not easily broken, which is usually the case with nitrocellulose membranes.

8. Carefully remove the filters using forceps and individually place the filters, plaque side up, on a piece of wet Whatman 3MM filter paper saturated with denaturing solution for 4 min at room temperature. Label and wrap each plate with a piece of Parafilm, and store the plates at 4°C until use.  
Note: This step serves to denature the double-stranded DNA for hybridization with a probe.
9. Transfer the filters, plaque side up, on another piece of Whatman 3MM paper saturated with neutralization solution at room temperature for 4 min.
10. Carefully transfer the filters, plaque side up, on another piece of Whatman 3MM filter paper saturated with 5 $\times$  SSC at room temperature for 2 min.
11. Air-dry the filters at room temperature for about 15 min and then cover the filters with dry Whatman 3MM paper and bake the filters in a vacuum oven at 80°C for 2 h or use a UV cross-linker. Wrap the filters with aluminum foil and store at 4°C until prehybridization.

Note: This step is to fix the DNA onto the filters.

12. Immerse the filters in  $5\times$  SSC for 5 min at room temperature to equilibrate the filters.

Note: *Do not let the filters dry during subsequent steps. Otherwise, a high background will show up.*

13. Place the filters in the prehybridization solution and carry out prehybridization for 2 to 4 h with slow shaking at 60 rev/min.

Notes:

- (1) *We strongly recommend not using plastic hybridization bags because it is not easy to get rid of air bubbles underneath the filters or they cannot be well sealed. This may cause leaking and contamination. An appropriate size of plastic beaker or tray is the best type of hybridization container.*
  - (2) *The prehybridization temperature depends on the prehybridization buffer. The temperature should be set at 42°C if the buffer contains 30% to 40% (for low stringency conditions) or 50% formamide (for high stringency condition). If the buffer, on the other hand, does not contain formamide, the temperature is set at 65°C or higher. Low stringency conditions can help identify DNA of a potential multigene family. High stringency conditions help prevent nonspecific cross-linking hybridization.*
  - (3) *It is strongly recommended that a regular culture shaker with a cover and temperature control be used as the hybridization chamber. This type of chamber is easy to handle simply by placing the hybridization beaker or tray containing the filters and buffer on the shaker in the chamber. A commercial hybridization oven may be difficult to operate because the filters must be covered with a matrix and put inside the hybridization bottle, during which time air bubbles are easily generated.*
  - (4) *If many filters are used in hybridization, a beaker should not contain more than three filter disks. Too many filters in one beaker may cause weak hybridization signals.*
  - (5) *The volume of prehybridization solution should be 15 ml per 100 cm<sup>2</sup> filter disk.*
14. Prepare a DNA probe for hybridization as described in Chapter 7.
  15. If the probes are double-stranded DNA, denature the probe in boiling water for 10 min and immediately chill on ice for 5 min. Briefly spin down before use.

Notes: *This is a critical step. If the probes are not completely denatured, a weak or no hybridization signal will occur. Single-strand oligonucleotide probes, however, do not require denaturation.*

Caution: *[ $\alpha$ -<sup>32</sup>P]dCTP is a dangerous isotope. A laboratory coat and gloves should be worn when working with the isotope. Gloves should be changed often and put in a special container. Waste liquid, pipette tips, and papers contaminated with the isotope should be collected in labeled containers. After finishing, a radioactive contamination survey should be performed and recorded.*



16. Dilute the purified probe with 1 ml of hybridization solution and add the probe at  $2$  to  $10 \times 10^6$  cpm/ml to the hybridization buffer. Mix well and carefully transfer the prehybridized filters to the hybridization solution. Allow hybridization to proceed overnight or up to 19 h.

17. Wash the hybridized filters according to the following conditions:

*Use of high stringency conditions*

- (a) Wash the filters in a solution (50 ml/filter) containing  $2\times$  SSC and 0.1% SDS (w/v) for 15 min at room temperature with slow shaking. Repeat once.
- (b) Wash the filters in a fresh solution (50 ml/filter) containing  $2\times$  SSC and 0.1% SDS (w/v) for 20 min at  $65^\circ\text{C}$  with slow shaking. Repeat two to four times.
- (c) Air-dry the filters at room temperature for about 40 min and prepare for autoradiography.

*Use of low stringency conditions*

- (a) Wash the filters in a solution (50 ml/filter) containing  $2\times$  SSC and 0.1% SDS (w/v) for 10 min at room temperature with slow shaking. Repeat once.
  - (b) Wash the filters in a fresh solution (50 ml/filter) containing  $2\times$  SSC and 0.1% SDS (w/v) for 15 min at 50 to  $55^\circ\text{C}$  with slow shaking. Repeat once.
  - (c) Air-dry the filters at room temperature for 40 min and proceed with autoradiography.
18. Wrap the filters one by one with Saran Wrap™ and place in an exposure cassette. In a dark room with the safe light on, cover the filters with a piece of x-ray film and place the cassette with an intensifying screen at  $-80^\circ\text{C}$  for 2 to 24 h before they are developed.

*Note: The film should be slightly overexposed in order to obtain a relatively dark background. This will help to identify the marks made previously.*


19. To locate the positive plaques, match the developed film with the original plate by placing the film underneath the plate with the help of markers made previously.

*Note: This can be done by placing a glass plate over a lamp and putting the matched film and plate on the glass plate. Turn on the light so that the positive clones can be easily identified. Make sure that the plaque facing side exposed on the film faces down to identify the actual positive plaques. Any mismatch will cause failure of identification.*

20. Remove individual positive plugs containing phage particles from the plate using a sterile pipette tip with the tip cut off. Expel the plug into a microcentrifuge tube containing 1 ml of elution buffer. Allow elution for 4 h at room temperature with occasional shaking.

21. Transfer the supernatant containing the eluted phage particles into a fresh tube and add 20  $\mu\text{l}$  of chloroform. Store at  $4^\circ\text{C}$  for up to 5 weeks.

22. Determine the pfu of the supernatant as described previously. Replate the phage and repeat the screening procedure with the same isotopic probe several times until 100% of the plaques on the plate are positive (Figure 15.3).



**FIGURE 15.3** Diagram of rescreening and purification of positive clones from a genomic DNA library.

Note: During the rescreening process, the plaque number used for each plate should be gradually reduced. In our experience, the plaque density for one 100-mm plate in rescreening procedures is 1000 to 500 to 300, and to 100.

23. Amplify the putative DNA clones and isolate the recombinant lambda DNAs by either the plate or the liquid method. The purified DNA can be used for subcloning and sequencing.

### Reagents needed

- *Elution buffer*  
10 mM Tris-HCl, pH 7.5  
10 mM MgCl<sub>2</sub>
- *Phage buffer*  
20 mM Tris-HCl, pH 7.4  
100 mM NaCl  
10 mM MgSO<sub>4</sub>
- *20× SSC solution (1 l)*  
3 M NaCl  
0.3 M Na<sub>3</sub> citrate (trisodium citric acid)  
Autoclave.
- *Denaturing solution*  
1.5 M NaCl  
0.5 M NaOH  
Autoclave.
- *Neutralizing solution*

- 1.5 M NaCl
- 0.5 M Tris-HCl, pH 7.4
- Autoclave.
- *50× Denhardt's solution*
  - 1% (w/v) Bovine serum albumin (BSA)
  - 1% (w/v) Ficoll (Type 400, Pharmacia)
  - 1% (w/v) Polyvinylpyrrolidone (PVP)
  - Dissolve well after each addition. Adjust the final volume to 500 ml with distilled water and sterile filter. Divide the solution into 50-ml aliquots and store at  $-20^{\circ}\text{C}$ . Dilute 10-fold into prehybridization and hybridization buffers.
- *Prehybridization buffer*
  - 5× SSC
  - 0.5% SDS
  - 5× Denhardt's reagent
  - 0.2% denatured salmon sperm DNA
- *Hybridization buffer*
  - 5× SSC
  - 0.5% SDS
  - 5× Denhardt's reagent
  - 0.2% denatured salmon sperm DNA
  - [ $\alpha$ - $^{32}\text{P}$ ]-labeled DNA probe

### 15.7.2 METHOD B. SCREENING OF A GENOMIC LIBRARY USING A NONISOTOPE LABELED PROBE

1. Carry out steps 1 to 13 as described in Method A (Section 15.7.1).
2. Perform prehybridization and hybridization, which are the same as described in Method A except that a nonradioactive probe and appropriate buffers are used.
3. Transfer the hybridized, washed filters into a clean dish containing buffer A (15 ml/filter) for 2 to 4 min.
4. Transfer the filters in buffer B (15 ml/filter) for 60 min.
5. Incubate the filters with an antibody solution, which is the anti-DIG-alkaline phosphatase (Boehringer Mannheim Biochemicals) diluted at 1:10,000 in buffer B, at room temperature for 40 to 60 min using 10 ml/filter.
6. Wash the filters (100 ml/filter) in buffer A for 20 min and repeat once using a fresh washing tray.

Note: *The used antibody solution can be stored at  $4^{\circ}\text{C}$  for up to 1 month and reused for five to six times without any significant decrease in the antibody activity.*
7. Equilibrate the filters in buffer C for 1 to 4 min.
8. Detect the hybridized band(s) by one of the two methods.
  - (1) Using Lumi-Phos 530 (Boehringer Mannheim Biochemicals) as a substrate
    - (a) Add 0.5 ml of the Lumi-Phos 530 to the center of a clean dish, which should be prewarmed to room temperature for 1 h before use.

- (b) Briefly damp a filter using a forceps and completely wet the plaque facing side of the filter and/or both sides of the filter by slowly laying the filter down in the solution several times.
  - (c) Wrap the filter with Saran Wrap and remove the excess Lumi-Phos solution using paper towels to reduce black background.
  - (d) Place the wrapped filter in an exposure cassette with the side facing up. Repeat steps (b), (c), and (d) until all the filters are complete.
  - (e) Overlay the wrapped filters with an x-ray film in a dark room with the safe light on and allow the exposure to proceed, by placing the closed cassette at room temperature, for 2 min to 24 h.
  - (f) Develop the film and proceed to identification of positive clones.
- Note: (1) Exposure for more than 4 h may produce a high black background. Based on our experience, a good hybridization and detection should generate sharp positive spots with 1.5 h of exposure. (2) The film should be slightly exposed to obtain a relatively dark background that will help identify the marks made previously.
- (2) Using the NBT and BCIP detection method
    - (a) Add 40  $\mu$ l of NBT solution and 30  $\mu$ l of BCIP solution in 10 ml buffer C for one filter. NBT and BCIP are available from Boehringer Mannheim Biochemicals.
    - (b) Place the filter in the mixture prepared in step (a) and put in a dark place for color development at room temperature for 30 min to 1 day.
    - (c) Air-dry the filters and proceed to identification of positive clones in the original LB plates as described in Method A (Section 15.7.1).

### Reagents needed

- *Buffer A*
  - 100 mM Tris-HCl
  - 150 mM NaCl, pH 7.5
- *Buffer B*
  - 2% (w/v) Blocking reagent (Boehringer Mannheim Biochemicals) or an equivalent such as BSA, nonfat dry milk, gelatin in buffer A. Dissolve well by stirring with a magnetic stir bar.
- *Buffer C*
  - 100 mM Tris-HCl, pH 9.5
  - 100 mM NaCl
  - 50 mM MgCl<sub>2</sub>
- *NBT solution*
  - 75 mg/ml Nitroblue tetrazolium salt in 70% (v/v) dimethylformamide
- *BCIP solution*
  - 50 mg/ml 5-Bromo-4-chloro-3-indolyl phosphate (X-phosphate), in 100% dimethylformamide
- *Anti-DIG-alkaline phosphatase*
  - Anti-digoxigenin conjugated to alkaline phosphatase (Boehringer Mannheim Biochemicals)

## 15.8 ISOLATION OF $\lambda$ PHAGE DNAs BY THE LIQUID METHOD

1. For each 50 ml of bacterial culture, add 10 to 15  $\mu$ l of  $1 \times 10^5$  pfu of "plaque eluate" into a microcentrifuge tube containing 240 to 235  $\mu$ l of phage buffer. Mix with 0.25 ml of cultured bacteria and allow the bacteria and phage to adhere to each other by incubating at 37°C for 30 min.
2. Add the above mixture into a 250- or 500-ml sterile flask containing 50 ml of LB medium prewarmed at 37°C, which is supplemented with 1 ml of 1 M  $MgSO_4$ . Incubate at 37°C with shaking at 260 rev/min until lysis occurs.  
*Tips: It usually takes 9 to 11 h for lysis to occur. The medium should be cloudy after several hours of culture and then be clear upon cell lysis. Cellular debris also becomes visible in the lysed culture. There is a density balance between bacteria and bacteriophage. If the bacteria density is much over that of bacteriophage, it takes longer for lysis to occur, or no lysis takes place at all. In contrast, if bacteriophage concentration is much over that of bacteria, lysis is too quick to be visible at the beginning of the incubation, and later on, no lysis will take place. The proper combination of bacteria and bacteriophage used in step 1 will ensure success. In addition, careful observations should be made after 9 h of culture because the lysis is usually quite rapid after that time. Incubation of cultures should be stopped after lysis occurs. Otherwise, the bacteria grow continuously and the cultures become cloudy again. Once that happens, it will take a long time before lysis occurs, or no lysis takes place at all.*
3. Immediately centrifuge at 9000 g for 10 min at 4°C to spin down the cellular debris. Transfer the supernatant containing the amplified DNA library in bacteriophage particles into a fresh tube. Aliquot the supernatant, add 20 to 40  $\mu$ l of chloroform, and store at 4°C for up to 5 weeks.
4. Add RNase A and DNase I to the lambda lysate supernatant, each to a final concentration of 2 to 4  $\mu$ g/ml. Place at 37°C for 30 to 60 min.  
*Note: RNase A functions to hydrolyze the RNAs. DNase I will hydrolyze chromosomal DNA but not phage DNA that is packed.*
5. Precipitate the phage particles with 1 volume of phage precipitation buffer and incubate for at least 1 h on ice.
6. Centrifuge at 12,000 g for 15 min at 4°C and allow the pellet to dry at room temperature for 5 to 10 min.
7. Resuspend the phage particles with 1 ml of phage release buffer per 10 ml of initial phage lysate and mix by vortexing.
8. Centrifuge at 5000 g for 4 min at 4°C to remove debris and carefully transfer the supernatant into a fresh tube.
9. Extract the phage particle proteins using an equal volume of TE-saturated phenol-chloroform. Mix for 1 min and centrifuge at 10,000 g for 5 min.
10. Transfer the top, aqueous phase to a fresh tube and extract the supernatant one more time as in step 9.
11. Transfer the top, aqueous phase to a fresh tube and extract once with 1 volume of chloroform/isoamyl alcohol (24:1). Vortex and centrifuge as in step 9.

12. Carefully transfer the upper, aqueous phase containing  $\lambda$ DNAs to a fresh tube and add 1 volume of isopropanol or 2 volumes of chilled 100% ethanol. Mix well and precipitate the DNAs at  $-80^{\circ}\text{C}$  for 30 min or  $-20^{\circ}\text{C}$  for 2 h.
13. Centrifuge at 12,000  $g$  for 10 min at room temperature and aspirate the supernatant. Briefly wash the pellet with 2 ml of 70% ethanol and dry the pellet under vacuum for 10 min. Resuspend the DNA in 50 to 100  $\mu\text{l}$  of TE buffer. Measure the DNA concentration (similar to RNA measurement described previously) and store at  $4^{\circ}\text{C}$  or  $-20^{\circ}\text{C}$  until use.

### Reagents needed

- *SM buffer (per liter)*  
50 mM Tris-HCl, pH 7.5  
0.1 M NaCl  
8 mM  $\text{MgSO}_4$   
0.01% gelatin (from 2% stock)  
Sterilize by autoclaving.
- *Phage buffer*  
20 mM Tris-HCl, pH 7.4  
100 mM NaCl  
10 mM  $\text{MgSO}_4$
- *Release buffer*  
10 mM Tris-HCl, pH 7.8  
10 mM EDTA
- *Phage precipitation solution*  
30% (w/v) Polyethylene glycol (MW 8000) in 2 M NaCl solution
- *TE buffer*  
10 mM Tris-HCl, pH 8.0  
1 mM EDTA
- *TE-saturated phenol/chloroform*  
Thaw crystals of phenol in a  $65^{\circ}\text{C}$  water bath and mix with an equal volume of TE buffer. Allow the phases to separate for about 10 to 20 min. Mix 1 part of the lower phenol phase with 1 part of chloroform/isoamyl alcohol (24:1). Allow the phases to separate and store at  $4^{\circ}\text{C}$  in a light-tight bottle.
- **DNase-free RNase A**  
To make DNase-free RNase A, prepare a 10 mg/ml solution of RNase A in 10 mM Tris-HCl, pH 7.5 and 15 mM NaCl. Boil for 15 min and slowly cool to room temperature. Filter if necessary. Alternatively, RNase (DNase-free) from Boehringer Mannheim can be utilized.

## 15.9 RESTRICTION MAPPING OF RECOMBINANT BACTERIOPHAGE DNA CONTAINING THE GENOMIC DNA INSERT OF INTEREST

Once putative clones are isolated, the next logical step is to locate the gene of interest within the DNA insert, which indicate how large the gene is and where it is located

in the insert. It is necessary to have this information in order to subclone or directly sequence the gene. To obtain this information, restriction mapping should be carried out using three to four restriction enzymes. The selection of enzymes depends on the restriction enzyme sites in the vectors. For example, if  $\lambda$ GEM-11 or  $\lambda$ GEM-12 is used as the cloning vector, the mapping procedure can be performed as follows:

1. Set up, on ice, a series of single-enzyme and double enzyme digestions.


Components	Tube #1	2	3	4	5	6
Recombinant, positive phage DNA	20 ( $\mu$ g)	20	20	20	20	20
Appropriate 10 $\times$ restriction enzyme buffer	4 ( $\mu$ l)	4	4	4	4	4
<i>Eco</i> RI (10 units/ $\mu$ l)	6.7 ( $\mu$ l)	0	0	6.7	6.7	0
<i>Bam</i> HI (10 units/ $\mu$ l)	0 ( $\mu$ l)	6.7	0	6.7	0	6.7
<i>Xho</i> I (10 units/ $\mu$ l)	0 ( $\mu$ l)	0	6.7	0	6.7	6.7
Add dd.H <sub>2</sub> O to a final volume of	40 ( $\mu$ l)	40	40	40	40	40

Enzyme Used for Digestion	Tube #
<i>Eco</i> RI	1
<i>Bam</i> HI	2
<i>Xho</i> I	3
<i>Eco</i> R I + <i>Bam</i> HI	4
<i>Eco</i> R I + <i>Xho</i> I	5
<i>Bam</i> H I + <i>Xho</i> I	6

2. Incubate the reactions at an appropriate temperature for 2 to 3 h.
3. After restriction enzyme digestion, carry out electrophoresis on a 0.9% agarose gel, blot onto a nylon membrane, and perform prehybridization and hybridization using the same probe used for screening of the genomic library. Washing and detection are described in detail in Southern blotting in Chapter 7.
4. To ensure that the correct results are obtained, we recommend that steps 1 to 3 be repeated. Both primary and repeated Southern blots should have identical hybridization patterns. An example of such results is as follows:

Restriction Enzyme Digestion	Bands Observed on Gel (kb)*
<i>Eco</i> R I	20, 9, <u>10</u> , 6, 4
<i>Bam</i> H I	20, 9, <u>10</u> , <u>6</u> , 4
<i>Xho</i> I	20, 9, <u>12</u> , <u>6</u> , 2
<i>Eco</i> R I + <i>Bam</i> H I	20, 9, <u>6</u> , <u>4</u> , 2
<i>Eco</i> R I + <i>Xho</i> I	20, 9, <u>6</u> , <u>4</u> , 2
<i>Bam</i> HI + <i>Xho</i> I	20, 9, <u>6</u> , <u>4</u> , <u>2</u>

\* Hybridized bands are indicated by underlined numbers. Doublets or triplets are possible.



**FIGURE 15.4** Restriction mapping of a gene in a lambda cloning vector.

- Identify and locate the gene in the insert according to the Southern blot hybridization results and draw a restriction map (Figure 15.4). Check out the fragments based on the map as follows:

Restriction Enzyme Digestion	Bands Observed on Gel (kb)*
<i>EcoRI</i>	20, 9, <u>10</u> , 6, 4
<i>BamHI</i>	20, 9, <u>10</u> , <u>6</u> , 4
<i>XhoI</i>	20, 9, <u>12</u> , <u>6</u> , 2
<i>EcoRI</i> + <i>BamHI</i>	20, 9, <u>6</u> , <u>4</u> , 4, 4, 2
<i>EcoRI</i> + <i>XhoI</i>	20, 9, <u>6</u> , 6, 4, 2, 2
<i>BamHI</i> + <i>XhoI</i>	20, 9, <u>6</u> , <u>6</u> , 4, <u>2</u> , 2

\* Hybridized bands are indicated by underlined numbers. Doublets or triplets are possible.

In conclusion, the gene identified is 8 kb in size and is located in the middle of the insert (Figure 15.4).

- Once the size and location of the gene have been identified, purification of the gene from recombinant  $\lambda$ GEM-11 or  $\lambda$ GEM-12 may be carried out using appropriate restriction enzymes. The isolated gene can be subjected to subcloning and DNA sequencing.

## 15.10 SUBCLONING OF THE ISOLATED GENE OR DNA FRAGMENTS

Detailed protocols are described in Chapter 4.

## 15.11 CHARACTERIZATION OF THE ISOLATED DNA

Isolated DNA clones should be carefully characterized. For DNA sequencing and sequence analysis, detailed methods are given in Chapters 5 and 6.



## Troubleshooting Guide

1. *Plaques are small in one area and large in other areas in the LB plates.* This is due to the uneven distribution of the top agar mixture. Make sure that the top agar mixture is spread evenly.
2. *Too many positive clones appear in the primary screening.* The specificity of the primary antibodies is low, or the concentration is too high, or the blocking efficiency is low. Try to use IgG or an affinity-column purified antibodies and carry out different dilutions of the antibodies, and/or to increase the percentage of the blocking reagent in TBST buffer.
3. *Purple background is evident on the filter.* Color is overdeveloped. Try to stop the color reaction as soon as the desired signals appear.
4. *Unexpected larger purple spots occur.* Air bubbles may be produced when one overlays the filters on the LB plates. Make sure that no air bubbles appear underneath the filters.
5. *No signal appears at all in any plates of the primary screening plates.* The pfu numbers used for each plate may be too low. For a rare gene,  $2 \times 10^6$  pfu should be used in primary screening of the library.
6. *Signals are weak on the filters in subsequent screening.* The antibodies have low activity or color is underdeveloped.
7. *Black background appears on the filter.* The filter was partially dried, the blocking efficiency is low, or the quality of the filter is not good. Try to avoid air-drying of the filter; increase the percentage of BSA and the denatured salmon sperm DNA, and use a fresh neutral nylon membrane filter.
8. *Unexpected black spots shown on the filter.* Unincorporated  $^{32}\text{P}$ dCTP was not effectively removed. Try to use a G-50 Sephadex column to purify the labeled DNA.

## REFERENCES

1. Sambrook, J., E. F. Fritsch, and T. Maniatis. 1989. *Molecular Cloning: A Laboratory Manual*, 2nd edn. Cold Spring Harbor, NY: Cold Spring Harbor Press.
2. Wu, W. 1995. Genomic DNA Libraries. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke, 165–210. Boca Raton, FL: CRC Press.
3. Tonegawa, S., C. Brock, N. Hozumi, and R. Schuller. 1977. Cloning of an immunoglobulin variable region gene from mouse embryo. *Proceedings of the National Academy of Sciences of the United States of America* 74: 3518.
4. Saiki, R. K., D. H. Gelfand, S. Stoffel, S. Scharf, R. Higuchi, G. T. Horn, K. B. Mullis, and H. A. Erlich. 1988. Primer-directed enzymatic amplification of DNA with a thermostable DNA polymerase. *Science* 239: 487.
5. Wu, L.-L., I. Song, D. Kim, and P. B. Kaufman. 1993. Molecular basis of the increase in invertase activity elicited by gravistimulation of oat-shoot pulvini. *Journal of Plant Physiology* 142: 179.
6. Erlich, H. A. 1989. *PCR Technology: Principles and Applications for DNA Amplification*. New York, NY: Stockton Press.
7. Jones, D. H., and S. C. Winistorfer. 1993. A method for the amplification of unknown flanking DNA: Targeted inverted repeat amplification. *BioTechniques* 15: 894.



---

# 16 Mouse Stem Cells as a Model Mammalian Cell Line for Gene Expression

## 16.1 INTRODUCTION

Mouse embryonic stem (ES) cells are initially derived from inner cell mass (ICM) cells of mouse blastocyst-stage embryos, and then isolated and maintained in culture conditions. In recent years, ES cells have been applied to a variety of research fields because of their advantages over other mammalian cells.<sup>1-4</sup> Not only can ES cells be used as a model mammalian cell line for studies on gene cloning, manipulation, expression, and cell biology,<sup>2-6</sup> but they are also pluripotent cells compared with other mammalian cell lines. This multipotent feature of ES cells offers a very powerful tool for investigators and opens a broad area of research. As a matter of fact, if one wishes to investigate the potential function(s) of the gene of interest *in vitro* and *in vivo* in both cells and animals, the ES cell line is the best choice of cell line to achieve objectives. In other words, by using the ES cell line, the roles of a specific gene can be studied at the cellular level, and later transgenic animals can be generated with genetically altered expression of the gene of interest.<sup>7-9</sup> Therefore, ES cells provide invaluable hosts for gene overexpression, underexpression, and knockout.

In spite of the fact that the general culture techniques are similar to other mammalian cell lines, the growth and maintenance of ES cells need some special care. This chapter describes in detail the appropriate procedures for ES cell culture, maintenance, freezing, and thawing. We routinely use ES cells for studying the genetic alternation of the expression of the HSP27 gene. Based on our experience, we provide special tips and/or notes for the success of ES cell culture. It should be noted that although the present chapter focuses on ES culture, the general techniques can be adopted and applied to other mammalian cell cultures.

## 16.2 PROTOCOL 1. CULTURE OF ES CELLS IN MEDIA CONTAINING LEUKEMIA INHIBITORY FACTOR

*Cautions: Every single step should be carried out under sterile conditions to avoid bacteria or fungi contamination. Gloves should be worn and wiped periodically using 70% ethanol. Pipetteman and centrifuge tubes should be wiped outside with*

70% ethanol before use. Pipette tips and pipettes should be autoclaved. All solutions, buffers, and media should be sterile-filtered.

1. Coat the bottom of tissue culture dishes (e.g., Falcon 60 × 25 mm or 100 × 20 mm) or flasks (Falcon 25 cm<sup>2</sup> or 75 cm<sup>2</sup>) by adding 3 to 6 ml of 1% gelatin solution into each dish or flask. Overlay the entire bottom surface with the solution and cap the flasks or wrap dishes. Allow coating to proceed at 4°C overnight.

Note: *If culture dishes or flasks are not precoated with gelatin solution or its equivalent, ES cells cannot attach to the bottom, resulting in failure of proliferation or death.*

2. Transfer the precoated dishes or flasks to be used to a laminar flow hood and turn on the UV light. Allow them to be warmed to room temperature under the UV light for 20 to 30 min.
3. Clean the exterior of the warmed dishes or flasks with 70% ethanol and aspirate the gelatin solution. Rinse the dishes or flasks with 3 to 6 ml sterile distilled water and aspirate the water.
4. Add 3 to 6 ml of ES culture medium to each of the dishes or flasks, depending on the size of the flask or dish. Label dishes or flasks, including cell line, passage number, and date.
5. Add the appropriate number of cells into each flask or dish, depending on a specific experiment. Gently mix the cells in the medium.
6. Place the flasks or dishes in a cell culture incubator at 37°C with humidity, 5% CO<sub>2</sub>, and 95% air. For flasks, the caps should be slightly loosened so that CO<sub>2</sub> and air can get in.
7. Grow cells to an appropriate confluence with culture medium changed once every 1 to 3 days, depending on the proliferation rate of cells.

Notes and Tips:

- (1) *The striking feature of ES cells is that they form multiple layers of clones instead of monolayer cells. Because of the rapid proliferation or division rate of ES cells, they should not be allowed to grow over 30% confluence on the bottom of a dish or flask. Otherwise, almost 100% of the cells will die within 1 day or so. Thus, the cells should be monitored on a daily basis.*
- (2) *If some ES cells in a flask or dish are differentiated for some unknown reasons, the entire flask or dish should be discarded. Never try to rescue some normal cells in the flask. Otherwise, it will be difficult to obtain uniform, undifferentiated ES cells.*
- (3) *Contamination is a common problem even though great care has been taken. The cells should be checked on a daily basis. To prevent potential contamination during checking, the flasks should be tightly capped and it is recommended that the stage under a microscope be wiped with 70% ethanol before viewing the cells under the microscope. Make sure to loosen the cap of a flask before placing it back to the incubator. If a specific flask or dish is found to be contaminated with bacteria or fungi (e.g., yeast), it should be immediately treated with bleach solution and discarded.*

### Reagents needed

- *Cell lines*  
 Mouse ES cell line (D3 or R1) are available from the American Type Culture Collection (ATCC) (Rockville, MD).
- *Culture media (Gibco BRL, Gaithersburg, MD)*  
 45% (v/v) Nutrient mixture Ham's F-12 with glutamine  
 45% (v/v) Dulbecco's modified Eagle medium (DMEM) with high glucose and glutamine  
 5% Fetal bovine serum (FBS)  
 5% Newborn calf serum (NCS)  
 50 µg/ml Gentamicin sulfate as an antibiotic  
 Sterile-filter, add 1% (v/v) of diluted 2-mercaptomethanol solution (70 µl 2-mercaptomethanol in 100 ml PBS), and store the medium at 4°C until use.
- *Leukemia inhibitory factors (Gibco BRL)*  
 The cells can be maintained in the undifferentiated state by adding leukemia inhibitory factors (LIF) to the culture medium (10<sup>3</sup> units/ml).

### 16.3 PROTOCOL 2. PREPARATION OF MITOTICALLY INACTIVATED STO CELLS AS FEEDER LAYERS FOR GROWTH OF ES CELLS

1. Coat the bottom of each tissue culture dish or flask with 4 to 5 ml of 1% gelatin solution. Allow coating to proceed at 4°C overnight.
2. Transfer the coated dishes or flasks to a laminar flow hood and allow them to be warmed to room temperature under the UV light for 20 min.
3. Briefly rinse the dishes or flasks with 3 to 6 ml sterile water and aspirate the water.
4. Add 3 to 6 ml of STO cell culture medium to each dish or flask.
5. Add the appropriate number of cells (1 × 10<sup>6</sup> cells/flask) into each flask or dish. Place the flasks or dishes into a cell culture incubator at 37°C with humidity, 5% CO<sub>2</sub>, and 95% air. For flasks, the caps should be slightly loosened so that CO<sub>2</sub> and air can get in.
6. Allow the cells to grow for 5 to 7 days to form a confluent layer of cells with culture medium changed once every 3 days.
7. Replace the medium with 10 ml/flask of fresh culture medium containing 10 µg/ml of mitomycin C (Sigma Chemicals). Incubate the STO flasks for 3 to 4 h.
8. Aspirate the medium and wash the cells three times with 10 ml of PBS or fresh culture medium before being trypsinized. These cells should be used within 7 days for ES cell culture.

- *STO cell culture medium*  
90% (v/v) DMEM (low glucose)  
10% (v/v) FBS  
50 µg/ml Gentamicin sulfate as an antibiotic  
Sterile-filter then store the medium at 4°C until use.

## 16.4 PROTOCOL 3. CULTURE OF ES CELLS ON FIBROBLAST FEEDER LAYERS

ES culture described in Protocol 1 uses LIF in the culture medium to prevent cell differentiation. However, ES cells can grow on feeder cell layers such as mouse STO cells. The feeder cells can produce LIF that can keep ES cells in proliferation stage.

1. Aspirate the medium from mitotically inactivated STO feeder cell layers and add 3 to 6 ml of ES culture medium to each dish or flask. Label dishes or flasks, including ES cell line, passage number, and date.
2. Add the appropriate number of cells into each flask or dish, depending on a specific experiment.
3. Place the flasks or dishes into a cell culture incubator at 37°C with humidity, 5% CO<sub>2</sub>, and 95% air. For flasks, the caps should be slightly loosened so that CO<sub>2</sub> and air can get in.
4. Allow cells to grow to an appropriate confluence with culture medium changed once every 1 to 3 days, depending on the proliferation rate of cells.

*Tips: The drawback of using feeder layers to provide LIF for the growth of ES cells is that if the STO cells are not 100% mitotically inactivated, they will grow very well in the ES culture medium, which could make it difficult to clean them out of the ES cells.*

## 16.5 PROTOCOL 4: TRYPSINIZING, FREEZING, AND THAWING OF MAMMALIAN CELLS

### 16.5.1 TRYPSINIZING

*Note: The trypsinizing procedure is only applied to those cell lines that cells usually attach to the bottom of culture flasks or dishes. For floating cell culture such as some insect cells, trypsinizing is not necessary. Instead, directly transfer the cell suspension to the centrifuge tube, add an equal volume of culture medium, centrifuge, and carry out steps 8 to 11 as described below.*

1. Remove cell culture flasks or dishes from an incubator, tightly cover the flask, and check the health and confluence or density of cells in the flask or dish.
2. Loosen the caps of flasks and aspirate the medium from each flask or dish.

Note: *If the medium contains toxic chemicals after toxicant treatment, the medium must be collected in a special container for toxic waste disposal.*

3. Wash cells once with an appropriate volume of 1× HBSS (Gibco BRL) (3 ml/25 cm<sup>2</sup> flask or 4 ml/100 mm dish).

Note: *HBSS solution serves to remove dead cells and serum secreted from the cells during the culture. This solution is usually stored at room temperature under sterile conditions. Serum can inhibit the activity of Trypsin–EDTA at the next step and should be removed at this step.*

4. Carefully remove the solution as described in step 2.

Note: *Cells should be still attached to the bottom of the flask or dish.*

5. Add an appropriate volume of 1× Trypsin–EDTA solution (Gibco BRL) to flasks or dishes (1 to 1.5 ml/25 cm<sup>2</sup> flask or 2 ml/100 mm dish). Tighten the caps of flasks or cover the dishes and completely overlay cells with the solution with a hand. Place the flasks or dishes in a laminar flow hood for 7 to 10 min at room temperature or in culture incubator at 37°C for 5 min.

Tips: *When using flasks, cells can be detached from the bottom by gently patting the side walls of the flasks with a hand for approximately 2 min. Trypsin–EDTA solution should be stored at 4°C to reserve its maximum activity. Its function is to detach cells from the bottom of the culture flask or dish. The mechanism, however, is not well understood. We and others believe that Trypsin–EDTA acts to depolymerization of cellular microfilaments of cells, causing the cell to round up and detach from the bottom of the flask/dish.*

6. Periodically check the detachment of cells under a microscope. Cells should be round shaped and floating in Trypsin–EDTA solution.

7. Vertically place the flasks or tilt the dishes in a laminar flow hood to drain the cell solution to one side of the flask or dish. Carefully transfer the cell suspension to a sterile, plastic centrifuge tube (Falcon 15 ml or 50 ml) containing an equal volume of culture medium as the volume of Trypsin–EDTA solution added in step 5.

Note: *Pipette used for transferring should be changed for each flask or dish or different cell lines in order to avoid cell–cell mixing. Centrifuge tube should be sterile and labeled according to the labels of flasks or dishes.*

8. The centrifuge tubes should be tightly capped, balanced, placed in an appropriate centrifuge (e.g., swing-bucket centrifuge on bench), and centrifuged at 1200 g or 1000 rev/min for 5 min.

9. Carefully transfer the tubes back to laminar flow hood and gently wipe the exterior of the tubes with Kimwipe paper wetted with 70% ethanol. Gently loosen the cap of the tube and carefully aspirate the medium from the tube.

Note: *Caution should be taken at the present step. The tubes should be gently handled without vigorously disturbing the contents. The worst thing may be that if cell pellet is loosened into the media, they will be aspirated away. Furthermore, the pipette used to aspirate the medium should never*

*be inserted at the very bottom of tube where the cell pellet is. Otherwise, cells will be sucked away.*

10. Add an appropriate volume of normal culture medium to each of the tubes, then gently and thoroughly resuspend the cells using 5- or 10-ml sterile pipette.

*Note: The volume of culture medium used to resuspend cells depends on the cell density. Based on our experience with mouse stem cells and STO cells, 1,000,000 cells/ml medium should be applied. To completely resuspend cells, use a 5-ml pipette to take up the medium from the tube followed by flushing the bottom of the tube. Repeat up and down suspension approximately 20 to 25 times. In this way, more than 95% of the cells are separated from each other. The efficiency of cell resuspension can be monitored under a microscope using 5  $\mu$ l of the cell suspension. Pipette used for cell suspension should be changed for each cell sample to avoid cell contamination.*

11. Use the cell suspension to determine the cell density (Protocol 5), to split cell aliquot or to freeze back the cells, depending on the particular purpose.

### 16.5.2 FREEZE BACK

1. Resuspend the cells at step 9 above in an appropriate volume of freezing medium at approximately  $10^6$  cells/ml.
2. Label sterile freezing vials: cell line name, passage number, date, and person's name. Aliquot the cell suspension into the vials (0.5 to 1.0 ml/tube).
3. Place the vials in a Styrofoam box precooled at  $-70^{\circ}\text{C}$  freezer.  
*Tip: This step is optional. In fact, cells in the freezing medium can be directly stored at  $-140^{\circ}\text{C}$  freezer or in a liquid nitrogen tank.*
4. Store the vials in a  $-140$  or  $-180^{\circ}\text{C}$  freezer or in a liquid nitrogen tank.

### Materials needed

- *Sterile freezing vials*  
 $-70^{\circ}\text{C}$  freezer,  $-180^{\circ}\text{C}$  freezer or liquid nitrogen tank  
Styrofoam box  
Culture medium
- *Freezing medium*  
70% to 75% (v/v) culture medium  
20% (v/v) FCS  
5% to 10% (v/v) DMSO  
Filter-sterilize

### 16.5.3 THAWING AND REculture

1. Prepare culture dishes or flasks for growth of cells as described in Protocol 1.
2. Remove a vial containing the cells from the storage freezer and thaw it by holding it in a hand or in a  $37^{\circ}\text{C}$  water bath for about 3 to 6 min.



3. Once the last visible ice crystal disappears, wipe the outside of the vial with 70% ethanol and add 40 to 100  $\mu\text{l}$  of the suspension to each flask or dish.
4. Culture the cells under normal conditions as described in Protocol 1.  
*Tip: DMSO can lower the freezing point of cells to prevent ice crystals from being formed inside the cells and protect the cells during freezing. However, DMSO in the freezing medium is toxic to cells under normal culture temperature. Thus, one should change the culture medium in the flask or dish about 12 to 18 h after reculture of the frozen cells.*

## 16.6 PROTOCOL 5. CELL COUNTING AND DETERMINATION OF CELL DENSITY


1. Trypsinize and resuspend cells as described in Protocol 2.  
*Note: The volume of the culture medium for suspending the cells will be considered the total volume of cell suspension.*
2. Add 10  $\mu\text{l}$  of cell suspension to the cross in a clean hemacytometer plate.  
*Tips: The cell suspension should be gently and thoroughly mixed before immediately taking up the 10  $\mu\text{l}$ . Because cells are heavier than the culture medium, they tend to sink at the bottom of the centrifuge tube. If cells are not well suspended, the counted result of the 10  $\mu\text{l}$  cell suspension will not be the actual density of the cell suspension.*
3. Cover the cross with a clean hemacytometer coverslip.  
*Note: Place the coverslip carefully so that there are no air bubbles trapped underneath the coverslip. Otherwise, bubbles may affect cell counting.*
4. Focus cells on the plate under an inverted phase-contrast microscope and count all cells in each of the four corners in the hemacytometer plate using a counter as an aid.  
*Tips: Counting must be accurate. Any cells located outside the four corner areas should not be counted. Only cells inside the four corners are counted. Each corner consists of 16 squares as shown below and the counting directions are recommended. Cells in any clusters should be counted as accurately as possible (Figure 16.1).*
5. Calculate the cell density of cell suspension as follows:

$$\text{Total \# of cells in 4 corners} / 4 \times 10^4 = \# \text{ of cells/ml cell suspension}$$

6. Calculate total cells of the cell suspension as follows:

$$\text{Cells/ml} \times \text{volume of the cell suspension} = \text{total cells in the suspension}$$

7. In case of cell treatment, and/or cell splitting/subculture that mandates an equal number of cells per culture flask or dish, calculate the volume of the cell suspension containing a given number of cells for each flask/dish using the cell density determined in step 5.



**FIGURE 16.1** Diagram of cell counting in four corners of hemacytometer plate.

*Tips: For example, if total cells in four corners is 100, the cell density will be  $100/4 \times 10^4 = 2.5 \times 10^5$  cells/ml cell suspension. If 10,000 cells are needed for each flask or dish, the volume of the cell suspension will be calculated:  $2.5 \times 10^5$  cells/ml cell suspension =  $2.5 \times 10^2$  cells/ $\mu$ l cell suspension  $10,000$  cells/ $2.5 \times 10^2$  cells/ $\mu$ l =  $4 \mu$ l cell suspension per flask or dish.*

- Aliquot the volume of cell suspension calculated at step 7 into each culture flask or dish with the same size and the same volume of the appropriate culture medium.

*Tips: The cell suspension should be gently and thoroughly mixed and immediately take up an appropriate volume of the cell suspension into each flask as described at step 2. We strongly recommend to use a Pipetteman attached with an appropriate volume of tip to aliquot the cell suspension. The tip should be changed for each aliquot to normalize the number of cells for each culture flask or dish. Because cells tend to sink at bottom, transferring the total cell suspension into 1-, 2-, or 5-ml syringe/pipette followed by aliquot of an appropriate volume into the flask may not work well. Otherwise, the total number of cells in each flask will be dramatically different.*

### Troubleshooting Guide

- ES cells do not attach to the bottom of culture dish or flask. One causal factor is that the flask or dish may not be well coated with gelatin solution. Unlike other mammalian cells, ES cells mandate precoated culture flask or dish for culture. Assuming that culture conditions are normal, another possible factor is that the DMSO in the frozen cells' suspension, in case of*

thawing and reculture of the cells, might not be removed. So, make sure to follow the preceding protocols to replace the old medium containing DMSO for freezing.

2. *Cells look sick or some of them are being differentiated.* There are three possibilities: (a) Cell culture conditions are altered. For example, some components may be missed. Temperature in the incubator may be above 37°C and there may be no water in the water pan. (b) If culture conditions are normal, it is most likely that the LIF provided may be not sufficient or its activity is gone. Try to use some fresh feeder layers or commercial LIF. (c) If items (a) and (b) are not the case, check the cell passage number. If the passage number is more than 50, it is recommend that one use a lower passage number of ES cells.
3. *Numerous cell colonies float in the medium.* This is certainly due to over-density or overculture of the cells. ES cells proliferate very fast. The medium should be changed once every 2 days and monitored on a daily basis. In general, if the initial cell density in the 100-mm culture dish is 10,000 cells, under normal culture conditions, they should be split or frozen back after 7 days' culture. Once many floating colonies are visible, it is a good idea to discard the whole flask or dish because some ES cells have undergone differentiation and cannot be used for subsequent passages.
4. *More than 50% of cells disappear after being washed, trypsinized, and centrifuged.* It is most likely that cells have been washed or trypsinized for too long. It is also possible that, after centrifugation, the cells were kept in the suspension medium for too long before being frozen back or placed in a culture incubator. If this is the case, a lot of cells are somehow lysed. It is a good practice to handle the procedures of rinsing, trypsinizing, and resuspending as fast as possible.

## REFERENCES

1. Wu, W., and M. J. Welsh. 1996. Expression of the 25-kDa heat-shock protein (HSP27) correlates with resistance to the toxicity of cadmium chloride, mercuric chloride, *cis*-platinum(II)-diammine dichloride, or sodium arsenite in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Toxicology and Applied Pharmacology* 141: 330–339.
2. Capecchi, M. R. 1989. Altering the genome by homologous recombination. *Science* 244: 1288.
3. Mansour, S. L., K. R. Thomas, and M. R. Capecchi. 1988. Disruption of the proto-oncogene *int-2* in mouse embryo-derived stem cells: A general strategy for targeting mutations to non-selectable genes. *Nature* 336: 348.
4. Riele, H. T., E. R. Maandag, and A. Berns. 1992. Highly efficient gene targeting in embryonic stem cells through homologous recombination with isogenic DNA constructs. *Proceedings of the National Academy of Sciences of the United States of America* 89: 5128.
5. Schorle, H., T. Holtschke, T. Hunig, A. Schimpl, and I. Horak. 1991. Development and function of T cells in mice rendered interleukin-2 deficient by gene targeting. *Nature* 352: 621.

6. Tybulewicz, V. L. J., C. E. Crawford, P. K. Jackson, R. T. Bronson, and R. C. Mulligan. 1991. Neonatal lethality and lymphopenia in mice with a homozygous disruption of the *c-abl* proto-oncogene. *Cell* 65: 1153.
7. Weinstock, P. H., C. L. Bisgaier, K. A. Setala, H. Badner, R. Ramakrishnan, S. L. Frank, A. D. Essenburg, R. Zechner, and J. L. Breslow. 1995. Severe hypertriglyceridemia, reduced high density lipoprotein, and neonatal death in lipoprotein lipase knockout mice. *Journal of Clinical Investigation* 96: 2555.
8. Michalska, A. E., and K. H. A. Choo. 1993. Targeting and germ-line transmission of a null mutation at the metallothionein I and II loci in mouse. *Proceedings of the National Academy of Sciences of the United States of America* 90: 8088.

---

# 17 Strategies for Gene Double Knockout

## 17.1 INTRODUCTION

The mutation or targeting of a specific gene is one of the most attractive approaches in which scientists can gain insight into the potential function(s) of the gene of interest.<sup>1-5</sup> To genetically alter the expression of a specific gene and explore the potential roles of the gene, strategies for stable overexpression or underexpression of a specific gene are widely employed.<sup>4-7</sup> Nonetheless, up- or down-regulation of the expression of the gene of interest can only reveal the partial function of the gene. To prove the roles of an endogenous gene well, one may need to utilize another powerful tool—gene knockout or gene targeting by homologous recombination technology. This genetic approach can provide the highest level of control over producing mutations in an endogenous gene. Hence, it becomes an invaluable technique for investigators to make null mutations of transgenic mice to demonstrate *in vivo* gene function.<sup>9-11</sup> This will allow one to address questions as to what a gene does in an organism, what it does for the body, and when and where in development a gene is mandated, using an animal model.


Previous gene targeting method has two disadvantages.<sup>3-6</sup> One is that the targeted gene is usually a single knockout in one chromosome in cultured embryonic stem (ES) cells isolated from a brown mouse strain. The ES cells carrying a single-copy mutation of a specific gene are inserted by microinjection into young embryos isolated from a black female mouse strain. The black strain lacks the *agouti* gene that generates a brown coat phenotype. Hence, using the coat color as a selective marker, any newborns with brown shading intermixed with black are considered to be chimeras because they contain cells derived from two different strains of mice. In other words, this first generation (F1) of mice produced from the single knockout clones are heterozygous mutants. To obtain homozygous mice, all resulting chimeric males need to be back-crossed with black (non-*agouti*) females or heterozygous F1 mice should be interbred to produce the F2 generation. The germ line transmission of F2 will be scored according to coat pigment. Any pure or solid brown F2 mice are most likely the target mutants with a double knockout in both chromosomes, which should be subjected to detail characterization.<sup>9-14</sup> Certainly, this approach is time-consuming and costly to obtain homozygous or double-knockout mice. Another major concern with the previous gene knockout strategy is the potentially lethal effect of the targeted gene. In some cases, gene knockout results in early death of embryos and young animals or in morphologically and functionally abnormal offspring such as blind or otherwise handicapped animals.<sup>9-11</sup> These two limitations of the previous method greatly restrict the application of gene knockout techniques. As a matter of

fact, numerous grant proposals for targeting of some crucial genes have encountered difficulties in obtaining approval because of potentially lethal concerns.

To overcome these limitations, a novel strategy was developed by which gene double knockout strategy can be achieved at the ES cell level instead of waiting for the F2 generation. An even more powerful argument is that, in order to address the lethal concerns, the homozygously targeted gene can be kept being silent until it is activated. It is hoped that this new strategy will expand the areas of applications tremendously. This chapter describes in detail the strategy for generating null mutant mice. These protocols can be readily adapted and applied to cells or animals other than ES cells and mice.

## 17.2 OVERVIEW AND GENERAL PRINCIPLES OF STRATEGIES: GENE DOUBLE-KNOCKOUT AND TEMPORAL SILENCE

The primary principle of the gene double knockout or homologous recombination is that a manipulated gene or fragment of genomic DNA transferred into a mammalian cell can locate and recombine with the endogenous homologous sequences in both chromosomes in cultured cells. As outlined in Figure 17.1, gene double knockout starts with manipulation of the gene to be targeted. One approach is to mutate the cloned gene of interest by deletion of one or more exons that are replaced with a selectable marker gene, such as a neomycin resistance (*neo<sup>r</sup>*) or hygromycin resistance (*hyg<sup>r</sup>*) gene in a targeting vector. Another strategy is to use isogenic DNA



**FIGURE 17.1** Diagram of gene knockout procedure in mouse ES cells and transgenic mice.

to obtain a high efficiency of gene targeting.<sup>15</sup> The 5'- and 3'-end isogenic DNA fragments with deletion of the entire gene or exons of interest flank a marker gene (e.g., *neo<sup>r</sup>* or *hyg<sup>r</sup>*) in a targeting vector. As illustrated in Figure 17.1, each targeting vector usually contains two marker genes for drug double selections. One is the *neo<sup>r</sup>* or *hyg<sup>r</sup>* gene for positive selection of replacement of endogenous homologous DNA sequences. The other is the Herpes simplex virus *thymidine kinase* gene (HSV-*tk*) located immediately adjacent to the target sequence for negative selection of random insertion. The core portion of a typical targeting construct contains a "specific DNA fragment A + *neo<sup>r</sup>* or *hyg<sup>r</sup>* gene + specific DNA fragment B + *tk* gene," forming a "gene targeting sandwich." These "sandwiches" containing the mutated gene or DNA fragment are then introduced into mouse ES cells (D3 or R1 cell line) followed by selection of stably transfected ES cells using the drugs, G418/ganciclovir or hygromycin B/ganciclovir. If all goes well, three groups of cells will be selected based on three specific principles. One group will be the cells that contain no insertion of "gene targeting sandwiches." These cells are killed by G418 or hygromycin B during the selection because they lack the *neo<sup>r</sup>* or *hyg<sup>r</sup>* gene. Another group of cells has a random insertion of an entire "gene targeting sandwich." As a result, these cells are very sensitive to and are killed by the addition of ganciclovir, the antiherpes drug, to the cell culture medium, which is attributable to the *tk* gene in the sandwich. Ultimately, the survival cells are those whose genomic DNA contains the target insertion by homologous recombination. When homologous recombination occurs, the endogenous homologous sequence is replaced by the majority of the "gene targeting sandwich" except for the *tk* gene, which includes a "specific DNA fragment A + the *neo<sup>r</sup>* or *hyg<sup>r</sup>* gene + the specific DNA fragment B." However, the *tk* gene, lying outside the region of matching sequences, does not integrate into the chromosome of the cell and is degraded in the cell.

According to probability analysis, the cells that carry integrated homologous DNA are extremely rare, occurring at a frequency of approximately 1 per 10<sup>5</sup> for only a single copy knockout. For a gene double knockout to occur in ES cells, the stably transfected cells need to be subjected to a second round of transfection with exactly the same "gene targeting sandwich" or a different "sandwich" containing another positive selection marker gene. In other words, if the positive selection gene in the first round of transfection is *neo<sup>r</sup>* or *hyg<sup>r</sup>*, then *hyg<sup>r</sup>* or *neo<sup>r</sup>* gene should be used as the positive selection marker in the second round of transfection. For double transfection, the survival cells after the first round of drug selection may not be individually isolated and expanded. The mixed cell populations can be used directly for retransfection. When using the same "gene targeting sandwich" for a second round of gene targeting, one should use a double dose of an appropriate drug for positive selection. However, the dose of ganciclovir may be the same as for the first round of selection. The primary principles of the second selection are quite similar to those for the first selection. If all goes well, most of the survival cells after the second selection should contain a double knockout or homologous recombination in both chromosomes that carry both copies of the targeted gene.

It is strongly recommended that two different "gene targeting sandwiches" containing two different selectable marker genes be constructed. These sandwiches (e.g., *neo<sup>r</sup>* and *hyg<sup>r</sup>* gene sandwiches) can be mixed at a ratio of 1:1 and simultaneously

introduced into ES cells, eliminating a second round of transfection. The advantage of this approach is that the ES cells can be kept at the lowest passage number possible, and that the efficiency of generating transgenic mice will be enhanced substantially. After transfection, the stably transfected cells can be obtained by triple selections using G418, hygromycin B, and ganciclovir in the culture medium. If all goes well, only cells that contain the doubly targeted gene by homologous recombination in both chromosomes can survive in a triple selection medium.

After the drug selections, the individual cell clones or cell lines should be developed or expanded from single cells in order to generate homogeneous populations of cells. The obtained homologous recombinant cell lines are then subjected to characterization by Southern blotting, polymerase chain reaction (PCR) screening, northern blotting, and/or western blotting.<sup>8</sup> At this point, if there is no need to be concerned with the potential lethal effects of gene knockout, some of the cells may be transferred into the cavity of blastocyst-stage embryos to generate transgenic mice. On the other hand, we offer a strategy to overcome lethal concerns even though no obvious lethal effects can be observed in cultured ES cells. The cells with a double knockout gene are used as the recipients for a third transfection with a DNA construct containing the entire coding region of the cDNA of the targeted gene. The expression of the cDNA is driven by an appropriate inducible promoter such as RSV-LTR enhancer linked to the dexamethasone-inducible MMTV-LTR promoter. In this way, the double knockout gene can be temporarily rescued, or kept silent, by inducing the expression of the cDNA with dexamethasone. However, the effects of the targeted gene can be readily activated by stopping the use of the inducer molecules. Therefore, the lethal effect of the knocked out gene should be less or not effective until it is turned on. It should be noted that a different selectable gene such as the *Hprt* gene should be included in the inducible DNA construct so that stably transfected cells can be selected with HAT-containing medium. These cells should be characterized to ensure that the expression of the introduced cDNA occurs before initiating development of mice.

As soon as the ES cells contain the doubly knocked-out gene, the cells are ready to be injected into the cavities of young embryos at the blastocyst stage, which are isolated from an appropriate female mouse strain (e.g., black coat strain). To keep the potentially lethal effect of gene knockout silent, an inducible chemical such as dexamethasone should be delivered into the female and/or the cavity at an appropriate concentration based on induction curve. The manipulated embryos are then reimplanted into recipient female mice to generate mice. F1 mice can be interbred to maintain the colonies that carry the null gene. These offspring should be characterized in detail by Southern blotting, northern blotting, western blotting, and immunocytochemistry. More importantly, the potential functions of the null gene should be analyzed in the animals.

### 17.3 MANIPULATION OF THE SPECIFIC GENE TO BE TARGETED

For gene targeting or knockout, genomic DNA should be manipulated before making the gene knockout construct. This section describes in detail three protocols that have been used in our other laboratories.<sup>12,13</sup>




### 17.3.1 PROTOCOL A. DISRUPTION OF AN EXON IN A SPECIFIC GENE

Disruption of an exon of the gene to be targeted is a traditional technique for targeting mutations. The basic principle of this strategy is to insert a selectable marker gene such as *neo<sup>r</sup>* gene in the middle exon of the gene of interest. After homologous recombination in the genome of mouse ES cells, the disrupted protein produced by the mutated gene cannot function as the native gene product.


To disrupt an exon, a cloned DNA sequence of a chosen locus can first be digested with an appropriate restriction enzyme followed by insertion of the *neo<sup>r</sup>* gene at the cut site (Figure 17.2). Detailed protocols for appropriate restriction enzyme digestion and DNA ligation are given in Chapter 4.

### 17.3.2 PROTOCOL B. DELETION OF EXONS OF A SPECIFIC GENE

Although disruption of an exon in a gene can create a functional mutation of the gene of interest, the efficiency of disorder may not be sufficient in some cases. To overcome this limitation, deletion of one or more exons in the gene of interest has been widely utilized. The primary principle of this technique is to remove some exons from a cloned gene. In our experience, adjacent intron(s) can also be deleted simultaneously to obtain a high efficiency of gene targeting. The deleted region is then replaced by a selectable marker gene (Figure 17.3). One should refer to Chapter 4 (Subcloning of Genes or DNA Fragments) for appropriate protocols for restricting enzyme digestion of DNA and for DNA ligation.



**FIGURE 17.2** Mutation of gene X by insertion of a marker gene (*neo*) and a reporter gene (*Lac Z*) into exon 2.




**FIGURE 17.3** Mutation of gene X by deletion of exons 2 and 3 and by replacement of the exons with a marker gene (*neo*) and a reporter gene (*Lac Z*).

### 17.3.3 PROTOCOL C. PREPARATION OF ISOGENIC DNA BY PCR

This is the strategy used to obtain the highest possible efficiency of gene knockout or DNA homologous recombination. We have developed a method for the preparation of isogenic DNA fragments from 129 SVJ mouse genomic library (Stratagen) by PCR techniques (Figure 17.4). Unlike exon disruption or deletion described in Protocol A (Section 17.3.1) and Protocol B (Section 17.3.2), the major principle of the isogenic DNA approach is the exclusion of all exons and introns in the gene to be knocked out. The excluded exons and introns are replaced by a selectable marker gene (e.g., *neo<sup>r</sup>*). During homologous recombination, exogenous isogenic DNA flanking the gene with no exons and introns will locate and recombine with endogenous isogenic DNA or genes. If all goes well, the targeted gene will express no product and becomes a completely null gene. Thus, the potentially functional leaking that occur when using the exon disruption or deletion approach is avoided using the isogenic DNA strategy.

#### 17.3.3.1 Design of Two Pairs of Primers

As illustrated in Figure 17.4, two pairs of primers should be designed. The forward primer 1 (FP1) is designed based on the sequence in the T3 promoter region of the cloned vector. The reverse primer 1 (RP1) is based on the known sequence in the 5' untranslated region (5'-UTR) of cDNA or the upstream region of the first exon. The design of FP2 is based on the known sequence in the 3' untranslated region (3'-UTR) or the downstream region of the last exon of the gene to be targeted. RP2 is chosen from the T7 promoter region in the cloned vector. It is extremely important that each pair of primers be carefully designed to anneal with two template DNA strands that are complementary to each other. If two primers are annealed with the same DNA



**FIGURE 17.4** PCR amplification of isogenic DNA fragments for targeting of gene X by replacement. E1 to E3, exons 1 to 3; I1 to I2, introns 1 to 2; FP1, forward primer 1; RP1, reverse primer 1; FP2, forward primer 2; RP2, reverse primer 2. T3 and T7 are promoters built in cloning vector at sites adjacent to multiple cloning site (MCS) for insertion of genomic DNA.

strand, no PCR products will be produced. The primers should be analyzed with an appropriate computer program before they are used in PCR. We routinely use the Oligo Version 4.0 or CPrimer f to check the quality of the primers, including GC contents,  $T_m$  value, potential formation of intraloops/dimers and interduplexes of the primers, and potential annealing between the primers and the region flanking by the primers. Based on previous studies, the length of isogenic DNA fragments plays a significant role in the success of gene targeting. It has been demonstrated that isogenic DNA fragments of 2 to 7 kb in length are required for gene knockout. To obtain a large size of DNA fragments, the length of the primers is also critical. In general, primers should be >27 bases with <60% GC contents. The first base at the 5'- or the 3'-end should be G or C followed by A or T for an efficient annealing. No more than four bases of introprimer or interprimer complementary are allowed. If all goes well, different sizes of 5'- or 3'-isogenic DNA fragments may be amplified because different portions of the gene to be targeted may be cloned in different vector molecules in the genomic library. These fragments should be purified by agarose gel electrophoresis. In our experiments, the following primers are designed to obtain isogenic DNA fragments for HSP25 gene targeting.

- For 5'-isogenic DNA  
 FP1 (33-mer): 5'-CATGCCAGAGCTCTAATACGACTCACTATAGG-3'  
 RP1 (31-mer): 5'-CTCTCGAGTTGGCGTGCAAGGCTGAGGATC-3'
- For 3'-isogenic DNA fragments  
 FP2 (35-mer): 5'-GATCTAGAGTGCCTCTTTTGATACATACATTTAC-3'  
 RP2 (34-mer): 5'-GAGAATTCGCTCAATTAACCCTCACTAAAGGGAG-3'

### 17.3.3.2 Amplification of 5'- and 3'-Isogenic DNA Fragments by PCR

- (a) Place two 0.5-ml thin-walled microcentrifuge tubes (Boehringer Mannheim) on ice and set up PCR reaction mixture by adding the following components to the appropriate tubes in the order shown:

#### *Tube A*

10× amplification buffer	4 µl
Mixture of four dNTPs (2.5 mM each)	5 µl
Forward primer 1 (FP1) (3 µM in dd.H <sub>2</sub> O)	4 µl
Reverse primer 1 (RP1) (3 µM in dd.H <sub>2</sub> O)	4 µl
Genomic library DNA (3–4 µg in dd.H <sub>2</sub> O) (e.g., 129 SVJ mouse genomic library)	2 µl
3% (v/v) DMSO or formamide in case of GC-rich DNA template	1.2 µl
<u>Taq DNA polymerase</u>	4 units
Add dd.H <sub>2</sub> O to a final volume of	40 µl

#### *Tube B*

10× amplification buffer	4 µl
Mixture of four dNTPs (2.5 mM each)	5 µl
Forward primer 2 (FP2) (3 µM in dd.H <sub>2</sub> O)	4 µl
Reverse primer 2 (RP2) (3 µM in dd.H <sub>2</sub> O)	4 µl
Genomic library DNA (3–4 µg in dd.H <sub>2</sub> O) (e.g., 129 SVJ mouse genomic library)	2 µl
3% (v/v) DMSO or formamide in case of GC-rich DNA template	1.2 µl
<u>Taq DNA polymerase</u>	4 units
Add dd.H <sub>2</sub> O to a final volume of	40 µl

- (b) Overlay the mixture in each tube with 20 µl of light mineral oil to prevent evaporation of the sample.  
 (c) Program a PCR thermocycler according to the manufacturer's instructions.

Cycle #	Denaturation	Annealing	Extension	Additional Elongation
First	94°C, 3 min	60°C, 30 s	70°C, 4 min	
2–34	94°C, 30 s	60°C, 30 s	70°C, 4 min	20 s per cycle
35	94°C, 30 s	60°C, 30 s	70°C, 15 min	

Finally, hold at 4°C until the sample is removed.

- (d) Carefully transfer the reaction mixture underneath the mineral oil using a pipette attached with a 100-µl tip. Adjust the pipette volume to 40 µl. Press the top of the pipette to its first stop position, hold it, and carefully insert the tip into the bottom of the tube. Then slowly take up the liquid underneath the oil phase. Slowly withdraw the tip out of the oil layer and wipe off the outside of the tip with a clean piece of tissue, and transfer the PCR sample to a

fresh tube. Alternatively, the oil layer can be removed first, leaving the PCR sample in the tube. However, the oil layer may not be completely removed. Once this is done, the amplified DNA products should be analyzed and purified by agarose gel electrophoresis.

*Tips: In addition to those described under Design of Two Pairs of Primer (Section 17.3.3.1) the following points are very helpful for the success of large size of PCR products.*

- *Concentration of  $MgCl_2$  in PCR 10 $\times$  buffer: 18 mM for 1- to 25-kb PCR products and 22 mM for 15- to 3-kb PCR products.*
- *In case of GC-rich sequence (GC contents > 65%), 3% (v/v) of DMSO or formamide should be added to the PCR cocktail. We have found that the addition of DMSO or formamide helps a great deal.*
- *dNTP concentration: 300 to 400 nM for 1- to 25-kb fragments and 500 nM for <20-kb fragments as the final or working concentration.*
- *Oligonucleotide primers should be precipitated to remove any salt. The working concentration of each primer should be 250 to 300 nM.*
- *DNA template should be highly pure with a ratio of 1.85 to 2.0 at  $A_{260}$  nm/ $A_{280}$  nm. The working concentration is 350 to 400 ng.*
- *Taq polymerase plays a major role in DNA amplification by PCR. A high quality and high fidelity of Taq polymerase are required for obtaining long-length PCR products for gene targeting. Based on our experience, we recommend the Expand<sup>TM</sup> Long Template PCR System or Tth DNA polymerase or High Fidelity Taq Polymerase (Boehringer Mannheim). All of these enzymes generate single-base 5'-A overhangs to PCR products.*
- *Denaturing temperature needs to be 93 to 94°C. Except for the first cycle, 30 s of denaturation should be used for subsequent cycles. Longer denaturation at or above 94°C may cause DNA breaks.*
- *Annealing temperature should be 2 to 3°C above the  $T_m$  temperature of primers.*
- *Extension temperature should be 5 to 8°C above the annealing temperature. Starting from the second cycle, a 20-s of extra extension is recommended.*

## Materials needed

- A thermocycler
- Thin-walled microcentrifuge tubes (0.5 ml)
- Pipets or pipetman (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
- Sterile pipette tips (0 to 200  $\mu$ l, 0 to 1000  $\mu$ l)
- Taq DNA polymerase
- Primers
- DNA templates
- 10 $\times$  PCR amplification buffer
  - 0.5 M Tris-HCl, pH 9.2
  - 18 mM  $MgCl_2$
  - 0.14 mM  $(NH_4)_2SO_4$

- *10× PCR amplification buffer for GC-rich templates*
  - 0.5 M Tris–HCl, pH 9.2
  - 18 mM MgCl<sub>2</sub>
  - 0.14 mM (NH<sub>4</sub>)<sub>2</sub>SO<sub>4</sub>
  - 3% DMSO (v/v) or 3% (v/v) formamide

### 17.3.3.3 Electrophoresis of PCR Products

- (a) Clean an appropriate gel apparatus thoroughly by washing it with detergent; completely wash out the detergent with tap water and rinse with distilled water three to five times.
- (b) Prepare an agarose gel mixture in a clean bottle or a beaker as follows:

1× TBE or TAE buffer	30 ml (minigel)
Agarose (0.5% to 0.7%, w/v)	0.15 to 0.21 g

Note: *1× TBE or TAE buffer may be diluted from 5× TBE or 10× TAE stock solution in sterile dd.H<sub>2</sub>O. Because the agarose is <1%, its volume can be ignored when calculating the total volume.*

- (c) Place the bottle with the cap loose or beaker in a microwave oven and slightly heat the agarose mixture for 1 min. Briefly shake the bottle to rinse any agarose powder stuck to the wall. To completely melt the agarose, carry out gentle boiling for 1 to 3 min, depending on the volume of the agarose mixture. Gently mix, open the cap, and allow the mixture to cool to 50 to 60°C at room temperature.

- (d) While the gel mixture is cooling, seal a clean gel tray at the two open ends with a tape or gasket and insert the comb in place. Add 1 µl of ethidium bromide (EtBr, 10 mg/ml in dd.H<sub>2</sub>O) per ml of agarose gel solution at 50 to 60°C. Gently mix and slowly pour the mixture into the assembled gel tray and allow the gel to harden for 20 to 30 min at room temperature.

Caution: *EtBr is a mutagen and a potential carcinogen and should be handled carefully. Gloves should be worn when working with this material. The gel running buffer containing EtBr should be collected in a special container for toxic waste disposal.*

Note: *The function of EtBr is to stain DNA molecules by interlacing between the complementary strands of a double strand of DNA or in the regions of secondary structure in the case of ssDNA. It will fluoresce orange when illuminated with a UV light. The advantage of using EtBr in a gel is that DNA bands can be stained and monitored with a UV lamp during electrophoresis. During electrophoresis, the positively charged EtBr moves toward the negative pole, but the negatively charged DNA molecules migrate toward the positive pole. A drawback, however, is that the running buffer and gel apparatus are likely to become contaminated with EtBr. Thus, an alternative way is to stain the gel after electrophoresis is completed. The gel can be stained with EtBr solution for 10 to 30 min, then followed by washing it in distilled water for 3 to 5 min. Or, to minimize the amount of EtBr needed, 1 µl of EtBr (1 mg/ml in dd.H<sub>2</sub>O) can be added into each 10 µl of DNA sample.*

- (e) Slowly and vertically pull the comb out of the gel and remove the sealing tape or gasket from the gel tray. Place the gel tray in an electrophoresis apparatus and add a sufficient volume of 0.5× TBE or 1× TAE buffer to the apparatus until the gel is covered to a depth of 1.5 to 2 mm above the gel.

*Note: The comb should be slowly and vertically pulled out from the gel because any cracks occurring inside the wells of the gel will cause sample leaking when the sample is loaded. The top side of the gel where wells are located must be placed at the negative pole in the apparatus because the negatively charged DNA molecules will migrate toward the positive pole. If any wells contain visible bubbles, they should be flushed out of the wells using a small pipette tip to flush the buffer up and down the well several times. Bubbles may adversely influence the loading of the samples and the electrophoresis. The concentration of TBE or TAE buffer should never be less than 0.2×. Otherwise, the gel may melt during electrophoresis. Prerunning the gel at a constant voltage for 10 min is optional.*

- (f) Add 5× loading buffer to the DNA sample and to the DNA standard markers to a final concentration of 1×. Mix and carefully load DNA standard markers (0.2 to 2 µg/well) into the very left-hand or the right-hand well, or into both left- and right-hand wells of the gel. Carefully load the samples, one by one, into appropriate wells in the buffer-submerged gel.

*Notes: (1) One should not insert the pipette tip all the way down to the bottom of a well, because this will likely cause sample leaking and contamination. The tip containing the DNA sample should be vertically positioned at the surface of the well, stabilized with a finger of the other hand, and slowly loaded into the well. (2) The loading buffer should be at least 1× to final concentration; otherwise, the sample may float out of the well.*

- (g) After all samples are loaded, estimate the length of the gel between the two electrodes and set the power at 5 to 15 V/cm gel. Allow electrophoresis to proceed for 2 h or until the first blue dye reaches a distance of 1 cm from the end of the gel. If overnight running of the gel is desired, the total voltage should be determined empirically.

- (h) Stop electrophoresis of the gel and visualize the DNA bands in the gel under UV light. Photograph the gel with a Polaroid camera.

*Caution: Wear safety glasses and gloves for protection against UV light.*

*Notes: It is recommended that pictures be taken with a fluorescence ruler placed beside the gel. A short exposure is needed to obtain sharp band(s) and a clear background. A longer exposure is needed to visualize some very weak band(s). For PCR products, white and sharp band(s) should be visible in a black background.*

### Materials needed

- Gel casting tray
- Gel combs

- Electrophoresis apparatus
- *DC power supply*  
Small or medium size DNA electrophoresis apparatus depending on the number of samples to be run
- Ultrapure agarose powder
- *5× TBE buffer*  
600 ml dd.H<sub>2</sub>O  
0.45 M boric acid (27.5 g)  
0.45 M Tris base (54 g)  
10 mM EDTA (20 ml 0.5 M EDTA, pH 8.0)  
Dissolve well after each addition. Add dd.H<sub>2</sub>O to 1 l. Autoclave.
- *10× TAE buffer*  
600 ml dd.H<sub>2</sub>O  
400 mM Tris acetate (48.4 g Tris base, 11.42 ml glacial acetic acid)  
10 mM EDTA (20 ml 0.5 M EDTA, pH 8.0)  
Dissolve well after each addition. Add dd.H<sub>2</sub>O to 1 l. Sterile-filter.
- *Ethidium bromide*  
10 mg/ml in dd.H<sub>2</sub>O, dissolve well and keep in dark or brown bottle at 4°C.  
Caution: EtBr is extremely toxic and should be handled carefully.
- *5× Loading buffer*  
50% glycerol  
2 mM EDTA  
0.25% Bromphenol blue  
0.25% Xylene cyanol  
Dissolve well and store at 4°C.
- *10× TE buffer*  
100 mM Tris-HCl, pH 8.0  
10 mM EDTA

#### 17.3.3.4 Purification of PCR Bands from the Agarose Gel and Ligation of Isogenic DNA Fragments with a Selectable Marker Gene

Once the isogenic DNA fragments are separated from agarose gels, they can be eluted out from the gel matrix and ligated with a selectable marker gene as shown in Figure 17.4. Detailed protocols for DNA purification from an agarose gel, appropriate restriction digestion, and DNA ligation are described in Chapter 4.

### 17.4 DESIGN AND SELECTION OF VECTORS AND MARKER GENES FOR GENE DOUBLE KNOCKOUT AND TEMPORAL SILENCE

Plasmid-based vectors are commonly used for gene knockout or gene targeting. To achieve a double knockout of both copies of a specific gene in two chromosomes in cultured cells and to keep the targeted gene silent, three types of vectors need to be







FIGURE 17.5 Diagram of a standard vector for gene knockout.

chosen. Their structural and functional similarities and differences are described as follows.

#### 17.4.1 TYPE A. *NEO<sup>R</sup>* GENE VECTOR FOR THE FIRST COPY OF GENE KNOCKOUT

This vector is designed for single-copy knockout of the gene of interest. Its necessary components and functions are illustrated in Figure 17.5.

1. Plasmid backbone includes *f1 ori* for replication of the plasmid, ColE1 for a high copy number of the plasmid, and ampicillin gene for the selection of bacterial transformants.
2. The *neo<sup>r</sup>* gene with its own promoter, pA, and splicing region. This marker gene plays a key role in selection of single-copy targeted gene following homologous recombination.
3. The *Lac Z* gene with its own promoter, pA, and splicing region is linked adjacent to the *neo* gene. This reporter gene allows one to stain targeted cells, embryos, and tissues from adult mice.
4. Cloning sites at both ends of the *neo-lac Z* gene cassette are used for insertion of 5'- and 3'-portions of the gene to be targeted.
5. The *hsv-tk* gene is adjacent to a cloning site. The function of this gene is to serve as a negative selection marker. If homologous recombination occurs, this gene should be spliced out and degraded in the cell. Since the cell does



**FIGURE 7.6** Diagram of a standard vector for gene knockout.


not contain this gene, the cell is resistant to ganciclovir-containing medium. However, if random insertion takes place instead of homologous recombination and since the cell has *tk* gene, the cell will be sensitive to and killed by ganciclovir.

#### 17.4.2 TYPE B. *HYG<sup>R</sup>* GENE VECTOR FOR THE SECOND COPY OF GENE KNOCKOUT

Structurally, this type of vector is almost the same as type A except that the positive selection marker gene is replaced by the *hyg<sup>r</sup>* gene (Figure 17.6). In case of homologous recombination, the cells should be resistant to both hygromycin B and ganciclovir in the culture medium. Nonetheless, if cells are transfected only with this type of vector with an insertion of the gene to be targeted, the homologous recombination is usually a single copy of gene knockout. However, if cells are simultaneously transfected with both type A and B vectors, each with an insertion of the gene to be knocked out, the very rare homologous recombination is most likely double knockout of the gene using triple selection with G418, hygromycin B, and ganciclovir in the culture medium.

#### 17.4.3 TYPE C. *HYRT<sup>R</sup>* GENE VECTOR FOR KEEPING THE DOUBLE KNOCKOUT GENE SILENT

To avoid potential lethal effects of the targeted gene, it may be necessary to keep the double knockout of the gene silent until it is activated. To achieve this objective, the cells containing a gene double knockout should be retransfected with a rescue DNA construct (Figure 17.7). The components and functions are described as follows:




**FIGURE 17.7** Diagram of a rescue vector used for silencing a gene double knockout.


1. A plasmid backbone containing *fl ori* for replication of the plasmid, ColE1 for a high copy number of plasmids, and ampicillin gene for selection of bacterial transformants.
2. An inducible promoter such as RSV MMTV-LTR controls the expression of the cDNA to be cloned.
3. A multiple cloning site (MCS) immediately downstream of the inducible promoter will be used for the insertion of the entire coding region of cDNA of the gene to be targeted. The expression of the cDNA will then be induced by the addition of dexamethasone to the culture medium or into the animal body.
4. An SV40 polyadenylation site and an early splicing region are placed immediately downstream of the MCS site for splicing of mRNA to be expressed from the cloned cDNA.
5. The *hyrt'* gene with its own promoter, pA, and a splicing region. This marker gene must be different from the marker genes in types A and B. This gene will play a key role in selection of stably transfected cells. Any integration of the *hyrt* gene enables the cell to be tolerant to the HAT medium containing hypoxanthine, aminopterin, and thymidine.

## 17.5 PREPARATION OF DNA CONSTRUCTS FOR A DOUBLE KNOCKOUT AND A SILENCER


As soon as desirable targeting vectors and manipulated genes or isogenic DNA fragments are available, preparations of DNA constructs for gene knockout can be carried out. The gene or DNA fragments of interest should be inserted in an appropriate type of vector at the right sites in the right orientations. The general procedures and



**FIGURE 17.8** Diagram of disruption of gene X by exon deletion and sequence replacement by homologous recombination in genome of cell.



**FIGURE 17.9** Targeting of gene X by deletion of gene and sequence replacement with isogenic DNA fragments by homologous recombination in genome of cell.



**FIGURE 17.10** Temporary rescue of a double knockout gene by induction of cDNA expression.

principles for gene disruption or gene targeting (homologous recombination) as well as for temporary rescue of double knockout are illustrated in Figures 17.8, 17.9, and 17.10. The detailed protocols for appropriate restriction enzyme digestion and DNA ligation are described in Chapter 4.

## 17.6 TRANSFECTION OF ES CELLS WITH DOUBLE KNOCKOUT AND SILENCER DNA CONSTRUCTS

This section describes two methods that are widely used for transfection of mammalian cells. Each method has its own principles, strength, and weakness.

### 17.6.1 METHOD A. TRANSFECTION BY ELECTROPORATION

This is a fast and effective transfection technique. The principle underlying this method is that cells and DNA constructs to be transferred are mixed and subjected to a high voltage electrical pulse that creates pores in the plasma membranes of the cells. This allows the exogenous DNA to enter the cytoplasm of the cell and the nucleus through nuclear pores and become integrated into the genome. This method is suitable for both transient and stable transformation experiments. However, the pulse conditions should be adjusted empirically for a particular cell type. Although this method has a high efficiency of transfection, its main drawback is that approximately 50% of the cells are killed by the high voltage of electrical pulse. These dead cells should be removed on a daily basis in order to reduce toxicity.

## Protocol

1. Linearize the DNA constructs to be transferred by a unique restriction enzyme. Protocols for appropriate restriction enzyme digestion are described in Chapter 4.

*Tips: (1) The unique restriction enzyme cut should be in the plasmid backbone area such as the ColEI, fi ori or ampicillin gene. It is extremely important that this cut not be made in any area that will affect gene targeting by homologous recombination, as well as the activities of Lac Z and selectable marker genes such as neo, hyg, hyrt, and HSV-tk. In the case of double knockout rescue DNA, ensure that the cut is not made in any part of the promoter, inserted cDNA, and splicing site. (2) In our experience, plasmid DNA constructs do not need to be linearized for homologous recombination. In fact, plasmid DNA enhances the transfection efficiency by up to 30%.*

2. Harvest the cells by gentle trypsinization as described in Chapter 16. Centrifuge the cells at 150 g for 5 min and resuspend the cells well in normal culture medium at about  $10^6$  cells/ml.

*Note: Make sure that the cells are gently but well suspended before transfection because aggregation of cells may cause difficulty in isolation of stably transfected cell clones.*

3. In a sterile laminar flow hood, gently mix 0.6 ml of the cell suspension with 15 to 30  $\mu$ l of DNA constructs (25 to 50  $\mu$ g) in a disposable electroporation cuvette (Bio-Rad, Hercules, CA).
4. According to the manufacturer's instructions, carry out electroporation using a Gene Pulser (Bio-Rad) with a Pulse Controller and Capacitance Extender at 300 V and 250  $\mu$ F.
5. The electroporated cells should be immediately plated into culture dishes at a density of about 3000 cell/100 mm Petri dish and culture the cells at 37°C with 5% CO<sub>2</sub>. Proceed to drug selection.

### 17.6.2 METHOD B. TRANSFECTION OF CELLS BY LIPOFECTIN REAGENTS

Lipotransfection is relatively safe and achieves a higher efficiency of transfection in mammalian cells. It is suitable for both transient and stable transfection of tissues or cells. It mandates a smaller amount of DNA for transfection compared with electroporation and other methodologies. Lipofectin reagents are commercially available (e.g., Gibco BRL Life Technologies). Liposome formulation is composed of polycationic lipids and neutral lipids at an appropriate ratio (e.g., 3:1). The primary principles of this method include: (1) positively charged and neutral lipids can form liposomes that can complex with negatively charged DNA constructs; (2) DNA-liposome complexes are applied to cultured cells and are uptaken by endocytosis; (3) endosomes undergo breakage of membranes, releasing DNA constructs; and (4) DNA enters into the nucleus through the nuclear pores and facilitates homologous recombination or integration into the chromosomes of the cell.

The main disadvantage of the lipotransfection method is that if the ratio of lipids-DNA and cell density is not at an appropriate level, severe toxicity will be generated, killing quite a number of cells. Additionally, ES cells are more sensitive to toxicity compared with other fibroblasts, such as NIH 3T3 and mouse STO cells.

### Protocol

1. Harvest ES cells by gentle trypsinization as described in Chapter 18. Centrifuge the cells at 150 g for 5 min and resuspend the cells well in normal culture medium at about  $10^6$  cells/ml.  
*Note: Make sure that the cells are gently but well suspended before transfection because aggregation of cells may cause difficulty in isolation of stably transfected cell clones.*
2. In a 60-mm tissue culture dish, seed the suspended cells at about  $1 \times 10^6$  cells in 5 ml of normal culture medium. Allow the cells to grow under normal conditions for 12 h. Proceed to transfection.  
*Note: ES cells grow fast and form multiple layers of clones instead of monolayers as seen in other cell lines. Because of these features, ES cells are not recommended to be overcultured before transfection. Otherwise, multilayers of ES cells may result in a low efficiency of transfection and a high percentage of potential death. Therefore, once a relatively high density of cells is plated, transfection can be carried out as soon as the ES cells attach to the bottom of the dish and grow for 6 to 12 h.*
3. While the cells are growing, one can linearize DNA constructs to be transferred by a unique restriction enzyme. Protocols for appropriate restriction enzyme digestion are described in Chapter 4.
4. In a sterile laminar flow hood, dissolve 10 to 15  $\mu\text{g}$  of DNA in 0.1 ml of serum-free medium and dilute lipofectin reagents to 2- to 5-fold in 0.1 ml of serum-free medium. Combine and gently mix the DNA-lipids media in a sterile tube. Allow the mixture to incubate at room temperature for 15 to 30 min. A cloudy appearance of the medium indicates the formation of DNA-liposome complexes.
5. Rinse the cells once with 10 ml of serum-free medium. Dilute the DNA-liposome solution to 1 ml in serum-free medium and gently overlay the cells with the diluted solution. Incubate the cells for 4 to 24 h under normal culture conditions. During this period, transfection takes place.
6. Replace the medium with 5 ml of fresh, normal culture medium with serum every 12 to 24 h. Allow the cells to grow for 2 to 3 days before selection or analysis in case of transient transfection.
7. Trypsinize the cells and plate them at a density of about 3000 cells/100 mm Petri dish and culture for 24 h at  $37^\circ\text{C}$  with 5%  $\text{CO}_2$ . Proceed to drug selection.

## 17.7 SELECTION AND CHARACTERIZATION OF TARGETED ES CELL CLONES

Drug selection depends on the appropriate drug-resistant genes carried by DNA constructs. With regard to novel strategies for gene knockout described in this chapter, four different selectable marker genes are utilized. Therefore, selections can be divided into three types.

### 17.7.1 DOUBLE SELECTIONS OF CELLS CONTAINING A DOUBLE KNOCKOUT GENE

If the cells were initially subjected to transfection twice with the same DNA constructs whose vector contains either *neo<sup>r</sup>* and *tk* (Figure 17.5) or *hyg<sup>r</sup>* and *tk* (Figure 17.6) genes, double selections (positive and negative selections) should be used. To identify the very rare cells that have a double knockout gene in the genome, double-dose the positive selection drug (G418 for *neo* or hygromycin B for *hyg*).

1. The transfected cells should be plated into culture dishes at a density of 1000 cells/100 mm dish and cultured for 36 to 48 h before selection. Replace the culture medium with 10 ml of drug selection medium at double the concentration. If the cells were transfected twice with *neo<sup>r</sup>-tk<sup>r</sup>* DNA constructs (Figures 17.9 and 17.10), the selection medium should contain 500 to 600 µg/ml of G418 and 50 to 100 nM gancyclovir (GANC). However, if the cells were transfected twice with *hyg<sup>r</sup>-tk<sup>r</sup>* DNA constructs (Figures 17.9 and 17.10), the selection medium should contain 300 to 350 µg/ml of hygromycin B and 50 to 100 nM gancyclovir (GANC).

*Note: The concentration of drugs used for selection depends on the specific cell line. In our killing-curve experiments, 250 to 300 µg/ml of G418 can kill nontransfected ES cells. A concentration of 50 to 100 nM GANC in the culture medium is not cytotoxic to the parental ES cells but is sufficient to kill ES cells containing the HSV-tk gene. The single dose for hygromycin B is 150 to 175 µg/ml.*

2. Remove dead cells by changing the medium once every 24 h and continue the selection for 3 weeks.

*Tips: Drug-resistant colonies usually begin to grow after 10 days in the selection medium and within a few more days, they grow to an appropriate size for isolation.*

3. To pick up stably transfected clones, remove the medium and rinse ES cell colonies with 3 ml/plate of normal culture medium (drug-free). Hold the dish under a light and individually mark or circle well-isolated colonies outside on the bottom of the plate using a red marker pen.
4. Place the plate in the sterile laminar flow hood and overlay each of the marked colonies with a small volume (5 µl/colony) of 1× trypsin–EDTA solution. Allow the cells to become detached from the plate during a 5-min period at room temperature without disturbing the plate. Overlay each colony with 5 µl of culture medium and gently flush the cells in each individually marked area by pipetting the minicell suspension up and down several



times, using a sterile plastic 100- $\mu$ l pipette tip. The purpose of doing this is to ensure detachment of cells from the culture substrate.

5. Carefully take up the cells from each individual colony without disturbing the other colonies and transfer the cells to a 25-cm<sup>2</sup> culture flask containing appropriate drugs as described in step 1.
6. Allow the cells to grow for another 5 to 10 days to the appropriate confluence with medium being replaced once every 3 days. Freeze back some cells from each clones (for details, see Chapter 16). The rest of cells from each of the clones can be utilized for characterization or further proliferation.

### 17.7.2 TRIPLE SELECTIONS OF CELLS CONTAINING A DOUBLE KNOCKOUT GENE

Triple selections refer to cells that are simultaneously transfected with two types of DNA constructs (see Figures 17.5, 17.6, 17.8, and 17.9). If all goes well, successfully targeted cells should contain both *neo<sup>r</sup>-tk<sup>r</sup>* and *hyg<sup>r</sup>-tk<sup>r</sup>* DNA in their chromosomes. Taking advantage of the triple drug-resistant genes, triple selections can allow cells containing the double knockout gene of interest to be isolated. The selection and development procedures for stably transfected cells are almost the same as described in the preceding section except for a few differences. The selection medium will contain 500 to 600  $\mu$ g/ml of G418, 300 to 350  $\mu$ g/ml of hygromycin B, and 50 to 100 nM GANC.

### 17.7.3 SINGLE SELECTION OF CELLS CONTAINING A SILENT KNOCKOUT GENE

Single selection utilizes a single drug in the selection medium. Because double knock-out clones were further transfected with a rescue DNA construct containing the rescue cDNA of the targeted gene and a unique drug resistance gene (*hyr<sup>r</sup>*), the stably transfected cells should be identified with HAT medium that contains 0.1 mM hypoxanthine, 0.9  $\mu$ M aminopterin, and 20  $\mu$ M thymidine. The HAT can be prepared as a 100 $\times$  stock solution and diluted to 1 $\times$  in the culture medium before use. The procedures for isolation of colonies are the same as those described in the preceding section.

## 17.8 CHARACTERIZATION OF TARGETED ES CELL CLONES

Scientifically speaking, stably transfected cell clones mandate detailed characterizations, which include an activity assay of the reporter gene, Southern blotting, PCR screening, and western blot analysis. These analyses will provide crucial evidence to verify the putative cell clones containing the gene that is structurally disrupted or replaced and functionally knocked out.<sup>8,11</sup>

### 17.8.1 $\beta$ -GALACTOSIDASE STAINING OF CELLS

This is a fast procedure used to assay the activity of the *lac Z* gene. Because the gene targeting constructs contain the *lac Z* as a reporter gene within the homologous recombination region, stably transfected cells are expected to express the *lac Z* product, or  $\beta$ -galactosidase. This enzyme can hydrolyze X-gal (5-bromo-4-chloro-3-indolyl- $\beta$ -D-galactoside) and yield a blue precipitate, staining cells blue. Protocol is as follows:

1. Culture the stably transfected cells in a Petri dish for 1 to 2 days.
2. Aspirate the medium and rinse the cells with PBS.
3. Fix the cells in 0.2% glutaraldehyde or 4% paraformaldehyde (PFA) for 5 to 10 min at room temperature.
4. Wash the cells for  $3 \times 5$  min.
5. Stain the cells with X-gal solution for 1 to 24 h at 37°C.
6. Wash the cells for  $3 \times 5$  min in PBS. Any blue cells or colonies indicate that the cells express  $\beta$ -galactosidase, and that the cells most likely contain the targeted gene.

### Reagents needed

- *Potassium phosphate buffer (PBS)*
  - 2.7 mM KCl
  - 1.5 mM  $\text{KH}_2\text{PO}_4$
  - 135 mM NaCl
  - 15 mM  $\text{Na}_2\text{HPO}_4$
  - Adjust pH to 7.2, then autoclave
- *Preparation of 4% (w/v) PFA fixative (1 l)*
  - (a) Carefully weigh out 40 g PFA powder and add it to 600 ml of preheated dd.H<sub>2</sub>O (55 to 60°C). Allow the PFA to dissolve at the same temperature with stirring.  
*Caution: PFA is toxic and should be handled carefully. The preparation should be carried out in a fume hood on a heating plate. Temperature should not be above 65°C and the fixative should not be overheated.*
  - (b) Add 1 drop of 2 N NaOH solution to clear the fixative.
  - (c) Remove from the heat, add 333.3 ml (1/3 total volume) of 3 $\times$  PBS (8.1 mM KCl, 4.5 mM  $\text{KH}_2\text{PO}_4$ , 411 mM NaCl, 45 mM  $\text{Na}_2\text{HPO}_4$ , pH 7.2; then autoclave).
  - (d) Adjust pH to 7.2 with 4 N HCl and bring a final volume to 1 l with dd.H<sub>2</sub>O.
  - (e) Filter the solution to remove undissolved fine particles, cool to room temperature, and store at 4°C until use.
- *X-gal solution*
  - PBS solution containing 0.5 mg/ml X-gal, 10 mM  $\text{K}_3[\text{Fe}(\text{CN})_6]$ . X-gal stock solution (50 mg/ml in dimethylsulfoxide or dimethylformamide). The stock solution should be kept in a brown bottle at -20°C before use.

### 17.8.2 SOUTHERN BLOT ANALYSIS

Data from Southern blot analysis will be the most important evidence to prove whether the stably transfected cell clones carry a double knockout or targeted gene in their chromosomes. Detailed protocols for restriction enzyme digestion of DNA and Southern blot analysis are described in Chapter 7 (Characterization of Gene

or DNA by Southern Blot Hybridization). This section mainly focuses on genomic DNA isolation and analysis of Southern blot data.

### 17.8.2.1 Isolation of Genomic DNA from Cultured Cells


- (1) Aspirate culture medium from cultured cells and rinse the cells twice in PBS.
- (2) Add 10 ml/60 mm culture plate (with approximately  $10^5$  cells) of DNA isolation buffer to the cells and allow cells to be lysed for 5 min at room temperature with shaking at 60 rev/min.
- (3) Incubate the plate at 37°C for 5 h or overnight to degrade proteins and extract the genomic DNA.
- (4) Allow the lysate to cool to room temperature and add 3 volumes of 100% ethanol (precooled at -20°C) to the lysate. Gently mix it and allow DNA to precipitate at room temperature with slow shaking at 60 rev/min. Precipitated DNA, appearing as white fibers, should be visible in 20 min.
- (5) “Fish” out the DNA using a sterile glass hook or spin down the DNA. Rinse the DNA twice in 70% ethanol and partially dry the DNA for 40 to 60 min at room temperature to evaporate the ethanol. The DNA can be directly subjected to restriction enzyme digestion without being dissolved in TE buffer or dd.H<sub>2</sub>O. We usually overlay the precipitated DNA with an appropriate volume of restriction enzyme digestion cocktail and incubate the mixture at an appropriate temperature for 12 to 24 h. The digested DNA is mixed with an appropriate volume of DNA loading buffer and is now ready for agarose gel electrophoresis.

### Reagents needed

- *DNA isolation buffer*
  - 75 mM Tris-HCl, pH 6.8
  - 100 mM NaCl
  - 1 mg/ml Proteinase K
  - 0.1% (w/v) *N*-Lauroylsarcosine

### 17.8.2.2 Analysis of Southern Blot Data


After Southern blot hybridization, it now becomes an exciting moment to analyze the data. Figure 17.11 illustrates the expected results. Keep in mind that disruption of gene X here refers to insertion of marker genes and *lac Z* into one of the exons of the gene to be targeted. As a result, a unique restriction enzyme (E) that originally cuts outside of gene X and generates a 6-kb fragment can produce a large-sized DNA fragment. For instance, insertion of *neo* and *lac Z* genes results in a 10-kb fragment. On the other hand, integration of *hyg* and *lac Z* produces a 12-kb DNA fragment. The genomic DNA is isolated from different targeted cell lines, including nontargeted cells as a control. The DNA can be digested with a unique restriction enzyme and separated by agarose gel electrophoresis. For Southern blot hybridization, two probes can be utilized: probe A, which is external to the targeting vector but internal to gene X, and probe B, which is internal to the marker gene (*neo* or *hyg*) but external to gene X. If both probes A and B are used for hybridization, only a 6-kb band is seen



**FIGURE 17.11** Southern blot analysis of genomic DNA with targeted gene X. Lane 1, non-mutant control cells; lane 2, single copy targeting with a *neo* vector; lane 3, single knockout with *hyg* vector; lane 4, double knockout of gene X with both *neo* and *hyg* vectors. P. A, probe A internal to gene X but external to marker gene; P. B, probe B internal to marker gene but external to gene X.

in nontargeted cells (lane C). If the gene is a single-copy knockout gene, one can see a 6-kb band in the control and a 10 kb-band with the *neo* probe (lane 1) or a 12-kb band with the *hyg* probe (lane 2). In the case of a double knockout by two different targeting constructs (Figures 17.5 and 17.6), both copies of gene X in two chromosomes should be targeted. Thus, two bands should be detected. One is a 10-kb band corresponding to the *neo* probe, and the other is a 12-kb band obtained with the *hyg* probe (lane 3). The 6-kb band shown in the control disappears.

Unlike exon disruption, the isogenic DNA targeting strategy described earlier in this chapter refers to completely replacing gene X to be knocked out. As shown in Figure 17.12, using 5'-isogenic DNA and 3'-isogenic DNA fragments flanking the gene X in the genome, gene X can be replaced by *neo* and *lac Z* or *hyg* and *lac Z* genes by homologous recombination at the sites indicated in the figure. If all goes well, a 20-kb fragment generated by a unique restriction enzyme (E) will become larger or smaller following homologous recombination. To detect knockout sites, probe A can be chosen as internal to gene X and external to the marker genes. Probe B can be designed as external to gene X but internal to the marker genes. After Southern blot hybridization, a 20-kb band should be seen in nontransfected cells as the control (lane C). If gene X is a single-copy targeted, a weak band of 20 kb can be seen as the control with an additional 18-kb band using the *neo* probe (lane 1) or a 16-kb band using the *hyg* probe. If both copies of the gene X have been knocked out, only 18- and 16-kb bands should be detected without the 20-kb band seen in control cells (lane 3).




**FIGURE 17.12** Analysis of double knockout gene X with isogenic DNA. (a) Use of marker *neo* gene vector. (b) Use of marker *hyg* gene vector. (c) Southern blot analysis of genomic DNA with targeted gene X. Lane 1, nonmutant control cells; lane 2, single copy targeting with the *neo* vector; lane 3, single knockout with the *hyg* vector; lane 4, double knockout of gene X with both *neo* and *hyg* vectors. P. A, probe A internal to gene X but external to marker gene; P. B, probe B internal to marker gene but external to gene X.

It should be noted that one important subject of this chapter is the rescue strategy with the double knockout gene so as to temporarily avoid potential lethal effects. To analyze the success of rescue transfection after a double knockout, Southern blot analysis should be carried out. As shown in Figure 17.13, if the unique restriction enzyme does not cut the rescue construct, after successful integration, the original 2-kb band will be expanded to 12 kb in size (Figure 17.13a). In this case, two different probes can be prepared. Probe A is internal to the marker gene (*hyr1*) but external to the targeted gene X. Probe B, on the other hand, is internal to the rescue cDNA of gene X but external to the marker gene. After Southern blotting, probe A will detect a 12 kb band (lane 1). In case of exon insertion by the rescue construct, probe B will detect both 12- and 6-kb bands (lane 2). However, probe B should only reveal a 12-kb band after the replacement of gene X by the rescue construct (lane 3).

### 17.8.2.3 Western Blot Analysis


Protein analysis of the targeted gene is the bottom line of gene double knockout. The detailed protocols for protein extraction and western blot hybridization are described in Chapter 11. This section focuses on how to analyze western blot data. Assuming that the product or protein of gene X to be targeted is 46 kDa, and that monoclonal



**FIGURE 17.13** Analysis of integration of rescue cDNA for the targeted gene X. (a) Diagram of integration. (b) Southern blot analysis of genomic DNA containing rescue cDNA for targeted gene X. Lane 1, double knockout control cells; lane 2, integration into DNA containing a single-copy knockout gene X; lane 3, rescue of double knockout of gene X. P. A, probe A internal to gene *hyrt'* but external to cDNA; P. B, probe B internal to cDNA but external to *hyrt'*.

antibodies have been raised to be against the 46-kDa protein (as shown in Figure 17.14), only a 46-kDa band is detected in wild-type (WT) or control cells. Lane 1 indicates that a single copy of gene X is targeted by a targeting construct containing the *neo* gene. Thus, a weak 46-kDa band as shown in control cells and a 90-kDa band due to the fusion protein are seen. Similar results are revealed in lane 2 if gene X is singly targeted by a construct containing the *hyg* gene (lane 2). In the case of a double knockout by insertion into an exon of gene X, two bands larger than 46 kDa will be detected, which represent two different sizes of fusion proteins due to the insertion of two different marker genes and the *lac Z* gene (lane 3). Interestingly, if both copies of gene X are completely replaced by the double knockout constructs, no bands should be seen (lane 4). On the other hand, the cells shown in lane 3 are rescued by gene X cDNA. In this case, three different bands will be detected, including a 46-kDa band seen in control cells (lane 5). In contrast, if the cells shown in lane 4 are rescued by gene X cDNA, only a single 46-kDa band is detected. This is the same as that from the control cells (lane 5).

Assuming that the targeted cell lines have been characterized by X-gal staining, Southern blot analysis, and western blot hybridization, and that the cell clones containing the gene double knockout have been obtained, it is fair to say that this is a big reward for the investigators and represents more than the halfway point in the long journey to obtain transgenic mice.



**FIGURE 17.14** Protein analysis by western blotting. Assume that the product of gene X has a molecular weight of 46 kDa, and that monoclonal antibodies against the 46-kDa protein are used in western blot analysis. WT, wild type as nontransfected cells. Lane 1, cells containing single copy knockout of gene X by *neo* gene; lane 2, cells containing a single copy knockout of gene X by *hyg* gene; lane 3, double knockout of gene X by disruption of an exon with both *neo* and *hyg* genes; lane 4, double knockout of gene X by replacement of the gene with both *neo* and *hyg* genes; lane 5, cDNA rescue of targeted gene X as shown in lane 3; lane 6: cDNA rescue of targeted gene X as shown in lane 4.

## 17.9 GENERATION OF TRANSGENIC OFFSPRING FROM DOUBLE-KNOCKOUT ES CELLS

C57BL/6J female mice are commercially available and are widely utilized for embryo recovery and transfer. This strain of mice is different from 129 SVJ mice in coat color, which can be used as a useful marker.

### 17.9.1 PROCEDURE 1. SELECTION OF C57BL/6J ESTROUS FEMALES

C57BL/6J mouse is a well-established strain and widely chosen as the best choice of host embryo for ES cell chimeras and germline transmission. These mice have a coat color that is different from that of 129 SVJ mice, which can be used as a coat color selection marker. In order to relatively synchronize the estrous cycle and to simplify female selection, it is recommended that female mice be caged together without a male. Their estrous cycle is approximately 3 to 4 days, and ovulation usually occurs at about the midpoint of the dark period in a light/dark cycle. This light-and-dark cycle can be altered to meet one's schedule. For example, the cycle may be adjusted to 14 h of light and 10 h of dark. In this way, most strains of mice produce blastocysts that can be utilized for injection in the late morning of the third or fourth day. The key question is how to identify proestrous or estrous females for mating. The basic criteria are the external vaginal epithelial features. At the proestrous stage, the vaginal epithelium is usually characterized by being moist, folded, pink/red, and

swollen. At the estrous stage, the general features of the vaginal epithelium include being dry but not wet, pink but not red or white, wrinkled epithelium on both upper and lower vaginal lips, and being swollen. After the females have been caged for a while and when they reach the proestrous prediction, they should be monitored on a daily basis. Once they are at the estrous stage, mating should be set up.

An alternative way to promote the estrous cycle is via hormonal induction of ovulation with exogenous hormones. This procedure is termed superovulation. Injection of pregnant mare serum gonadotropin (PMSG, Sigma) can stimulate and induce immature follicles to develop to the mature stage. Superovulation can be achieved by further administration of human chorionic gonadotropin (HCG, Sigma). The procedure is outlined as follows:

- (a) Three days or 72 to 75 h before mating, induce superovulation of 10 to 15 female mice (3 to 4 weeks old) by injecting 5 to 10 units of PMSG intraperitoneally into each female between 9:00 A.M. and noon on day 1.
- (b) Two days or 48 to 50 h later, inject 5 to 10 units of HCG intraperitoneally into each female between 9:00 A.M. and noon on day 3. After injection, cage the females and proceed to mate them with sterile males.

#### **17.9.2 PROCEDURE 2. PREPARATION OF A BANK OF STERILE MALES BY VASECTOMY**

Detailed protocols are described in Chapter 9.

#### **17.9.3 PROCEDURE 3. PAIRING OF ESTROUS FEMALES AND STERILE MALES**

Detailed protocols are described in Chapter 9.

#### **17.9.4 PROCEDURE 4. PREPARATION OF BLASTOCYST-STAGE EMBRYOS FROM PSEUDOPREGNANT MICE**

Detailed protocols are described in Chapter 9.

#### **17.9.5 PROCEDURE 5. PREPARATION OF MICROMANIPULATION APPARATUS**

Detailed protocols are described in Chapter 9.

#### **17.9.6 PROCEDURE 6. INJECTION OF ES CELLS INTO BLASTOCYSTS**

Detailed protocols are described in Chapter 9.

#### **17.9.7 PROCEDURE 7. REIMPLANTATION OF INJECTED BLASTOCYSTS INTO THE UTERUS OF RECIPIENT FEMALES**

Detailed protocols are described in Chapter 9.



## 17.10 CHARACTERIZATION OF MUTANT MICE

Once offspring or transgenic mice have been obtained, they should be analyzed at DNA, protein, morphological, and functional levels. DNA can be isolated from mouse tails and Southern blot hybridization be carried out as described in Chapter 7. Extraction of proteins from soft tissues (brain, liver) and analysis by western blotting are described in Chapter 11. Analyses of Southern and western blot data are virtually the same as described above for cell line characterization. In addition, immunohistochemical or cytochemical analyses can be performed by *in situ* hybridization (Chapters 12 to 14).

Morphological and functional analyses can provide the most powerful evidence for the occurrence of gene double knockout in transgenic mice. For example, if gene X controls red eyes in wild-type mice. If double knockout of gene X is successful, then mutant mice will have white eyes. As a result, the transgenic mice may not see as well as wild-type mice. Other physiological/pathophysiological, toxicological, and pharmacological approaches may also be used to study transgenic mice having targeted genes of interest.

## REFERENCES

1. Capecchi, M. R. 1994. Targeted gene replacement. *Scientific American* 270: 52.
2. Capecchi, M. R. 1989. Altering the genome by homologous recombination. *Science* 244: 1288.
3. Mansour, S. L., K. R. Thomas, and M. R. Capecchi. 1988. Disruption of the proto-oncogene *int-2* in mouse embryo-derived stem cells: a general strategy for targeting mutations to non-selectable genes. *Nature* 336: 348.
4. Riele, H. T., E. R. Maandag, and A. Berns. 1992. Highly efficient gene targeting in embryonic stem cells through homologous recombination with isogenic DNA constructs. *Proceedings of the National Academy of Sciences of the United States of America* 89: 5128.
5. Schorle, H., T. Holschke, T. Hunig, A. Schimpl, and I. Horak. 1991. Development and function of T cells in mice rendered interleukin-2 deficient by gene targeting. *Nature* 352: 621.
6. Tybulewicz, V. L. J., C. E. Crawford, P. K. Jackson, R. T. Bronson, and R. C. Mulligan. 1991. Neonatal lethality and lymphopenia in mice with a homozygous disruption of the *c-abl* proto-oncogene. *Cell* 65: 1153.
7. Weinstock, P. H., C. L. Bisgaier, K. A. Setala, H. Badner, R. Ramakrishnan, S. L. Frank, A. D. Essenburg, R. Zechner, and J. L. Breslow. 1995. Severe hypertriglyceridemia, reduced high density lipoprotein, and neonatal death in lipoprotein lipase knockout mice. *Journal of Clinical Investigation* 96: 2555.
8. Michalska, A. E., and K. H. A. Choo. 1993. Targeting and germ-line transmission of a null mutation at the metallothionein I and II loci in mouse. *Proceedings of the National Academy of Sciences of the United States of America* 90: 8088.
9. Hasty, P., J. R. Perez, and A. Bradley. 1991. The length of homology required for gene targeting in embryonic stem cells. *Molecular and Cellular Biology* 11: 5586.
10. Paul, E. L., M. L. Tremblay, and H. Westphal. 1992. Targeting of the T-cell receptor chain gene in embryonic stem cells: strategies for generating multiple mutations in a single gene. *Proceedings of the National Academy of Sciences of the United States of America* 89: 9929.
11. Hasty, P., and Bradley, A. 1993. Gene targeting vectors for mammalian cells. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: IRL Press, Oxford University Press, Inc.

12. Wu, W. 1995. Electrophoresis, blotting, and hybridization. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke. Boca Raton, FL: CRC Press.
13. Wu, W. 1995. Gene transfer and expression in animals. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke. Boca Raton, FL: CRC Press.
14. Wurst, W., and A. L. Joyner. 1993. Production of targeted embryonic stem cell clones. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: IRL Press, Oxford University Press, Inc.
15. Papaioannou, V., and R. Johnson. 1993. Production of chimeras and genetically defined offspring from targeted ES cells. In *Gene Targeting: A Practical Approach*, ed. A. L. Joyner. New York, NY: IRL Press, Oxford University Press, Inc.

---

# 18 Large-Scale Expression and Purification of Recombinant Proteins in Cultured Cells

## 18.1 INTRODUCTION

Expression of large amounts of specific proteins has become more and more important to scientific research in academic fields, and is invaluable to industry as well. In fact, protein labeling, protein crystallization, production of antibodies, and synthesis of proteins for gene transcriptional regulation mandate a fair amount of pure proteins. Recently, DNA recombination technology, gene transfer, and expression techniques have made it possible to overexpress a protein of interest at a very high level in a short period.<sup>1-4</sup> Different strategies and expression systems have been developed using prokaryotic and eukaryotic expression vectors and hosts.

*Escherichia coli* has been well studied for decades. It has been demonstrated that *E. coli* is the best prokaryotic system for expression of foreign genes.<sup>1-3</sup> Since DNA recombination technology became available, *E. coli* has been widely used as the leading host organism for broad applications of protein expression.<sup>2-7</sup> Compared to eukaryotic cells, *E. coli* has two major advantages: (1) it has a very short life cycle of approximately 20 min per generation; and (2) it is easy to manipulate and large-scale cultures can be made in inexpensive media. Thus, it is not surprising that *E. coli* has been chosen as an ideal system to express large quantities of proteins encoded by cloned cDNA or genes.

One drawback, however, is that posttranslation modifications of eukaryotic proteins may not take place in *E. coli*. Fortunately, eukaryotic expression systems have been established to overcome this difficulty in the processing of proteins in bacteria. A well-known example is the yeast *Pichia* system from Invitrogen (San Diego, CA). Compared with other eukaryotic cell lines, yeast is easy to grow at a low cost.<sup>9</sup> Perhaps the major advantages of using yeast as a host for protein expression are that the genome is easy for manipulation and suitable for cloning of foreign genes and overexpression and purification of proteins of interest.

This chapter introduces and describes the detailed protocols for large-scale expression, collection, and purification of proteins of interest in *E. coli* and yeast systems.<sup>4-11</sup> Because of the rapid advances in current biotechnology, the authors strongly encourage users to obtain up-to-date information or suitable expression systems for a particular research, which may be available from biotechnology companies.

## 18.2 EXPRESSION AND PURIFICATION OF PROTEINS IN PROKARYOTIC SYSTEMS


This section will focus on the current strategies used for expression and purification of large amounts of specific proteins using *E. coli* as the host.

### 18.2.1 DESIGN AND SELECTION OF BACTERIAL EXPRESSION VECTORS

Expression of a specific protein in *E. coli* begins with the insertion of a cDNA into an expression vector. Selection of appropriate vectors will play a major role in the success of protein expression. So far, plasmid-based vectors are widely utilized for such purposes. Different types of expression vectors are commercially available; for example, the pTrcHis (A, B, C) and pRSET (A, B, C) series have been developed by Invitrogen and pET series by Novagene. All three reading frames are available in the vector series. Other expression vectors are available from Strategene and Gibco BRL.

In general, a desirable expression vector should have the features shown in Figure 18.1. If some features are not present in commercial vectors, for research purposes, appropriate sequences may be created by polymerase chain reaction (PCR) or other subcloning approaches and sequences inserted at appropriate positions in a vector.

1. **A strong bacteriophage T7 promoter for transcription.** Its activity is induced by endogenous T7 RNA polymerase of the host cell or by introduction of a bacteriophage T7 RNA polymerase gene into the host cell. Bacteriophage T7 RNA polymerase is a very active enzyme that synthesizes RNA much faster than *E. coli* RNA polymerase. In fact, the enzyme is so selective and active that it uses the majority of the cellular machinery for the expression of foreign proteins. Because of the high selectivity of the T7 RNA polymerase, the enzyme mainly initiates its own promoter activity, but not the initiation of transcription from other sequences on *E. coli* DNA. As a result, the desired protein can be >50% of the total proteins in the cell



**FIGURE 18.1** An ideal vector for large-scale expression and purification of specific proteins in *E. coli* strain BL21 (DE3) by IPTG induction.

after several hours of induction. Additionally, because the T7 promoter is controlled by T7 RNA polymerase, the expression of a cDNA, or a gene cloned downstream from the T7 promoter, can be maintained transcriptionally silent or “off” in the uninduced state. This is particularly useful when expression of some proteins is potentially toxic to the host cell.

- The *lac* operator and *lacI* gene.** Immediately downstream of the T7 promoter is the *lac* operator. Like the T7 promoter, the *lac* operator can also control the expression of the cDNA or gene cloned downstream from the operator. However, the operator is negatively controlled by the *lac* repressor encoded by the *lacI* gene that is separated from the T7 promoter and the *lac* operator. When the repressor binds to the operator, the transcription of downstream cDNA or gene is turned off. However, upon addition of an appropriate dose of isopropyl- $\beta$ -D-thiogalactoside (IPTG), which will bind to the repressor, the operator will be activated and the expression of a foreign gene will then be turned on. Thus, regulation between the *lac* operator and repressor can reduce the basal expression of a foreign gene when the product of the gene is potentially toxic to the host cell. Besides, the *lacO* operator and the *lacI* repressor gene in the vector provide transcriptional regulation in any *E. coli* strain. In other words, the cloned cDNA or gene at the multiple cloning site (MCS) can be expressed in any strain of *E. coli* except that the expression level is not as high as that controlled by the bacteriophage T7 promoter.
- A strong ribosome binding site (RBS).** A bacteriophage RBS consists of AAGGAG sequence lying very closely upstream from the first codon ATG, which will provide a high efficiency of translational initiation. The small subunits of ribosomes will selectively recognize and bind to the sequence, thus initiating the translation of the mRNA. Again, if the sequence is not available in the vector, the sequence can be easily created immediately upstream of the ATG codon. With the sequence, the translational rate can be enhanced several times.
- The ATG codon.** ATG (AUG in mRNA) is designed almost immediately after the RBS sequence. This will be the first codon for the recombinant protein. The purpose of including this first codon is attributable to the very next His-tag for future affinity purification. Because the first codon is fixed in the vector, a cDNA or gene to be cloned should be carefully oriented so that absolutely no stop codon and no reading frame shifts are allowed. Detailed cautions will be noted in cloning of insert into vector.
- His-tag.** The His-tag sequence located immediately following the ATG codon will code for 6 to 10 consecutive histidine residues. These His residues will be the N-terminal leader sequence of a protein to be expressed from the cloned cDNA or gene and will serve as the affinity tag for rapid purification of the protein with metal chelation affinity chromatography using an appropriate His-binding resin.
- Protease cleavage site (PCS).** A sequence coding for a PCS is designed between the His-tag and the MCS. The amino acid sequence encoded by this sequence will be the target site for an appropriate protease (e.g., thrombin, Factor Xa, or enterokinase). This will allow removal of the N-terminal

His-tag leader sequence *in vitro* as desired. It should be noted here that non-cleaved fusion proteins will be acceptable for use as antigens. However, for biochemical, cell biology, or enzyme assays, the leader sequence may need to be removed because a native protein is better than a fusion protein.


7. **Multiple cloning site.** An MCS contains different restriction enzyme sites for insertion of a specific cDNA for expression of a specific protein. Usually, commercial vectors contain overlapping bases for adjacent restriction enzymes. Perhaps it is for ease of use that all three reading frames vector series have been developed. This strategy allows cloning of a cDNA to be expressed at different restriction enzyme sites without causing reading frame shifts.
8. **Terminator.** A translational terminator sequence may be designed immediately downstream from the MCS. Nonetheless, if the cDNA to be expressed contains a stop codon, it will be fine without the terminator sequence built in the vector.
9. **Plasmid backbone (Ampicillin gene, F1 ori, and ColE1).** A plasmid-based expression vector should contain plasmid backbone elements. An ampicillin-resistant gene or *Amp<sup>r</sup>* will serve as an antibiotic marker for selection of positive transformed colonies. In theory, only bacteria carrying an *Amp<sup>r</sup>* gene in the introduced plasmid DNA are resistant to the killing by ampicillin. A F1 ori sequence will allow the synthesis of single-stranded plasmid DNA by infection of F'-containing host strains with helper phage (e.g., R408). The ColE1 element makes it possible to replicate the introduced plasmid DNA with as high a copy number as possible.

As mentioned earlier, the use of a bacteriophage T7 RNA polymerase/promoter system will certainly make possible the large-scale expression of specific proteins. However, for utilization of the vector type as diagrammed in Figure 18.1, the DNA constructs needs to be transformed into a special *E. coli* strain such as BL21 (DE3) that contains a T7 RNA polymerase gene on the bacterial chromosome under the control of the *lac* promoter.<sup>3</sup> Or, two DNA constructs may need to be introduced into the same *E. coli* strain: one is the vector type shown in Figure 18.1 and the other is a construct containing the bacteriophage T7 RNA polymerase gene and the *lac* promoter.

An alternative approach is to design or obtain a vector that contains the features shown in Figure 18.1 and has the bacteriophage T7 RNA polymerase gene under the control of the *lac* promoter as shown in Figure 18.2. The major advantages of using this type of vector are: the DNA constructs can be introduced into any standard *E. coli* strains, and the expression of T7 RNA polymerase can be easily induced either by IPTG or by heat shock at 42°C for 30 to 40 min.

### 18.2.2 CLONING OF cDNA INSERTS INTO VECTORS

Detailed protocols concerning DNA digestion, preparation of vectors and insert DNA, ligation, transformation, selection, and purification of plasmid DNA are described in Chapter 4. This section primarily focuses on several special precautions that should be taken when cloning a cDNA for expression.



**FIGURE 18.2** An ideal vector for large-scale expression and purification of specific proteins in any *E. coli* strains by heat induction.

1. Restriction enzyme(s) used for DNA digestion should be unique so as to cut outside the entire coding region of the cDNA to be cloned at the MCS of the vector. To ensure the success of protein expression, no enzyme cuts are allowed inside the coding region of the cDNA or outside the MCS region of the vector DNA. Detailed restriction enzyme mapping should be carried out when preparing vectors and insert DNA.
2. Carefully trim out as much as possible the 5'-UTR and 3'-UTR regions of the cDNA to be expressed using appropriate restriction enzymes or PCR approaches. In our experience, long 5'-UTR or 3'-UTR regions may decrease the efficiency of protein expression.
3. Because of the orientation of the driving promoter and the first ATG codon fixed in place in the vector, one should make sure to insert the poly(T) strand instead of the poly(A) of the cDNA in 3'→5' orientation downstream from the driving promoter. In other words, the cDNA to be expressed should be cloned at the sense orientation under the control of the driving promoter. Therefore, antisense cloning done by mistake is not allowed.
4. Because the first codon ATG is fixed in place in the vector, the cDNA to be expressed must be carefully orientated so that absolutely no stop codon and no reading frame shifts are allowed. To make sure that the cDNA has been cloned at the right position with the correct reading frame starting from the ATG in the vector, it is strongly recommended that the DNA constructs obtained be carefully analyzed by appropriate restriction enzyme digestion pattern analysis and by DNA sequencing of the 5' junction site. However, the entire cDNA does not need to be sequenced. In the authors' experience, as long as the 5' portion of the cloned cDNA has the correct nucleotide sequence and the right reading frame with regard to the ATG codon and the leading sequence, the constructs should be fine without sequencing the whole cDNA.

### 18.2.3 EXPRESSION OF PROTEINS OF INTEREST IN BACTERIA

Once an expression construct is established, the plasmid constructs can be introduced into an appropriate *E. coli* strain for induction of protein expression. As discussed earlier, different types of vectors require different bacterial strains. For example, Protocols A and B (Sections 18.3.2.1 and 18.3.2.2) can be applied to the vector type shown in Figure 18.1. Protocols C and D (Sections 18.3.2.3 and 18.3.2.4) are suitable for the vector type shown in Figure 18.2.

#### 18.2.3.1 Protocol A. Transformation of *E. coli* BL21 (DE3) with Vector Shown in Figure 18.1 Using CaCl<sub>2</sub> Method

1. Thaw an aliquot of 0.2 ml of frozen CaCl<sub>2</sub>-treated competent cells of *E. coli* BL21 (DE3) on ice.
2. Perform transformation as follows:

Components	Tube #1	#2
Cells	50 $\mu$ l	50 $\mu$ l
DNA	100 ng in 5 $\mu$ l	400 ng in 5 $\mu$ l

*Tip: Fifteen to twenty microliters of the ligated mixture can be directly added to 50 to 60  $\mu$ l of competent cells.*

3. Incubate on ice for 45 to 50 min.
4. Heat shock at 42°C for 1 to 1.5 min and quickly place the tubes on ice for 1 min.  
*Tip: The heat shock treatment and chilling on ice should not exceed the time indicated. Otherwise, the efficiency of transformation will decrease by 10- to 20-fold.*
5. Transfer the cell suspension to sterile culture tubes containing 1 ml of Luria–Bertani (LB) medium without antibiotics. Incubate at 37°C for 1 to 2 h with shaking at 140 rev/min to recover the cells.
6. Transfer 50 to 150  $\mu$ l of the cultured cells per plate onto the center of LB plates containing 50  $\mu$ g/ml ampicillin. Immediately spread the cells over the entire surface of the LB plates using a sterile, bent glass rod.
7. Invert the plates and incubate them at 37°C overnight. Selected colonies should be visible 14 h later.

#### 18.2.3.2 Protocol B. Induction of Protein Expression with IPTG

1. Inoculate a single colony into 5 ml of LB medium containing 50  $\mu$ g/ml ampicillin. Grow the cells at 37°C overnight with shaking at 200 rev/min. Store the cells at 4°C before use.
2. Add 1 ml of the cell suspension into each flask containing 100 ml of LB medium and 50  $\mu$ g/ml ampicillin in the medium and incubate with shaking at 37°C until OD<sub>600</sub> reaches 0.7 to 1.0 (usually 3 to 5 h). One sample will serve as uninduced control, and the other will be subjected to IPTG induction.



3. Add IPTG from a 100-mM stock solution to the IPTG induction flask to a final concentration of 1 mM. Allow the cells to grow for another 3 to 4 h at 37°C with shaking.

Principles: *During the cell culture, a large quantity of T7 RNA polymerase is expressed by the T7 RNA polymerase gene on the host chromosomal DNA. T7 RNA polymerase activates the bacteriophage T7 promoter that controls the expression of the cDNA cloned downstream from the promoter. However, there is a lac operator immediately following the T7 promoter. The lac operator is usually bound by the lac repressor and becomes silent. Therefore, even though a lot of T7 RNA polymerases are produced, the expression of the cDNA is in an inactivated state. IPTG binds to the lac repressor, preventing the repressor from binding to the operator. As a result, there is no “blocking door” downstream of the T7 promoter. Once the T7 promoter is activated, the expression of the cloned cDNA is turned on. Using a large amount of T7 RNA polymerase, the T7 promoter can virtually convert most of the host’s resources for the synthesis of foreign proteins.*

4. Place the flasks on ice for 10 min and centrifuge at 5000 rev/min for 5 min at 4°C.
5. Decant the supernatant and resuspend the cells in 20 ml of Tris–HCl buffer (pH 8.0) containing 2 mM EDTA.
6. Carry out centrifugation as described in step 4. The cells can be resuspended in an appropriate protein extraction buffer.

### Reagents needed

- *LB medium (per liter)*  
10 g Bacto-tryptone  
5 g Bacto-yeast extract  
5 g NaCl  
Adjust to pH 7.5 with 0.2 N NaOH and autoclave.
- *LB plates*  
Add 15 g of Bacto-agar to 1 l of freshly prepared LB medium and autoclave. Allow the mixture to cool to about 55°C and add an appropriate amount of antibiotic stock. Pour 25 to 30 ml of the mixture into each of the 100-mm Petri dishes in a sterile laminar flow hood with filtered air flowing. Remove any bubbles with a pipette tip and let the plates cool for 5 min before they are covered. Allow the agar to harden for 2 h and partially dry at room temperature for a couple of days. Store the plates at room temperature for up to 10 days or at 4°C in a bag for 1 month. Allow the cold plates to warm up at room temperature for 1 to 2 days before use.

#### 18.2.3.3 Protocol C. Transformation of *E. coli* Strains HB101, JM109, TOP10, or DH5 $\alpha$ F' Using Vector Type Shown in Figure 18.2

If a DNA construct is developed as shown in Figure 18.2, the constructs may be transferred into standard *E. coli* strains such as HB101, K38, JM109, TOP10, or

DH5 $\alpha$ F', assuming that the products expressed from the cloned cDNA are not toxic to the host cell. The transformation procedure is the same as described above.

#### 18.2.3.4 Protocol D. Induction of Protein Expression by Heat Shock

Cells containing the plasmid construct shown in Figure 18.2 can be induced for expression of the cloned cDNA by either IPTG as described above or by heat shock as follows:

1. Inoculate a single colony into 5 ml of LB medium containing 50  $\mu$ g/ml ampicillin. Grow the cells at 30°C overnight with shaking at 200 rev/min. Store the cells at 4°C before use.
2. Add 1 ml of the cell suspension to each flask containing 100 ml of LB medium with 50  $\mu$ g/ml ampicillin in medium and incubate with shaking at 30°C until OD<sub>600</sub> reaches 0.5 to 0.7. One sample will serve as the uninduced control, and the other will be subjected to heat induction.
3. Raise the temperature to 42°C and allow the cells to grow at 42°C for 30 to 40 min with shaking.

*Principles: During incubation at low temperature (30°C), the expression of the cloned cDNA under the control of the T7 RNA polymerase promoter is inhibited by the lac repressor expressed under the control of E. coli Plac promoter. However, at high temperature (42°C), the inhibition is inactivated, resulting in the activation of the T7 promoter. Subsequently, a large quantity of T7 RNA polymerase is expressed under the control of the T7 RNA polymerase promoter. T7 RNA polymerase activates the bacteriophage T7 promoter that controls the expression of the cDNA cloned downstream from the promoter. In other words, once the T7 promoter is activated, the expression of the cloned cDNA is turned on. Using a large amount of T7 RNA polymerase, the T7 promoter can virtually convert most of the host's resources for the synthesis of foreign proteins.*

4. Reduce the temperature to 4°C and allow the cells to grow for 1.5 to 2 h with shaking.
5. Place the flasks on ice for 10 min and centrifuge at 5000 rev/min for 5 min at 4°C.
6. Decant the supernatant and resuspend the cells in 20 ml of Tris–HCl buffer (pH 8.0) containing 2 mM EDTA.
7. Carry out centrifugation as described in step 5. The cells can be resuspended in an appropriate protein extraction buffer.

### 18.2.4 PURIFICATION AND CLEAVAGE OF EXPRESSED PROTEINS

#### 18.2.4.1 Analysis of Cellular Proteins by SDS-PAGE, Dot Blot, or Western Blotting

Before large-scale culture of bacteria and purification of proteins, the overexpression of proteins of interest from cultured cells should be quickly analyzed or confirmed by sodium dodecyl sulfate-polyacrylamide gel electrophoresis (SDS-PAGE) followed by Coomassie blue staining, or by dot blot or western blot analysis if specific antibodies are available. The bacteria containing the overexpressed


proteins can be completely solubilized under denaturation conditions, which can be loaded into SDS-PAGE or used for dot blotting. The detailed protocols for protein extraction, solubilization, SDS-PAGE, and western blot analysis are described in Chapter 11. In this chapter, the primary focus is on the assessment of the expression data.

The size of the expressed protein can be estimated based on the amino acids encoded by the reading frame of the cloned cDNA plus the leader sequence, assuming that the average molecular weight for each amino acid is 100 Da. However, it does not matter if it is not convenient to estimate the size of the product because, if all goes well, the band of the overexpressed proteins should be much larger than that of an uninduced protein sample. For example, if the protein band of interest is approximately 60 kDa, as shown in Figure 18.3, this band is zero or very weak in the uninduced bacterial sample but is about 50-fold higher in the induced bacterial samples (Figure 18.3a), which can be confirmed by western blotting using specific antibodies against the protein molecules (Figure 18.3b). If the expression level of the proteins is less than 5-fold compared with control cells, the protein expression can be considered unsuccessful.

After characterization of transformed colonies, the colonies that overexpress foreign proteins should be frozen back in as many vials as possible using sterile glycerol to a final concentration of 15% (v/v) at  $-80^{\circ}\text{C}$ .

#### 18.2.4.2 Extraction of Total Proteins for Purification

To obtain native proteins without denaturation, a strong detergent such as SDS, 2-mercaptoethanol, or dithiothreitol (DTT) should be avoided. This is particularly



**FIGURE 18.3** Analysis of protein expression in uninduced and induced bacteria. (a) Analysis of equal amounts of proteins by SDS-PAGE followed by Coomassie blue staining. (b) Analysis of protein expression by western blotting using monoclonal antibodies against protein. Lane 1, total proteins from uninduced bacteria; lane 2, total proteins from IPTG-induced bacteria; lane 3, purified protein from total proteins in lane 2 with His-tag affinity chromatography; lane 4, removal of leader sequence from fusion protein shown in lane 3.

important for enzyme assays. However, if the expressed proteins will be used as antigens or labeling without the need for native proteins, the cells can be completely lysed and solubilized using 0.1% to 0.3% (w/v) *N*-lauroylsarcosine (sodium salt) in 45 mM Tris-HCl buffer (pH 6.8) containing 0.2 to 0.4 mM of phenylmethylsulfonyl fluoride (PMSF). PMSF should be added to the buffer shortly before use. Cells are allowed to lyse for 2 to 4 min at room temperature with occasional agitation by hand.

1. Perform a large-scale protein expression and pelletize the cells as described above. Completely aspirate the supernatant and resuspend the cells in 5 ml of ice-cold binding buffer per 100 ml of cell culture in a tube.
2. Place the tube on ice and sonicate the sample in the tube to break the cells and shear DNA using a microsonicator probe with a power setting at 20% to 40%.

*Note: Do not use a high power setting and long sonication time. Otherwise, heat generated may cause denaturation of proteins. In our experience, short sonication bursts (about 5 s/burst) with cooling in between (2 to 3 s) are strongly recommended. Carry out sonication until the sample is no longer viscous.*

3. Centrifuge the lysate at 15,000 to 20,000 *g* for 20 min at 4°C to remove debris.
4. Filter the supernatant through a 0.45- $\mu$ m membrane filter to prevent clogging of the column resin.

- *Binding buffer*  
20 mM Tris-HCl, pH 7.9  
0.5 M NaCl  
5 mM imidazole  
0.2 mM PMSF

#### 18.2.4.3 Rapid Purification of Expressed Proteins with His-Tag Affinity Column Chromatography

Affinity columns and His-tag affinity resin are commercially available from Invitrogene and Novagene.

1. Prepare binding buffer, charge buffer, washing buffer, and elution buffer, and filter-sterile.
2. Briefly mix the commercial His-bind or His-bound resin by inverting the bottle to completely suspend the slurry. Transfer an appropriate volume of the slurry into a chromatograph column using a clean, wide-mouth Pasteur pipette or its equivalent.
3. Allow the resin to pack under gravity flow at 4°C for about 1 to 2 h. During packing, remove some liquid from the top and add more resin slurry until approximately 2.5 ml of settled resin has been obtained.
4. Drain the liquid from the bottom of the column and wash the column with 3 volumes (to the settled bed volume) of dd.H<sub>2</sub>O.

5. Charge the column with 5 volumes of charge buffer for 10 min at room temperature and drain away the liquid.
6. Equilibrate the column with 3 volumes of binding buffer. Close the drain vial at the bottom of the column and loosen the resin in the column using a clean needle. Allow the resin to settle at 4°C for 30 min before draining the liquid.
7. In a cold room, load the filtered protein sample onto the top of the column bed with the bottom drain valve closed. Loosen the resin for efficient binding of the expressed proteins to the His-bind resin and allow the binding to proceed for 30 min.  
*Note: If the proteins are denatured by SDS or mercaptoethanol, chromatography can be performed at room temperature.*
8. Drain the liquid and reload the collected liquid onto the column two to three times to make use of unbound proteins during the first or second loading.
9. Wash the column with 20 volumes of binding buffer.
10. Wash the column with 15 volumes of washing buffer.
11. Elute the bound proteins with 6 volumes of elution buffer.  
*Note: The column can be regenerated and reused according to the manufacturer's instructions. The eluted protein sample contains a high concentration of salts, which may need to be desalted as described in step 12.*
12. Perform dialysis to desalt the protein sample as follows:
  - (a) Transfer the sample into a dialysis bag with a cutoff molecular weight less than the molecular weight of the fusion proteins.
  - (b) Seal the bag at both ends using appropriate clips or by making knots.
  - (c) Place the sample bag in a beaker containing 1 l of dialysis buffer.
  - (d) Perform dialysis in a cold room with stirring for 1 to 2 days. Change dialysis buffer every 12 h.
13. Concentrate the protein samples using plastic disposable microconcentrators from Amicon and centrifuge at 1000 rev/min at 4°C for an appropriate period of time. An alternative and effective way is to partially freeze-dry the samples or to partially lyophilize in a Speed Vac System under cold conditions until a minimum volume is reached.
14. Take 20 to 100 µl of the sample to measure the concentration (see Chapter 11). Store the protein sample at -20°C until use.
15. Take 2 to 3 µg protein to analyze the purity by SDS-PAGE and/or western blotting (Figure 18.3).

### Reagents needed

- *Binding buffer*  
20 mM Tris-HCl, pH 7.9  
0.5 M NaCl  
5 mM imidazole  
0.2 mM PMSF
- *Charge buffer*  
50 mM NiSO<sub>4</sub>

- *Washing buffer*  
20 mM Tris–HCl, pH 7.9  
0.5 M NaCl  
60 mM imidazole
- *Elution buffer*  
20 mM Tris–HCl, pH 7.9  
0.5 M NaCl  
1 M imidazole
- *Dialysis buffer*  
20 mM Tris–HCl, pH 7.5  
10 mM NaCl

#### 18.2.4.4 Protease Cleavage of His-Tag

As indicated in Figures 18.1 and 18.2, each vector contains a sequence encoding a PCS that allows removal of the His-tag using an appropriate protease, depending on the specific sequence at the cleavage site. The widely used enzymatic or chemical cleavage protocols are described below. It should be noted that removal of the leader sequence is optional. In fact, the presence of the His-tag does not appear to affect the biological activity of most proteins.

##### 18.2.4.4.1 Protocol 1. Enzymatic Cleavage of Leader Sequence by Factor Xa

If a vector contains a sequence between the His-tag and the MCS region, which encodes an amino acid sequence of Ile–Glu/Asp–Gly–Arg, the entire leader sequence including the His-tag and the cleavage sequence can easily be removed by treatment with Factor Xa, a mammalian serine protease that recognizes and cleaves the sequence of Ile–Glu/Asp–Gly–Arg↓.

#### 1. Determination of Optimum Digestion Conditions

- (a) Prepare Factor Xa buffer (see “Reagents needed”).
- (b) Set up two pilot cleavage reaction in two microcentrifuge tubes as follows:

Tube A:	
Fusion proteins	30 µg in 5–10 µl
10× digestion buffer	2.5 µl
Add dd.H <sub>2</sub> O to	29 µl
<u>Factor Xa</u>	<u>0.2 µg in 1µl</u>
Total volume	30 µl

Tube B:	
Fusion proteins	30 µg in 5–10 µl
10× digestion buffer	2.5 µl
Add dd.H <sub>2</sub> O to	29 µl
<u>Factor Xa</u>	<u>0.00</u>
Total volume	30 µl

Note: *Tube B will serve as control.*

- (c) Incubate the reactions at 4 to 37°C. Typically, the reactions can be incubated at room temperature.
- (d) Transfer 5- $\mu$ l aliquots from the reaction mixture into microcentrifuge tubes at each of the following time points: 6, 12, 18, 24, and 36 h after initiation of the reaction. Add 5  $\mu$ l of 2 $\times$  SDS sample loading buffer and place at -20°C until SDS-PAGE.
- (e) Carry out the time-course analysis of protease digested samples at step (d) by SDS-PAGE followed by Coomassie blue staining. The detailed protocols are described in Chapter 11. From the stained gel, identify the optimal time-point for large-scale digestion of fusion proteins.

### Reagent needed

- 10 $\times$  Factor Xa buffer  
500 mM Tris-HCl, pH 8.0  
1 M NaCl  
10 mM CaCl<sub>2</sub>

### 2. Large-Scale Cleavage of Fusion Proteins

Once the optimum incubation time is established, large-scale protease digestions can be carried out using 1 to 10 mg of fusion proteins under optimum conditions. If all goes well, the molecular weight of the cleaved proteins should be less than that of undigested proteins (Figure 18.3).

### 3. Purification of Cleaved Proteins with His-Bind Affinity Resin

To remove the cleaved leader sequence, the digested proteins can be readily purified by His-bind affinity matrix.

- (a) In a 1.5-microcentrifuge tube, charge 100 to 200  $\mu$ l of slurry of the His-bind resin with an equal volume of charge buffer (NiSO<sub>4</sub>) and suspend it to form a good suspension.
- (b) Spin down the resin at 1000 rev/min for 1 min and aspirate the supernatant.
- (c) Resuspend the resin in 1 ml of binding buffer. Spin down and aspirate as in step (b).
- (d) Resuspend the resin in 50  $\mu$ l of binding buffer and add 100  $\mu$ l of cleaved proteins to the resin. Mix well and incubate for 20 min at room temperature.
- (e) Spin down at 1200 rev/min for 1 min to pellet the resin and transfer the supernatant into a fresh tube.

Principle: *The cleaved His-tag leader sequence binds to the affinity resin but the digested proteins remain in the supernatant.*

- (f) Analyze part of the supernatant by SDS-PAGE.

### 4. Direct Cleavage and Purification of Matrix-Bound Proteins in Affinity Column

The His-tag leader sequence can be cleaved for the fusion proteins after the proteins bind to the His-bind resin. Below is the protocol for small-scale simultaneous purification and digestion of His-tag in a microcentrifuge

tube. This procedure, however, can be scaled up in an affinity column as desired.

- (a) In a 1.5-microcentrifuge tube, charge 200  $\mu\text{l}$  of slurry of His-bind resin with an equal volume of charge buffer ( $\text{NiSO}_4$ ) and suspend it to form a good suspension.
- (b) Spin down the resin at 1000 rev/min for 1 min and aspirate the supernatant.
- (c) Resuspend the resin in 1 ml of binding buffer and allow the resin to equilibrate for 30 min at room temperature. Spin down and aspirate as in step (b).
- (d) Resuspend the resin in 50  $\mu\text{l}$  of binding buffer and add 100  $\mu\text{l}$  of fusion protein sample to the resin. Mix well and incubate for 30 min at room temperature. Mix several times during the incubation period.
- (e) Spin down at 1000 rev/min for 1 min to pellet the resin and remove the supernatant.
- (f) Wash and spin down the resin with 1 ml of binding buffer twice and then 1 ml of washing buffer twice to eliminate nonspecific binding proteins from the resin.
- (g) Add 200  $\mu\text{l}$  of protease digestion cocktail to the resin, suspend it thoroughly, and incubate the reaction at room temperature for 12 to 24 h.
- (h) Spin down at 1200 rev/min for 1 min to pellet the resin and transfer the supernatant to a fresh tube.

Principle: *The cleaved His-tag leader sequence binds to the affinity resin but the digested proteins are eluted in the supernatant.*

- (i) If necessary, concentrate the protein samples via partially freeze drying the samples or partially lyophilizing in a Speed Vac System under cold conditions until a minimum volume (40 to 50  $\mu\text{l}$ ) is reached.
- (j) Analyze part of the supernatant by SDS-PAGE.

### Reagents needed

- *Binding buffer*  
20 mM Tris-HCl, pH 7.9  
0.5 M NaCl  
5 mM imidazole
- *Charge buffer*  
50 mM  $\text{NiSO}_4$
- *Washing buffer*  
20 mM Tris-HCl, pH 7.9  
0.5 M NaCl  
60 mM imidazole
- *10 $\times$  Factor Xa buffer*  
500 mM Tris-HCl, pH 8.0  
1 M NaCl  
10 mM  $\text{CaCl}_2$



- *Protease digestion cocktail*  
 10× digestion buffer            20  $\mu$ l  
 Appropriate protease            0.8–1.2  $\mu$ g  
 Add dd.H<sub>2</sub>O to a total volume of 200  $\mu$ l

#### 18.2.4.4.2 Protocol 2. Enzymatic Cleavage of Leader Sequence with Thrombin

If the vector contains a sequence between the His-tag and the MCS region, which encodes an amino acid sequence of Leu–Val–Pro–Arg–Gly–Ser, the leader sequence (the His-tag and majority of the cleavage sequence) can be removed by thrombin with ease. Thrombin is a mammalian serine protease that recognizes and cuts the sequence between Arg and Gly: Leu–Val–Pro–Arg↓–Gly–Ser. The procedures for digestion are quite similar to those described for Factor Xa cleavage except for the use of 10× thrombin buffer.

- *10× Thrombin buffer*  
 0.5 M Tris–HCl, pH 7.5  
 1.5 M NaCl  
 25 mM CaCl<sub>2</sub>

#### 18.2.4.4.3 Protocol 3. Chemical Cleavage of Fusion Proteins with Cyanogen Bromide

If only one Met residue exists in each protein and the Met is not important to the biological activity of the protein, the leader sequence fusion proteins can easily be cleaved with cyanogen bromide (CNBr). CNBr cleaves the C-terminal side of methionine residues at low pH in 70% formic acid. The general procedures are similar to those described for enzymatic digestion, including the small pilot trial reaction and the large-scale reaction. The chemical is dissolved in 70% formic acid at a concentration of 50 mg/ml. However, the CNBr can be replaced with 6 M guanidine–HCl/0.2 M HCl.


## 18.3 OVEREXPRESSION OF SPECIFIC PROTEINS IN EUKARYOTIC SYSTEMS

Unlike the prokaryotic systems described above, eukaryotic systems make it possible for the expressed proteins to undergo posttranslational modifications. There are several vector systems that have been developed for protein expression in eukaryotic cells, including baculovirus and mammalian and yeast systems. Because baculovirus and mammalian systems are relatively complicated, time-consuming, and costly, this chapter primarily focuses on the introduction of the yeast system, *Pichia pastoris*, which is widely used and commercially available from Invitrogen. Compared to other eukaryotic systems, it is easier to manipulate the yeast genome and to culture yeast without the need for a CO<sub>2</sub> incubator. The best-known yeast strain is *Saccharomyces cerevisiae*. *P. pastoris* shares many features with *S. cerevisiae*.

The primary principles underlying the use of *P. pastoris* as a protein expression system begins with its genome containing a gene, called *AOX1*. This gene encodes alcohol oxidase, which is a key enzyme that enables the yeast to metabolize methanol

as its sole carbon source. DNA recombination technology makes it possible to manipulate the *AOX1* gene and use its promoter to drive the expression of foreign protein at a very high level.<sup>4-6</sup> As diagrammed in Figure 18.4, the coding region of the *AOX1* gene is deleted and its promoter (5'-*AOX1*) and 3' portion (3'-*AOX1*) are utilized for the plasmid-based expression vector. The functions of each of the components of the vector are described as follows:


1. **A strong promoter (5'-*AOX1*).** It facilitates DNA construct integration into the *AOX1* locus of the *Pichia* genome and drives the expression of foreign proteins.
2. **A strong ribosome binding site.** A bacteriophage RBS consists of AAGGAG located very closely upstream from the first codon ATG will provide a high efficiency of translational initiation. The small subunits of ribosomes will selectively recognize and bind to the sequence, thus initiating the translation of the mRNA. With this sequence, the translational rate can be enhanced up to 10-fold.
3. **The ATG codon.** ATG (AUG in mRNA) immediately follows the RBS sequence. This will be the first codon for the recombinant protein. The purpose of including this first codon is attributable to the very next leader sequence, including a secretory sequence, His-tag, and a cleavage sequence. Because the first codon is fixed in the vector, a cDNA or gene to be cloned should be carefully oriented so that absolutely no stop codon and no reading frame shifts are allowed. Detailed cautions will be noted in cloning of the insert into the vector.
4. **The signal sequence (SS).** This DNA sequence will code for an N-terminal leader sequence (e.g.,  $\alpha$ -factor signal sequence), which will serve to secrete the expressed proteins into culture medium. As a result, purification of the proteins will be significantly simplified.



**FIGURE 18.4** A diagram of eukaryotic expression vector for large-scale expression and purification of specific proteins in yeast strain, *Pichia pastoris*.

5. **His-tag.** The His-tag sequence located immediately after the SS will code for 6 to 10 consecutive histidine residues. These His residues will be a part of the N-terminal leader sequence of a protein to be expressed from the cloned cDNA or gene and will serve as the affinity tag for rapid purification of the protein with metal chelation chromatography using an appropriate His-Bind resin.
6. **PCS.** A sequence encoding a PCS is designed between the His-tag and the MCS. The amino acid sequence encoded by this sequence will be the target site for an appropriate protease (e.g., thrombin, Factor Xa, or Factor Xa). This will allow removal of the N-terminal His-tag leader sequence *in vitro* as desired. It should be noted here that noncleaved fusion proteins will be OK for use as antigens. However, for biochemical, cell biology, or enzyme assays, the leader sequence may need to be removed because a native protein is better than a fusion protein.
7. **Multiple cloning site.** MCS contains different restriction enzyme sites for insertion of a specific cDNA for expression of a specific protein. Usually, commercial vectors contain overlapping bases for adjacent restriction enzymes. Perhaps it is for ease of use that all three reading frames vector series have been developed. This strategy will allow one to clone a cDNA to be expressed at different restriction enzyme sites without causing reading frame shifts.
8. **Terminator.** A transcriptional terminator sequence [splicing and poly(A) site] follows immediately downstream from the MCS.
9. **HIS4 gene.** This gene codes for histidinol dehydrogenase that will serve as a selectable marker for isolation of recombinant *Pichia* colonies.
10. **3'-AOX1.** This 3'-portion of the AOX1 gene will facilitate plasmid construct integration at the AOX1 locus.
11. **Plasmid backbone (Ampicillin gene, F1 ori, and ColE1).** A plasmid-based expression vector should contain the plasmid backbone elements. The ampicillin-resistant gene or *Amp<sup>r</sup>* will serve as an antibiotic marker for selection of positive transformed colonies. In theory, only bacteria carrying an *Amp<sup>r</sup>* gene in the introduced plasmid DNA can be resistant to ampicillin killing action. The F1 ori sequence will allow rescue of single-stranded plasmid DNA by infection of F'-containing host strains with helper phage (e.g., R408). The ColE1 element makes it possible to replicate the introduced plasmid DNA in as high a copy number as possible.

Because of the unique restriction enzyme sites indicated in the figure, if recombinant plasmid DNA is digested with a unique restriction enzyme such as *Bgl*III or *Not*I, the linearized DNA can undergo gene replacement by DNA homologous recombination at the 5'-AOX1 and 3'-AOX1 sites (Figure 18.5). When this occurs, the expression cassette will integrate and replace the endogenous AOX1 gene, generating a mutant AOX1 gene. As a result, most of the alcohol oxidase activity of the yeast strain will be lost, producing a strain that is phenotypically methanol utilization slow or Mut<sup>s</sup>. Therefore, the cells will grow slowly in a methanol medium. This can serve as an indicator of transformation for integration of a foreign gene. On the other hand,




**FIGURE 18.5** Replacement of AOX1 gene with a cDNA expression cassette in *P. pastoris*.

if the recombinant plasmid DNA is cut with a unique enzyme such as *SacI* or *SallI*, it will be possible for the linearized DNA to integrate the 5'-AOX1 or His4 site into the yeast genome. Single or multiple copies of insertion may occur. The entire project is outlined in Figure 18.6.

### 18.3.1 CLONING OF A cDNA TO BE EXPRESSED INTO EXPRESSION VECTORS

Invitrogen offers excellent plasmid-based *Pichia* expression vectors, including pHIL-D2, pHIL-S1, and pPIC9. Selection of a specific vector depends on intracellular or secretory protein expression. With permission from Invitrogen, vectors may be modified or altered as diagrammed in Figure 18.4, which is suitable for rapid



**FIGURE 18.6** Flowchart of protein overexpression in yeast.

cleavage and purification of the proteins of interest. Detailed protocols concerning DNA digestion, preparations of vector and insert DNA, ligation, transformation, selection, and purification of plasmid DNA are described in Chapter 4. This section focuses primarily on several special precautions that should be taken when cloning a cDNA for expression.

1. Restriction enzyme(s) used for DNA digestion should be unique so as to cut outside the entire coding region of the cDNA to be cloned at the MCS of the vector. To ensure success in protein expression, no enzyme cuts are allowed inside the coding region of the cDNA or outside the MCS region of the vector DNA. Detailed restriction enzyme mapping should be carried out when preparing vector and insert DNA.
2. Carefully trim out as much as possible the 5'-UTR and 3'-UTR regions of the cDNA to be expressed using appropriate restriction enzymes or the PCR approaches. In our experience, long 5'-UTR or 3'-UTR may alter the reading frame and/or decrease the efficiency of protein expression.
3. Because of the orientation of the driving promoter 5'-AOX1 and the first ATG codon, which are already fixed in place in the vector, the poly(T) strand should be inserted instead of the poly(A) of the cDNA in 3'→5' orientation downstream from the driving promoter. In other words, the cDNA to be expressed should be cloned in its sense orientation under the control of the driving promoter. No antisense cloning is allowed.
4. Because the first codon ATG is fixed in place in the vector, the cDNA to be expressed must be carefully oriented so that absolutely no stop codon and no reading frame shifts are allowed. To make sure that the cDNA has been cloned at the right position with the correct reading frame starting from ATG in the vector, it is strongly recommended that DNA constructs obtained be carefully analyzed by appropriate restriction enzyme digestion pattern analysis and by DNA sequencing of the 5'-junction site. However, the entire cDNA or construct does not need to be sequenced. In the authors' experience, as long as the 5' portion of the cloned cDNA has the correct sequence and the right reading frame with regard to the ATG codon and the leading sequence, the constructs should be fine without sequencing the whole cDNA.

## 18.3.2 TRANSFORMATION OF YEAST *PICHIA* WITH EXPRESSION DNA CONSTRUCTS

### 18.3.2.1 Protocol A. Linearization of Plasmid DNA

Linearization of plasmid constructs depends on particular types of transformants to be selected. We recommend that both types of HIS<sup>+</sup>Mut<sup>s</sup> and HIS<sup>+</sup>Mut<sup>+</sup> GS115 transformants be isolated. As shown in Figure 18.4, to obtain HIS<sup>+</sup>Mut<sup>s</sup>, plasmid DNA should be digested with the unique enzyme, *NotI* or *BglII*, assuming that the cloned cDNA does not contain *NotI* or *BglII* site. The linearized DNA will undergo AOX1 gene replacement, resulting in the HIS<sup>+</sup>Mut<sup>s</sup> genotype of transformants (Figure 18.5). In this way, the HIS<sup>+</sup>Mut<sup>s</sup> phenotype of transformants will

be isolated easily using His and MeOH media. AOX1 gene replacement by DNA homologous recombination will generate one or two copies of integrated gene to be expressed. To increase the integration copy numbers of plasmid constructs, it is recommended that one linearize the DNA with *SalI* or *SacI* (Figure 18.4). The merit of doing this is that the linearized DNA constructs may undergo random or site specific (5'-AOX1 or HIS4 site) integrations, resulting in one or more copies of the cassette in the genome of *Pichia* GS115. The HIS<sup>+</sup>Mut<sup>+</sup> transformants can be selected with a medium containing the His residue. Compared with gene replacement, multiple copies of integration will likely enhance the expression of foreign proteins at a high level.

Therefore, we recommend that the same plasmid DNA constructs be linearized in three Eppendorf tubes as follows:

1. Linearize 15 to 25  $\mu\text{g}$  DNA with *NotI* or *BgIII*.
2. Digest 15 to 25  $\mu\text{g}$  DNA with *SalI*.
3. Linearize 15 to 25  $\mu\text{g}$  DNA with *SacI*.

After digestion and purification of the DNA, pool the second and the third samples together, generating a DNA construct mixture that is linearized with *SalI* or *SacI*. The DNA mixture and the DNA linearized with either *NotI* or *BgIII* can then be separately transferred into yeast GS115. As a result, HIS<sup>+</sup>Mut<sup>+</sup> and multiple copies of HIS<sup>+</sup>Mut<sup>+</sup> transformants can be isolated, respectively.

Detailed protocols for restriction enzyme digestion, electrophoresis, and DNA purification are described in Chapter 4.

### 18.3.2.2 Protocol B. Transformation of *Pichia* by Electroporation

Compared with other methods, electroporation is the fastest method for transforming yeast with high efficiency of transformants. It is not necessary to prepare spheroplasts. In spite of the fact that up to 50% of cells may be killed by the high electric pulse, high efficiency of transformants will overcome such a minor drawback.

1. Culture 4 ml of *P. pastoris* in yeast peptone dextrose (YPD) medium at 30°C overnight with shaking at 250 rev/min.
2. Inoculate 0.4 ml of the culture into 500 ml of YPD medium. Grow the cells at 30°C overnight with shaking at 250 rev/min. The OD<sub>600</sub> will be 1.2 to 1.5.
3. Centrifuge at 1600 *g* for 5 min at 4°C, aspirate the supernatant, and resuspend the cells in 250 ml ice-cold sterile water.
4. Centrifuge and remove the supernatant as in step 3 and resuspend the cells in 250 ml ice-cold sterile water.
5. Centrifuge and remove the supernatant as in step 3 and resuspend the cells in 20 ml ice-cold 1 M sorbitol.
6. Centrifuge and remove the supernatant as in step 3 and resuspend the cells in 1.5 ml ice-cold 1 M sorbitol.

Note: The extensive washing of the cells will minimize the salt concentration and reduce the killing percentage during electroporation.

7. Add 80  $\mu$ l of the cells and 15 to 25  $\mu$ g linearized DNA to a 0.2-cm electroporation cuvette on ice. Incubate the mixture on ice for 5 min.
8. Carry out electroporation according to the manufacturer's instructions. If one uses the Gene Pulser from Bio-Rad, voltage, capacitance ( $\mu$ F), and resistance ( $\Omega$ ) may be 1500, 25, and 200, respectively. If an Electroporator II unit from Invitrogen is utilized, the three parameters should be 1500, 50, and 200, respectively, which is suitable for yeast electroporation.
9. Quickly add 1 ml of sorbitol solution to the cuvette to recover the cells and spread 0.2 to 0.5 ml of the cell suspension onto each 100-mm RD plate.
10. Invert the plates and incubate them at 30°C for 3 to 6 days. Colonies should be visible after 3 to 4 days incubation. Proceed to phenotype screening.

### Reagents needed

- *20% Dextrose solution*  
Dissolve 20 g dextrose (D-glucose) into a final volume of 100 ml dd.H<sub>2</sub>O and filter-sterilize.
- *YPD or YEPD (yeast extract peptone dextrose) medium (for 1 l)*  
20 g Peptone  
10 g Yeast extract  
Dissolve in 800 ml of dd.H<sub>2</sub>O and autoclave for 20 min in liquid cycle. Cool down to approximately 50°C and add dextrose stock solution to final concentration of 2% (w/v) and add sterile water to 1000 ml. Store at room temperature or 4°C until use.
- *1 M Sorbitol in distilled water*
- *RD plates (for 1 l)*  
Dissolve 186 g sorbitol and 20 g agar in 700 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place it in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10 $\times$  D, 100 ml of 10 $\times$  YNB (yeast nitrogen base), 2 ml 500 $\times$  B, 10 ml of 100 $\times$  AA, and 78 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution. Pour the mixture into plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.
- *RDH (Regeneration Dextrose and Histidine) plates (for 1 l)*  
Dissolve 186 g sorbitol and 20 g agar in 700 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place it in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10 $\times$  D, 100 ml of 10 $\times$  YNB, 2 ml 500 $\times$  B, 10 ml of 100 $\times$  AA, 10 ml of 100 $\times$  histidine, and 68 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution. Mix it and pour the mixture into plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for 2 days. Store the plates at 4°C until use.


### 18.3.2.3 Protocol C. Preparation of Spheroplasts for Transformation

If an electroporator is not available, transformation of yeast can be carried out with spheroplasts. Compared to electroporation in Protocol B, transformation of spheroplasts is much more complicated but it is a well-established method and is widely used.

1. Prepare yeast culture media and plates (see “Reagents needed”).
2. Streak *P. pastoris* strain GS115 onto a YPD plate as shown in Figure 18.7.
3. Inoculate a single colony into 10 ml of YPD medium in a flask and culture the cells overnight at 28 to 30°C with shaking at 250 rev/min. Store the cells at 4°C until use.
4. Inoculate 20  $\mu$ l of the cell culture at step 3 into 200 ml of YPD medium in a 500-ml culture flask. Grow the cells at 28 to 30°C with shaking at 250 rev/min. Six hours later, check  $OD_{600}$  once every hour to monitor the density of the cells. Store the cells at 4°C until use.

Note: An  $OD_{600}$  of 0.2 to 0.3 will result in high efficiency of transformation.

5. Centrifuge at 1600 g at room temperature for 8 min and aspirate the supernatant.
6. Resuspend the cells in 25 ml of dd.H<sub>2</sub>O and pellet the cells as in step 5. Repeat this step one more time.
7. Wash the cells by resuspending them in 25 ml of SED and pellet the cells as in step 5.
8. Resuspend the cells in 25 ml of 1 M sorbitol and centrifuge as in step 5.
9. Resuspend the cells by swirling in 20 ml of SCE buffer and aliquot the cells into two tubes, A and B. Place the samples at room temperature.
10. Carry out a time-course of Zymolyase digestion to determine the optimum conditions.
  - (a) Thaw the Zymolyase on ice and mix the slurry mixture well.



**FIGURE 18.7** Streaking of yeast stock in a “zigzag” pattern on a YPD plate. Two days later, well-isolated colonies will be generated in last streaking area on plate.



- (b) Set a UV-Vis spectrophotometer at 800 nm and blank it with a reference tube containing 200  $\mu\text{l}$  of SCE buffer and 800  $\mu\text{l}$  of 5% SDS solution.
- (c) Label 11 microcentrifuge tubes as follows: 0, 5, 10, 15, 20, 25, 30, 35, 40, 45, and 50. To each tube, add 800  $\mu\text{l}$  of 5% SDS solution.
- (d) Transfer 200  $\mu\text{l}$  of cell suspension from tube A (step 9 above) into the tube labeled "0". Place the tube on ice until use. This tube serves as the zero time point.
- (e) Quickly mix Zymolyase and add 7.5  $\mu\text{l}$  of it to tube A and gently mix. Incubate the digestion at 30°C without shaking because the Zymolyase digested cells are very weak.
- (f) Every 5 min, transfer 200  $\mu\text{l}$  of the cells from tube A into an appropriate tube labeled at step (c). Place the tubes on ice until use.
- (g) Measure the  $\text{OD}_{600}$  for all samples and determine the percentage of spheroplasting for each time point using the following equation:

$$\% \text{ Spheroplasting} = 100 - [(\text{OD}_{600} \text{ at time } t / \text{OD}_{600} \text{ zero time point}) \times 100]$$

For instance, if  $t = 0$ ,  $\text{OD}_{600}$  is 0.2; if  $t = 20$  min, the  $\text{OD}_{600}$  is 0.04. Then,

$$\begin{aligned} \% \text{ Spheroplasting} &= 100 - [(0.04/0.2) \times 100] \\ &= 100 - 20 \\ &= 80\% \end{aligned}$$

In general, 70% to 80% spheroplasting is considered an optimum digestion condition.

11. Quickly mix Zymolyase and add 7.5  $\mu\text{l}$  of it to tube B at step 9 and gently mix it. Incubate the digestion at 30°C without shaking for the optimum incubation time established above.
12. Centrifuge at 800 g for 10 min at room temperature and carefully aspirate the supernatant.
13. Gently resuspend the cells in 10 ml of 1 M sorbitol solution by gentle tapping the tube instead of vortexing. Centrifuge and remove the supernatant as in step 12.  
*Note: Sorbitol will help the spheroplasts regenerate cell walls after transformation.*
14. Wash the cells by resuspending them in 10 ml of CaS buffer and carry out centrifugation as in step 12.
15. Gently resuspend the spheroplasts in 500 to 600  $\mu\text{l}$  of CaS buffer and use the spheroplasts in 30 min for high efficiency of transformation.

### Reagents needed

- 20% Dextrose solution  
20 g Dextrose (glucose) in final 100 ml dd.H<sub>2</sub>O and filter-sterilize.

- *YPD or YEPD medium (for 1 l)*  
20 g Peptone  
10 g Yeast extract  
Dissolve in 800 ml of dd.H<sub>2</sub>O and autoclave for 20 min in liquid cycle. Cool down to approximately 50°C and add dextrose stock solution to final concentration of 2% (w/v) and sterile water to 1000 ml. Store at room temperature or 4°C until use.
- *YPD or YEPD plates (for 1 l)*  
20 g Peptone  
10 g Yeast extract  
20 g Difco agar  
Dissolve in 800 ml of dd.H<sub>2</sub>O and autoclave for 20 min in liquid cycle. Cool down to approximately 50°C with slow stirring and add dextrose stock solution to a final concentration of 2% (w/v). Add sterile water to 1000 ml. Pour plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.

The following buffers or solutions should be autoclaved or sterile-filtered:

- *1 M Sorbitol in distilled water*
- *0.5 M EDTA stock*  
0.5 M EDTA in 900 ml distilled water and warm the solution to completely dissolve EDTA. Allow it to cool down to approximately 40°C and begin to adjust the pH to 8.0 while the solution is cooling down to <30°C. Add sterile water to 1000 ml. Store at room temperature until use.
- *1 M Tris-HCl stock, pH 7.5*  
1 M Tris in 900 ml distilled water and adjust the pH to 7.5. Add sterile water to 1000 ml. Autoclave and store at room temperature until use.
- *0.5 M sodium citrate stock, pH 5.8*  
1 M Tris in 900 ml distilled water and adjust the pH to 5.8. Add sterile water to 1000 ml. Store at room temperature until use.
- *SE buffer*  
1 M Sorbitol  
25 mM EDTA (from stock)
- *SCE buffer*  
1 M Sorbitol  
1 mM EDTA (from stock)  
10 mM Sodium citrate (from stock)
- *CaS buffer*  
1 M Sorbitol  
10 mM Tris-HCl (from stock)  
10 mM CaCl<sub>2</sub>
- *Zymolyase*  
3 mg/ml in distilled water. Store at -20°C before use.

### 18.3.2.4 Protocol D. Transformation of Spheroplasts with Linearized DNA

1. Prepare culture media and plates (see “Reagents needed”). This should be done several days before transformation.
2. Transfer 0.1 ml of the spheroplasts prepared in Protocol C into a sterile 10- or 15-ml Falcon plastic tube with a cap and add 15 to 25  $\mu\text{g}$  linearized DNA constructs to spheroplast suspension. Gently mix and incubate at room temperature for 10 to 15 min.
3. During incubation, prepare 1 ml of fresh PEG–CaT solution for each transformation with 1:1 (v/v) of 40% PEG/CaT solution.
4. When the incubation is complete, add 1 ml of fresh PEG–CaT solution to the mixture, gently mix, and continue to incubate at room temperature for 10 to 15 min.
5. Centrifuge at 800  $g$  for 10 min at room temperature, then carefully and completely aspirate the supernatant.
6. Gently resuspend the pellet in 150  $\mu\text{l}$  of SOS medium and incubate it at room temperature for 20 to 25 min.
7. Add 0.85 ml of 1 M sorbitol solution to mixture.
8. Melt pre-made RD agarose using a microwave oven, cool it down to approximately 60°C, and then place it in a 55°C water bath before use.  
*Tip: Aliquot the top agarose medium into sterile tubes (5 ml each) and place the tubes in a water bath.*
9. Add 0.1 ml of the spheroplast–DNA mixture obtained at step 6 to 5 ml of molten RD agarose, briefly mix, and pour on a 100-mm RD plate. Quickly and carefully overlay the entire surface of the plate with the mixture. Allow the agarose to harden at room temperature for about 4 min. The surface should be very flat and without clumps. Repeat the procedure until all plates are complete.
10. Add 0.1 ml of spheroplasts without DNA constructs to 5 ml of molten RD agarose and pour on a plate.  
*This will serve as a negative control.*
11. Invert the plates to avoid potential moisture drops and incubate the plates at 28 to 30°C for 4 to 7 days. Proceed to phenotype screening.  
*Transformant colonies should be visible after 4 days of incubation. However, no colonies should be formed in the negative control plate.*

### Reagents needed

- 40% PEG  
40% (w/v) PEG in distilled water
- CaT buffer  
20 mM Tris–HCl, pH 7.5 (from stock) and 20 mM  $\text{CaCl}_2$
- SOS solution  
1 M sorbitol, 0.3 $\times$  YPD and 10 mM  $\text{CaCl}_2$
- 10 $\times$  D  
200 g dextrose or D-glucose in a final volume of 1000 ml water. Filter-sterilize it and store at room temperature.

- *10× YNB (for 1 l)*  
134 g YNB with ammonium sulfate but no amino acids in a final volume of 1 l. Briefly warm to dissolve the chemicals and filter-sterilize. Store at 4°C.
- *100× Histidine*  
0.4 g L-Histidine in 100 ml water. Briefly warm to dissolve the chemical and sterilize the solution. Store at 4°C.
- *100× AA*  
Place 0.5 g each of L-glutamic acid, L-methionine, L-lysine, L-leucine, and L-isoleucine in 100 ml water. Briefly warm to dissolve the chemicals and filter-sterilize. Store at 4°C.
- *500× B*  
20 mg Biotin in 100 ml water. Sterilize it and store at 4°C.
- *RD (Regeneration Dextrose) medium (for 1 l)*  
Dissolve 186 g sorbitol in 700 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Make a mixture containing 100 ml of 10× D, 100 ml of 10× YNB, 2 ml 500× B, 10 ml of 100× AA, and 88 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution.
- *RDH medium (for 1 l)*  
Dissolve 186 g sorbitol in 700 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place it in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10× D, 100 ml of 10× YNB, 2 ml 500× B, 10 ml of 100× AA, 10 ml of 100× histidine and 78 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution.
- *RD plates (for 1 l)*  
Dissolve 186 g sorbitol and 20 g agar in 700 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10× D, 100 ml of 10× YNB, 2 ml 500× B, 10 ml of 100× AA, and 78 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution. Pour the mixture into plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.
- *RDH plates (for 1 l)*  
Dissolve 186 g sorbitol and 20 g agar in 700 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10× D, 100 ml of 10× YNB, 2 ml 500× B, 10 ml of 100× AA, 10 ml of 100× histidine, and 68 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution. Mix it and pour the mixture into plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.


- *RD top agarose (500 ml)*  
Dissolve 93 g sorbitol and 10 g agar or agarose in 350 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 50 ml of 10× D, 50 ml of 10× YNB, 1 ml 500× B, 5 ml of 100× AA, and 49 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution. The agarose mixture can be immediately used or stored at 4°C. Premelt it in a microwave and cool down to approximately 45°C before use.
- *RDH top agarose (500 ml)*  
Dissolve 93 g sorbitol and 10 g agar or agarose in 350 ml distilled water and autoclave for 20 min in liquid cycle. Allow it to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 50 ml of 10× D, 50 ml of 10× YNB, 1 ml 500× B, 5 ml of 100× AA, 5 ml of 100× histidine, and 39 ml of sterile water. Warm the mixture to about 45°C and add it to the sorbitol solution. The agarose mixture can be immediately used or stored at 4°C. Premelt it in a microwave and cool down to approximately 45°C before use.

### 18.3.3 SCREENING AND ISOLATION OF HIS<sup>+</sup>MUT<sup>+</sup> AND HIS<sup>+</sup>MUT<sup>s</sup> PHENOTYPE

To better understand the principle of selection or screening, it is necessary to go back to the expression cassette shown in Figure 18.4. If plasmid constructs are linearized with *NotI* or *BglII* and introduced into *Pichia* GS115, AOX1 gene replacement is expected to take place, resulting in His<sup>+</sup>Mut<sup>s</sup> genotype transformants. Transformant colonies will display if the transformed cells are plated onto a plate lacking histidine. In other words, if all goes well, only His<sup>+</sup> phenotype transformants will grow. Additionally, if His<sup>+</sup> phenotype transformants are inoculated on a plate containing methanol, they will grow slowly (Mut<sup>s</sup> phenotype), as compared with wild-type cells, because at least one copy of the AOX1 gene coding for alcohol oxidase has been replaced by the protein expression cassette. Because of the decrease in alcohol oxidase activity, there is no sufficient enzyme to metabolize the methanol as the sole carbon source. This provides an efficient way to distinguish positive transformants (His<sup>+</sup>Mut<sup>s</sup> phenotype).

If the plasmid constructs are linearized with *SalI* or *SacI* and then transferred into the yeast, AOX1 gene replacement will most likely not occur. Instead, multiple copies of integration may take place. If all goes well, phenotype of His<sup>+</sup>Mut<sup>+</sup> transformants will be obtained. Therefore, they can grow on plates without histidine and are capable of metabolizing methanol as with wild-type GS115. The screening procedure is as follows:

1. Pick a His<sup>+</sup> colony using a sterile toothpick and streak it in a single spot on an MM plate first and then on an MD plate. Use a fresh toothpick and repeat streaking until 66 to 100 colonies have been inoculated. Mark and record the position for each individual transformant on the plates. Meanwhile, wild-type GS115 colonies should be streaked in the same way as with the control.
2. Invert the plates and incubate at 30°C for 2 to 4 days.



**FIGURE 18.8** Screening of transformant GS115 containing AOX1 gene replacement. (a) Colonies growing on an MD plate. (b) Same colonies are inoculated on an MM plate.

- Score His<sup>+</sup>Mut<sup>s</sup> colonies that grow normally on MD plates but very slowly on MM plates, as compared to wild-type GS115 cells (Figure 18.8). On the other hand, His<sup>+</sup>Mut<sup>t</sup> transformants should grow normally on both MD and MM plates.

### Reagents needed

- *10× M*  
5% Methanol in distilled water and then filter-sterilized
- *MD (minimal dextrose) medium (for 1 l)*  
Prepare a mixture containing 100 ml of 10× D, 100 ml of 10× YNB, and 2 ml 500× B. Add distilled water to 1000 ml and filter-sterilize. Store the plates at 4°C until use.
- *MD (minimal dextrose) plates (for 1 l)*  
Dissolve 15 g agar in 800 ml distilled water and autoclave for 20 min using the liquid cycle. Allow the solution to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10× D, 100 ml of 10× YNB and 2 ml 500× B. Warm the mixture to about 45°C and add it to the solution. Pour the mixture into plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.
- *MDH (minimal dextrose histidine) plates (for 1 l)*  
Dissolve 15 g agar in 790 ml distilled water and autoclave for 20 min in liquid cycle. Allow the solution to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10× D, 100 ml of 10× YNB, 2 ml 500× B, and 10 ml of 100× histidine stock. Warm the mixture to about 45°C and add it to the solution. Pour the mixture into plates (approximately

30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.

- *MM (minimal methanol) medium (for 1 l)*

Prepare a mixture containing 100 ml of 10× M, 100 ml of 10× YNB, and 2 ml 500× B. Add distilled water to 1000 ml and filter-sterilize. Store the plates at 4°C until use.

- *MM (minimal methanol) plates (for 1 l)*

Dissolve 15 g agar in 800 ml distilled water and autoclave for 20 min in liquid cycle. Allow the solution to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10× M, 100 ml of 10× YNB, and 2 ml 500× B. Warm the mixture to about 45°C and add to the solution. Pour the mixture into plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.

- *MMH (minimal methanol histidine) plates (for 1 l)*

Dissolve 15 g agar in 790 ml distilled water and autoclave for 20 min in liquid cycle. Allow the solution to cool down to approximately 60°C with slow stirring and then place in a 55°C water bath before use. Prepare a mixture containing 100 ml of 10× M, 100 ml of 10× YNB, 2 ml 500× B, and 10 ml of 100× histidine stock. Warm the mixture to about 45°C and add it to the solution. Pour the mixture into plates (approximately 30 ml/100 mm plate) in a laminar flow hood and allow the plates to evaporate the excess moisture at room temperature for a couple of days. Store the plates at 4°C until use.

#### 18.3.4 IDENTIFICATION OF TRANSFORMANTS CONTAINING cDNA TO BE EXPRESSED

Based on the phenotype screening data, His<sup>+</sup>Mut<sup>s</sup> and His<sup>+</sup>Mut<sup>+</sup> transformants may be characterized by PCR to make sure that the cDNA to be expressed is integrated into the host genome. To obtain this information, a forward primer can be designed in the 5'-P<sub>AOX1</sub> region, and a reverse primer designed from the 3'-end of the cDNA. Alternatively, the forward primer may be designed from the 5'-end of the cDNA and the reverse primer designed from the 3'-AOX1. After PCR amplification using genomic DNA from individual colonies, analyze the PCR products by 1% agarose gel electrophoresis. Positive transformants should reveal a DNA band as expected. If not, discard the colony. Detailed PCR protocols and agarose gel electrophoresis are described in Chapter 2. In addition, the insertion copy number of the cDNA can be determined by digesting yeast genomic DNA with a restriction enzyme that cuts outside the cDNA. The digested DNA is subjected to Southern blot hybridization using the cDNA as a probe. Compared to non-transfected control DNA, the number of detected bands will most likely be the copy number of the cDNA insertion. Detailed protocols for Southern blotting are described in Chapter 7.

### 18.3.5 EXPRESSION OF PROTEINS IN TRANSFORMANTS

#### 18.3.5.1 Determination of Optimum Conditions for Protein Expression


Before carrying out large-scale expression of proteins of interest, it is necessary to perform a time-course expression on a small scale.

1. Inoculate individual positive GS115 transformants (His<sup>+</sup>Mut<sup>s</sup> or His<sup>+</sup>Mut<sup>t</sup> with cDNA inserts confirmed) into 10 ml of BMG or BMGY in a 125-ml flask and grow the cells at 28 to 30°C for 12 to 16 h with shaking at 250 rev/min. An OD<sub>600</sub> = 2–6 indicates that the cells are in log-phase state of growth.
2. Centrifuge at 3000 g for 5 min at room temperature and aspirate the supernatant. To induce expression, resuspend the cells in MM, BMM, or BMMY medium to an OD<sub>600</sub> = 1.0.
3. Grow 50 ml of the cell suspension cells at 28 to 30°C with shaking at 250 rev/min.
4. Add 100% methanol to final concentration of 0.5% every 24 h.
5. Label nine microcentrifuge tubes (1.5 ml) for nine time points: 0, 12, 24, 36, 48, 60, 72, 84, and 96. Transfer 1 ml of the cell culture into an appropriate time point tube since the addition of methanol.
6. Centrifuge at 3000 g for 5 min at room temperature. Transfer the supernatant into a fresh tube for secreted expression and store the supernatant and cell pellet at –80°C until use.
7. Analyze both the supernatant and cell pellets for protein expression by SDS-PAGE followed by Coomassie blue staining, or by western blot analysis if specific antibodies are available. The cells can be completely solubilized under denaturation conditions, which can be loaded into SDS-PAGE. The detailed protocols for protein extraction, solubilization, SDS-PAGE, and western blot analysis are described in a great detail in Chapter 11.  
*Note: The size of the expressed protein can be estimated based on the amino acids encoded by the reading frame of the cloned cDNA plus the leader sequence, assuming that the average molecular weight for each amino acid is 100 Da. However, it does not matter if it is not convenient to estimate the size of the product because, if all goes well, the band of the expressed protein should be much larger than that of an uninduced protein sample, and there should be a time-course induction pattern (Figure 18.9).*
8. After characterization of transformant colonies, the colonies that produce large amounts of foreign proteins should be frozen back in as many vials as possible using sterile glycerol to a final concentration of 15% (v/v) and stored at –80°C.

#### Reagents needed

- 10× GY  
10% (v/v) of glycerol in distilled water and sterilize by filtering.
- 1 M potassium phosphate buffer, pH 6.0  
13.2% (v/v) of 1 M K<sub>2</sub>HPO<sub>4</sub> and 86.8% (v/v) of 1 M KH<sub>2</sub>PO<sub>4</sub>. If necessary, adjust the pH with phosphoric acid or KOH.





**FIGURE 18.9** Analysis of time-course of protein expression yeast by SDS-PAGE and Coomassie blue staining. Lanes 1 to 9 indicate induction of a 110-kDa protein with methanol at 0, 12, 24, 36, 48, 60, 72, 84, and 96 h, respectively.

- *BMG (buffered minimal glycerol)*  
700 ml of distilled water, 100 ml of 10× YNB, 100 ml of 1 M potassium phosphate buffer, pH 6.0, 2 ml of 500× B, and 100 ml of 10× GY. Mix well and sterilize by filtering. Store at 4°C.
- *BMM (buffered minimal methanol)*  
700 ml of distilled water, 100 ml of 10× YNB, 100 ml of 1 M potassium phosphate buffer, pH 6.0, 2 ml of 500× B, and 100 ml of 10× M. Mix well and sterilize by filtering. Store at 4°C.

### 18.3.5.2 Large-Scale Expression of Proteins

Once the optimal conditions have been determined for individual colonies, expression of the protein of interest can be scaled up using large volumes as in fermentation approaches.

1. Inoculate a GS115 transformant colony ( $\text{His}^+\text{Mut}^s$  or  $\text{His}^+\text{Mut}^+$  with cDNA inserts confirmed) into 25 ml of BMG or BMGY in a 250-ml flask and grow the cells at 28 to 30°C for 12 to 16 h with shaking at 250 rev/min. An  $\text{OD}_{600} = 2\text{--}6$  indicates that the cells are in log-phase state of growth.
2. Centrifuge at 3000  $g$  for 5 min at room temperature and aspirate the supernatant. To induce expression, resuspend the cells in MM, BMM, or BMMY medium to an  $\text{OD}_{600} = 1.0$ .
3. Grow the cell suspension cells in 2 to 4 l of culture medium at 28 to 30°C with shaking at 250 rev/min.
4. Add 100% methanol to a final concentration of 0.5% every 24 h until the optimal time of induction is reached.
5. Centrifuge at 3000  $g$  for 5 min at room temperature. Transfer the supernatant to a fresh tube for secreted expression and store the supernatant and cell pellet at  $-80^\circ\text{C}$  until use. Proceed to protein extraction and purification.

### 18.3.5.3 Extraction of Total Proteins for Purification

Procedures used here are virtually the same as those described for extraction of proteins from bacteria except for secretory proteins in the yeast culture medium as follows:

1. Precipitate the secreted proteins in the harvested supernatant with 60 to 80% (w/v)  $(\text{NH}_4)_2\text{SO}_4$ . Dissolve well and allow precipitation to take place at 4°C for 30 min.
2. Centrifuge at 15,000 rev/min for 20 min at 4°C and aspirate the supernatant.
3. Dissolve the protein pellet in 3 to 5 ml of protein buffer and transfer the sample into a dialysis bag with a molecular weight cutoff less than the molecular weight of the fusion proteins.
4. Seal the bag at both ends using appropriate clips or by making knots.
5. Place the sample bag in a beaker containing 1 l of dialysis buffer.
6. Perform dialysis in a cold room with stirring for 1 to 2 days. Change the dialysis buffer every 12 h.
7. Concentrate the protein samples using a plastic disposable microconcentrator from Amicon and centrifuge at 1000 rev/min at 4°C for an appropriate period of time. An alternative and effective way is to partially freeze-dry the samples or partially lyophilize in a Speed Vac System under cold conditions until a minimum volume is reached.
8. Take 20 to 100  $\mu\text{l}$  of the sample to measure the concentration (see Chapter 11). Store the protein sample at -20°C until use.
9. Take 2 to 3  $\mu\text{g}$  protein to analyze the purity by SDS-PAGE and/or western blotting.

### Reagents needed

- *Protein buffer*  
20 mM Tris-HCl, pH 7.5  
0.5 M NaCl
- *Dialysis buffer*  
20 mM Tris-HCl, pH 7.5  
10 mM NaCl

### 18.3.6 CARRY OUT FUSION PROTEIN PURIFICATION AND CLEAVAGE

Detailed protocols are described for purification and cleavage of proteins from bacteria in Section 18.2.

### REFERENCES

1. Studier, F. W., and B. A. Moffatt. 1986. Use of bacteriophage T7 RNA polymerase to direct selective high-level expression of cloned genes. *Journal of Molecular Biology* 189: 113-130.

2. Tabor, S., and C. C. Richardson. 1987. DNA sequence analysis with a modified bacteriophage T7 DNA polymerase. *Proceedings of the National Academy of Sciences of the United States of America* 84: 4767–4771.
3. Rose, M., and D. Botstein. 1993. Yeast promoters and *lac Z* fusions designed to study expression of cloned genes in yeast. *Methods in Enzymology* 101: 181–192.
4. Schein, C. H. 1989. Production of soluble recombinant proteins in bacteria. *BioTechnology* 7: 1141–1149.
5. Smith, D. B., and K. S. Johnson. 1988. Single-step purification of polypeptides expressed in *Escherichia coli* as fusions with glutathione S-transferase. *Gene* 67: 31–40.
6. Wu, W. 1995. Extraction and purification of proteins/enzymes. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke, 41–64. Boca Raton, FL: CRC Press.
7. Wu, W. 1995. Electrophoresis, blotting and hybridization. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke, 87–122. Boca Raton, FL: CRC Press.
8. Wearne, S. J. 1990. Factor Xa cleavage of fusion proteins: elimination of nonspecific cleavage by reversible acylation. *FEBS Letters* 263: 23–26.
9. Treco, D. A. 1995. Growth and manipulate of yeast. In *Current Protocols in Molecular Biology*, ed. F. M. Susubel, R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl, 13.2.1–13.2.11. New York, NY: John Wiley & Sons.
10. Treco, D. A. 1995. Manipulation of yeast genes. In *Current Protocols in Molecular Biology*, ed. F. M. Susubel, R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl, 13.7.1–13.7.6. New York, NY: John Wiley & Sons.
11. Reynolds, A. 1995. Yeast vectors and assays for expression of cloned genes. In *Current Protocols in Molecular Biology*, ed. F. M. Susubel, R. Brent, R. E. Kingston, D. D. Moore, J. G. Seidman, J. A. Smith, and K. Struhl, 13.6.1–13.6.4. New York, NY: John Wiley & Sons.




---

# 19 Quantitative Analysis of Functional Genome by Real-Time RT-PCR

## 19.1 INTRODUCTION


Genomic analysis plays an important role in quantification of gene expression or mRNA level.<sup>1-10</sup> Traditionally, methods used for quantitative analysis of gene expression at the mRNA level include northern blot, RNA protection assays, and non-real-time reverse transcription-polymerase chain reaction (RT-PCR).<sup>1-3</sup> The drawback, however, is that these traditional procedures are time consuming and costly, and experience significant variation. For instance, non-real-time RT-PCR involves pre-establishment of linear response curves before analyzing and comparing a specific mRNA level among RNA samples or different treatment groups.<sup>2-5</sup> First, it is necessary to set up multiple experiments to establish an optimal PCR cycles using the same amount of RNA as template (e.g., 1  $\mu\text{g}$  RNA/reaction) but different PCR cycles (e.g., 5, 10, 15, 20, 25) followed by 1% to 1.5% agarose gel visualization of the PCR products. The purpose is to find a PCR cycle range in which the signal intensity of PCR products/bands is in a linear range. Second, the amount of RNA (e.g., 0.5, 1.0, 1.5  $\mu\text{g}$  RNA/reaction) should be optimized in a linear range of PCR cycle number (e.g., 20 cycles). Again, an optimal amount of RNA should be identified (e.g., 0.5  $\mu\text{g}$ /reaction with 20 cycles), which will reveal the signal intensity of PCR bands/products within a linear range. Additionally, it may be necessary to optimize other conditions such as buffers/solutions, concentration of  $\text{MgCl}_2$ , and/or temperature. Obviously, these are very time consuming and labor intensive. Why are these optimization steps necessary? Many researchers do not prefer to optimize PCR conditions. Instead, they randomly select an amount of RNA (e.g., 2  $\mu\text{g}$ /reaction) and PCR cycles (e.g., 35), run RT-PCR, and compare signal intensity among RNA samples. This may seem simple and rapid; in fact, some manuscripts for publication included these types of data. Commonly, a severe critique or rejection will ensue. Why? One mistake might be not knowing that some signal intensity of PCR bands/products may reach plateau instead of being within a linear range. Hence, a comparison of specific mRNA level between samples/treatment groups is inaccurate. Nevertheless, traditional non-real-time RT-PCR remains a valuable tool for analysis of gene expression as long as it is performed in a scientific manner (Figure 19.1).

To overcome the shortcoming of non-real-time RT-PCR, the real-time RT-PCR technology has been developed.<sup>1,6</sup> The principles of the technology include: (1) A short, fluorescent probe hybridizes to the region between forward and reverse primers. The 5' end of the probe is labeled with a fluorescent dye as a reporter (e.g., FAM



**FIGURE 19.1** Schematic diagram of RT-PCR.

or VIC). The 3' end of the probe is a nonfluorescent quencher such as TAMRA. (2) When the probe is intact, due to an energy transfer, the signal of reporter is minimum but the signal of the quencher is strong. However, during primer extension and strand replacement, the 5' end of the probe is sequentially cleaved by the 5' nuclease activity of DNA *Taq* polymerase. As a result, the fluorescent signals increase but the quencher signals decrease. (3) Instruments such as ABI Prizm 7900 HT are equipped with a CCD camera that captures and records live the fluorescent fluctuations in all wells due to changes in concentration during PCR cycling. When RT-PCR is complete, the recorded data are utilized to generate a plot curve for each well, including a background phase, geometric phase, linear phase, and plateau phase. (4) To analyze and compare signal plot curves among different wells or samples (e.g., target gene and/or internal control gene), the  $C_t$  (cycle threshold) line can simply be placed or adjusted within the linear phase across all wells or samples for comparison. A  $\log_2 C_t$  value will be automatically calculated for each well by software such as SDS



**FIGURE 19.2** Procedure of fluorescence real-time PCR.

2.1. This chapter describes in detail how to analyze the mRNA levels or functional genomics of gene expression by real-time RT-PCR (Figure 19.2).

## 19.2 ISOLATION OF TOTAL RNA FROM TISSUES OR ORGANS OF INTEREST

1. Label one test tube (5 to 10 ml in size) for each sample and add 1 ml of Trizol reagents per 0.1 g tissue to each tube.  
*Warning: Trizol or phenol is very toxic and should be handled carefully. For protection, one should wear gloves, laboratory coat, and safety glasses. Gloves should be changed periodically during RNA isolation to minimize RNase activities. Whenever possible, Trizol reagents or phenol should be handled in a fume hood with a glass door placed between one's face and the inside of the hood.*
2. Quickly cut a tiny piece from each tissue (e.g., 100 mg) on a clean plastic Petri dish or an equivalent using a pair of scissor and forceps. Immediately place the cut piece into an appropriate tube labeled at step 1.  
*Tips: In case of many samples, cut and process less than 10 samples per round as the tissue samples should be homogenized as soon as possible to minimize RNase activities. Another round of RNA isolation can be started during the precipitation of the prior RNA samples at  $-20^{\circ}\text{C}$  for 1 to 2 h.*
3. Homogenize each sample to a fine homogenate. Quickly rinse the polytron probe in dd.H<sub>2</sub>O a couple of times before homogenizing the next sample.  
*Tips: The tube can be held with one hand and the speed of the polytron can be controlled with the other hand. Contract the probe with the tissue close to the bottom of the tube and start homogenizing for approximately 10 s. Turn on the polytron again and continue to homogenize for about three bursts, 5 to 10 s/burst by homogenizing up and down the homogenate. Note: Never let the polytron probe come in contact with the bottom of the tube to avoid breaking the tube.*
4. Slightly shake the tubes and place them on a bench and allow lysis of cells to occur for 5 min at room temperature (RT). At this point, label clean the 1.5-ml microcentrifuge tubes corresponding to the homogenate tubes.
5. Add 0.2 ml of chloroform to each homogenate, tightly cap the tubes, and vigorously shake each tube for approximately 30 s to optimize the lysis of cells and shear genomic DNA. Place the tubes on a bench for 2 min.
6. Transfer the lysate to appropriate microcentrifuge tubes.
7. Centrifuge for 10 min at  $4^{\circ}\text{C}$ . Label a set of clean microcentrifuge tubes.
8. Carefully transfer the top aqueous phase to fresh tubes.  
*Tips: This is a critical step in terms of RNA purity. Transfer the liquid a little at a time (e.g., 100 to 150  $\mu\text{l}$ /transfer) starting from the top portion to close to the interphase. In general, 250 to 350  $\mu\text{l}$  of the liquid can be transferred. Whenever possible during the transfer, the interphase containing proteins, lipids, carbohydrates, genomic DNA, etc., should not be disturbed. Once the top transferring liquid lowers approximately 2 mm to*

- the interphase, stop. Do not to be greedy! Otherwise, the RNA will be contaminated, which will be evidenced by a low ratio of  $A_{260}/A_{280}$  (e.g.,  $<1.5$ ).*
9. Add cold isopropanol to each tube (0.8 volume of the transferred liquid) and allow RNA to be precipitated for 1 to 2 h at  $-20^{\circ}\text{C}$ . Longer precipitation will be acceptable.
  10. Centrifuge for 10 min at  $4^{\circ}\text{C}$ . Decant the liquid and RNA pellet should be visible at the bottom of the tube. Add 1 ml of 75% of ethanol to each tube to wash the residual salt.
  11. Centrifuge for 5 min at  $4^{\circ}\text{C}$ .
  12. Dry the RNA samples in a SpeedVac for about 20 min. Avoid overdrying the samples.
  13. Dissolve RNA in 100 to 200  $\mu\text{l}$  RNase-free water or TE buffer for 40 min at RT or 20 min at  $50^{\circ}\text{C}$ .
  14. Carry out determination of RNA concentration in a spectrophotometer according to the instructions.  
 Note: *An excellent RNA sample should have a ratio of  $A_{260}/A_{280}$  of  $>1.9$  to 2.0. In contrast, a ratio of  $A_{260}/A_{280}$  of  $<1.5$  is a poor RNA preparation that contains proteins.*
  15. Run 5  $\mu\text{g}$  RNA of each sample in 1% agarose denaturing gel with ethidium bromide and carry out electrophoresis until the first blue dye reaches approximately 2 cm from the end of the gel. Take a picture of the gel.  
 Tips: *A good RNA preparation should display a sharp band of 28S rRNA, a sharp band of 18S rRNA, and a smear in each lane. The signal intensity of 28S rRNA/18S rRNA bands should be approximately 3:1. In case of RNA degradation, no visible or very weak rRNA bands or only 18S rRNA band is visible.*
  16. Store RNA samples at  $-80^{\circ}\text{C}$  until use.

### 19.3 ISOLATION OF TOTAL RNA FROM CULTURED CELLS

1. Aspirate or decant culture medium from the culture dishes or plates and quickly view cells under a microscope to estimate cell confluence and density. There is no need to scrape the cells out of Petri dishes or plates. Instead, directly add an appropriate volume of RNA isolation buffer such as Trizol reagents to the dish or plate, approximately 1 ml per  $10^{5-6}$  cells.  
 Warning: *Trizol or phenol is very toxic and should be handled carefully. For protection, one should wear gloves, laboratory coat, and safety glasses. Gloves should be changed periodically during RNA isolation to minimize RNase activities. Whenever possible, Trizol reagents or phenol should be handled in a fume hood with a glass door placed between one's face and the inside of the hood.*
2. Quickly overlay the dish or wells of plate with extraction buffer and pat the dish or plate with a hand to loosen cells. This takes a couple of minutes. Periodically monitor cell lysis under a microscope until cells disappear.  
 Tips: *To expedite cell lysis, use 1- to 5-ml pipette to flush the bottom of the dish or plate until cells disappear, indicating that a good lysis occurred.*



3. Once cell lysis is completed, transfer the lysate to 1.5-ml microcentrifuge tubes and place the tubes on a bench for 5 min at RT to maximize further lysis.
4. Add 0.2 ml of chloroform to every 1 ml of lysate, tightly cap the tubes, and vigorously shake each tube for approximately 30 s to optimize the lysis of cells and shear genomic DNA. Place the tubes on a bench for 2 min.
5. Centrifuge for 10 min at 4°C. Label a set of clean microcentrifuge tubes.
6. Carefully transfer the top aqueous phase to fresh tubes.

*Tips: This is a critical step in terms of RNA purity. Transfer the liquid a little at a time (e.g., 100 to 150  $\mu$ l/transfer) starting from the top portion to close to the interphase. In general, 250 to 350  $\mu$ l of the liquid can be transferred. Whenever possible during the transfer, the interphase containing proteins, lipids, carbohydrates, genomic DNA, etc., should not be disturbed. Once the top transferring liquid lowers approximately 2 mm to the interphase, stop. Do not be greedy! Otherwise, the RNA will be contaminated, which will be evidenced by a low ratio of  $A_{260}/A_{280}$  (e.g.,  $<1.5$ ).*

7. Add cold isopropanol to each tube (0.8 volume of the transferred liquid) and allow RNA to be precipitated for 1 to 2 h at  $-20^{\circ}\text{C}$ . Longer precipitation is acceptable.
8. Centrifuge for 10 min at 4°C. Decant the liquid; RNA pellet should be visible at the bottom of the tube. Add 1 ml of 75% of ethanol to each tube to wash residual salt.
9. Centrifuge for 5 min at 4°C.
10. Dry the RNA samples in a SpeedVac for about 20 min. Avoid overdrying the samples.
11. Dissolve RNA in 100 to 200  $\mu$ l RNase-free water or TE buffer for 40 min at RT or 20 min at 50°C.
12. Determine the concentrations of RNA samples using a spectrophotometer according to the instructions.  
*Note: An excellent RNA sample should have a ratio of  $A_{260}/A_{280}$  of  $>1.9$  to 2.0. In contrast, a ratio of  $A_{260}/A_{280}$  of  $<1.5$  is a poor RNA preparation that contains proteins.*
13. Run 5  $\mu$ g RNA of each sample in 1% agarose denaturing gel with ethidium bromide and carry out electrophoresis until the first blue dye reaches approximately 2 cm from the end of the gel. Take a picture of the gel.  
*Tips: A good RNA preparation should display a sharp band of 28S rRNA, a sharp band of 18S rRNA, and a smear in each lane. The signal intensity of 28S rRNA/18S rRNA bands should be approximately 3:1. In case of RNA degradation, no visible or very weak rRNA bands or only 18S rRNA band is visible.*
14. Store RNA samples at  $-80^{\circ}\text{C}$  until use.

## 19.4 PREPARATION OF RNA POOL

For drug, compound, chemical, or pharmacogenomic *in vitro* or *in vivo* studies, there will be many groups of samples, control vs. different treatment (e.g., 10 groups). Each group consists of many animals (e.g.,  $N = 5/\text{group}$ ). In this case, 50 RNA samples are isolated from 50 animals. Because it requires considerable time to analyze

the mRNA level of interest in 50 individual animals, quantitative real-time RT-PCR using the RNA pool/group can be performed or the same amount of RNA (e.g., 10  $\mu\text{g}$ ) from each of five animals can be combined in one vial. The final volume of each group should be the same (e.g., 100  $\mu\text{l}$ ). Hence, the final RNA concentration will be the same among animals or groups, 0.5  $\mu\text{g}/\mu\text{l}$ . This serves to minimize potential variations if individual animal RNA samples are pipetted instead of the RNA group pool. We recommend preparing a final concentration of 50  $\text{ng}/\mu\text{l}$  RNA pool per group to be utilized for real-time RT-PCR. Store RNA samples at  $-80^\circ\text{C}$  until use.

## 19.5 DESIGNING PRIMERS AND PROBES

Design of primers and probes is a critical step in a successful real-time RT-PCR. Poor quality of primers or probes could result in failure. We offer the following tips to help users achieve successful results. A couple of software programs are available for designing primers and probes. Because we utilized Prizm 7900 HT system (Applied Biosystems, CA) for real-time RT-PCR, Primer Express was primarily used for this purpose. Additionally, we used other software including Lasergene (DNA Star) and GCG program.

1. Obtain gene sequences of interest from GenBank via NCBI and save a sequence in a file folder with “.seq” at the end of sequence name (e.g., GFPcDNA.seq). Given specific accession number or EST ID number, and software such as Primer Express and Lasergene, can directly link to and import sequences from databases.

2. Design and select a forward primer, a reverse primer, and a probe between forward and reverse primers under default conditions (e.g., Primer Express) or specified parameters.

*Guidelines: (1) The 3' end of forward or reverse primer should be approximately 10 to 25 bases away from the 5' or 3' end of the probe between the primers. (2) The length of primers is 15 to 22 nucleotides. (3) The length of probe is 17 to 25 bases. (4) The forward and reverse primers should not form heterodimers. No more than five bases are allowed to form intra-loops of primers or probe. (5) GC content of primers should be <60% but the probe may have up to 80% GC content. (6) The  $T_m$  value for primers should be 58 to 60°C. However, the  $T_m$  for the probe should be 68 to 70°C. (7) Avoid Gs at the 5'-end of probe or primers.*

3. Carefully check the sequences before sending them out for synthesis. Primers and probes do not need HPLC purification. Standard desalt works fine in our laboratories.
4. Accurately calculate the concentrations of primers or probes and briefly spin down the primer or probe powder before adding dd.H<sub>2</sub>O to the vials. It is recommended that the concentrations for a primer or probe be 100 and 200  $\mu\text{M}$ , respectively.

*Notes: Making the correct concentration may be problematic for many people due to confusion. It is important to bear in mind that M, mM,  $\mu\text{M}$ , or nM refers to the concentration of 1 l. 1 M = 1000 mM, 1 mM = 1000  $\mu\text{M}$ ,*

$1 \mu\text{M} = 1000 \text{ nM}$ ,  $1 \text{ nM} = 1000 \text{ pM}$ ,  $1 \text{ pM} = 1000 \text{ fM}$ . It is improper to use  $1 \mu\text{M}$  xx per ml or  $\mu\text{l}$  because  $1 \mu\text{M}$  xx refers to the concentration of 1 l. Therefore, whether 10 ml, 1 ml, or  $1 \mu\text{l}$  is used, the concentration is  $1 \mu\text{M}$  in this case. How to dissolve a primer or oligonucleotide powder in a right volume of water to make the right concentration? For example, if one received an oligo primer powder with a specification of 50 nmol and wanted to resuspend the primer to a concentration of  $200 \mu\text{M}$ , how much water is needed (final volume)? Here is the formula:

$\text{Volume} \times \text{Concentration} = \text{Content}$  (e.g., mol, mmol,  $\mu\text{mol}$ , nmol, pmol, fmol)

For the present example,  $\text{Volume (l)} \times 200 \mu\text{M} = 50/1000 \mu\text{mol}$ . Thus,  $\text{Volume} = 0.05/200 = 0.00025 \text{ (l)} = 250 \mu\text{l}$ . One can add  $250 \mu\text{l}$  of dd.H<sub>2</sub>O to the vial containing 50 nmol of primer powder, generating a concentration of  $200 \mu\text{M}$  primer stock solution.

5. Make a working solution of primers or probe by diluting the stock primer or probe solution from  $200$  to  $10 \mu\text{M}$  in RNase- and DNase-free water. Forward and reverse primers can be combined into one vial,  $10 \mu\text{M}$  each. Store the primer or probe solution at  $-20^\circ\text{C}$  or  $4^\circ\text{C}$  until use.

## 19.6 REAL-TIME RT-PCR

### 19.6.1 ASSEMBLY OF REACTIONS

1. Thaw primers, probes, and reagents at RT and RNA samples on ice.
2. Design a real-time RT-PCR assay using a 96-well template (Figure 19.3) as a guide. We recommend a triplicate (3 wells) for each RNA sample (individual or RNA group pool).
3. Carefully calculate the amount or volume of primers, probes, RNA, reagents, and dd.H<sub>2</sub>O needed. Assemble a reaction mixture for each gene of interest in a microcentrifuge tube. The following cocktail is designed for 10 reactions or wells, total of  $50 \mu\text{l}/\text{well}$ .

Name of Real-Time RT-PCR: \_\_\_\_\_ Date: \_\_\_\_\_.

	1	2	3	4	5	6	7	8	9	10	11	12
A	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
B	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
C	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
D	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
E	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
F	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
G	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
H	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>

Notes:

FIGURE 19.3 96-well template used for real-time RT-PCR.

5× One-step RT-PCR master mixture	100 µl
100× RNase inhibitor (optional)	5.0 µl
Target gene primers (forward and reverse primers, 10 µM each)	25 µl
Internal control primers (e.g., GAPDH forward and reverse primers, 10 µM each)	25 µl
Target gene probe (fluorescent FAM-labeled, 200 µM)	2.5 µl
Internal control probe (fluorescent VIC-labeled, 200 µM)	2.5 µl
RNA (50 ng/µl)	40 µl
dd.H <sub>2</sub> O	300 µl
Total volume	500 µl

Notes: (1) RT-PCR master mixture contains reverse transcriptase, DNA Taq polymerase, dNTPs, MgCl<sub>2</sub>, buffer, etc. RT-PCR master mixture is commercially available (AB Applied Biosystems, CA; AHW Biomedical Systems, MI). (2) Assembly of this cocktail or mixture should be based on the conditions of preoptimization. Initially, optimization experiments should be set up. Based on our experience, we recommend trying a couple of conditions, including final concentration of primers (e.g., 125, 250, and 500 nM), probes (2.5 and 5 µM), and RNA (50, 100, and 150 ng/well). In this case, it may be necessary to add different components individually to appropriate wells. (3) Once the conditions are optimized based on real-time RT-PCR results, it is strongly recommended to assemble the reaction cocktail before transferring an appropriate volume to a well (e.g., 50 µl/well), minimizing variation by potential pipetting error. In general, the fewer the pipetting steps, the more accurate or less variation there will be. It is imperative to minimize variation as much as possible to quantify and compare gene expression levels among samples or treatment. (4) Whenever possible, target gene and internal control should be set up and processed in the same wells. We recommend GAPDH as an internal control. Many researchers use 18S rRNA as internal control. The drawback, however, is that 18S rRNA is overabundant. As a result, RT-PCR results may not reveal any difference in terms of 18S rRNA level between 1- and 2-fold total RNA as template.

4. Accurately aliquot the same volume of the reaction cocktail to each well according to the predesigned 96-well plate template.
5. Firmly cover the plate with a sheet of sticky film to prevent evaporation during RT-PCR.

### 19.6.2 PROGRAMMING AND PERFORMANCE OF REAL-TIME RT-PCR

1. Set up a real-time RT-PCR protocol and start a run according to the instructions. (1) Turn on the computer that controls the ABI Prizm 7900 HT System. (2) Open SDS 2.1 program. (3) Turn on ABI Prizm 7900 HT. The

instrument indicates red light → yellow light → green light. The instrument needs to be turned on for at least 15 min before RT-PCR. (4) Click File of SDS 2.1 program → click New → select quantitation → name → OK. (5) Click Detector Manager → Create a fluorescent color for each gene of interest. For examples, Name: ABC1 mRNA (target gene); Color/Detector: FAM green, Description: unknown. Name: p53 mRNA (target gene); Color/Detector: FAM yellow, Description: unknown. Name: GAPDH mRNA (internal control gene); Color/Detector: VIC pink, Description: unknown. Once all genes are set up, click Save, Copy file, and then Done. (6) Click Instrument set up → Highlight specific wells according to the 96-well plate template designed in the first place → Select specific target and internal control genes and colors set up by Detector Manager → Repeat the process for other wells.

Note: To obtain convenient export results to a terminal computer, the SDS 2.1 software recommends that wells in the plate be highlighted from row to row instead of from column to column. Therefore, when designing a 96-well plate template at the beginning of the experiment, triplicates should be set up for each gene in the same row instead of the same column.

(7) Click Profile → 48°C, 30 min (for RT step) → 95°C, 10 min → 40 cycles of [95°C, 15 s (denaturation) → 60°C, 1 min (annealing/extension)] → Volume: 50  $\mu$ l. (8) Click Data Collection: 95°C and 60°C points. (9) Click Open → place the plate in place → Click Close

2. Click Run. This will display the Thermal profile and the remaining time.

### 19.6.3 ANALYSIS OF DATA

1. Analyze real-time RT-PCR data after “The run is successfully completed” appears on the screen. Click Open → remove the plate → click Close to close the door. Click Analyze → Results → Amplification Plot. At this point, plate template and amplification plot are displayed on the screen.
2. Highlight specific wells for individual gene in a row-to-row fashion according to the initial design of the 96-well template. The amplification plot






FIGURE 19.4 Diagram of correct  $C_t$  line across real-time RT-PCR curves.



**FIGURE 19.5** Diagram of incorrect adjustment of  $C_t$  line across real-time RT-PCR curves.

window will automatically display RT-PCR curves for a particular gene. Adjust or place the  $C_t$  (cycle threshold) line in the linear phase across all the curves; a  $C_t$  value will be automatically displayed for each well on the same screen. Repeat the procedure until all the wells for all genes of interest are analyzed.

Notes: (1) All the wells designed for a specific gene (target gene or internal control gene) should be simultaneously highlighted from row to row instead of from column to column. (2) a  $C_t$  line should be placed in the linear phase (not in the geometric phase or plateau phase) and should be across all the curves for different RNA groups. Figures 19.4, 19.5, and 19.6 indicate the right or wrong way of placing the  $C_t$  line. (3) A  $C_t$  value for a particular well should not be  $>40$  because the maximum PCR cycle number was set at 40.  $C_t$  values  $>40$  seen in some wells indicate that the  $C_t$  line needs to be readjusted or the conditions of RT-PCR for those particular gene(s) should be optimized. For statistical analysis, a triplicate should be set up for each RNA sample (e.g., treated vs. control). If all goes well,  $C_t$  values for three




**FIGURE 19.6** Diagram of incorrect amplification curve for RNA sample C. RNA samples A, B, and D are fine.

**TABLE 19.1**  
**Analysis and Comparison of mRNA Levels between Control and Treated Groups**

	ABC1 Well 1 C <sub>1</sub> Value	ABC1 Well 2 C <sub>1</sub> Value	ABC1 Well 3 C <sub>1</sub> Value	GAPDH Well 1 C <sub>1</sub> Value	GAPDH Well 2 C <sub>1</sub> Value	GAPDH Well 3 C <sub>1</sub> Value	ABC1 C <sub>1</sub> Mean Value	GAPDH C <sub>1</sub> Mean Value	$\Delta C_i$ : ABC1- GAPDH (C <sub>1</sub> Mean Value)	$\Delta \Delta C_i$ : Treated Group ( $\Delta C_i$ - $\Delta C_i$ )	mRNA Fold- Change vs. Control = $2^{\Delta \Delta C_i}$	Actual mRNA Fold-Change vs. Control Group Using an Excel Formula: *IF(L2 < 1, - 1/L2, L2), Then Enter	mRNA Level % change (Treated vs. Control Group)
Control RNA	22.52	22.01	22.65	19.55	19.67	19.2	22.39	19.49	2.90	0	1	1	100%
Treated RNA 1	20.9	20.4	20.1	19.55	19.67	19.2	20.47	19.49	0.98	-1.92	3.7842	3.7842	378%
Treated RNA 2	21.6	21.2	21.7	19.55	19.67	19.2	21.5	19.49	2.01	-0.89	1.8531	1.8531	185%
Treated RNA 3	25.2	25.8	25.6	19.55	19.67	19.2	25.53	19.49	6.04	3.14	0.1134	-8.8152	-882%

*Note:* (1) C<sub>1</sub> values are derived from log<sub>2</sub>. Therefore,  $\Delta C_i$  data log<sub>2</sub> values. To calculate a log<sub>2</sub> value, one can use a formula: =log(<sub>base</sub>, number). For example, Log<sub>2</sub> value for 8 can be calculated as =log(2, 8) = 3. (2) Conversion of log<sub>2</sub> value to number, the formula is =2 <sup>$\Delta \Delta C_i$</sup>  for positive  $\Delta C_i$  or log<sub>2</sub> value. For example, 2<sup>3</sup> = 8. For negative  $\Delta C_i$  or log<sub>2</sub> value, the formula is =2<sup>- $\Delta \Delta C_i$</sup>  (e.g., 2<sup>-3</sup> = -8. In case 2<sup>- $\Delta \Delta C_i$</sup>  or 2 <sup>$\Delta \Delta C_i$</sup>  values are <1, a conversion is necessary to generate actual fold using an Excel formula: = IF(column row <1, -1/column row, column row). For example, IF(L2<1, -1/L2, L2), then press Enter. (3) Based on the converted numbers, one can calculate mRNA fold-change or percentage changes as compared to the control group. Please bear in mind that fold- or % changes are relative versus the control group. (4) For reproducibility and statistically significant data, we strongly recommend that real-time RT-PCR be repeated at least three times. In this way, one can calculate average fold- or percentage-change with standard deviation in the figures. Only consistent results are meaningful!




**FIGURE 19.7** Fold-change of mRNA level in treated or control groups.

*wells should be very similar and the amplified well positions displayed in the amplification plot window are almost horizontal. Any significant differences among triplicate wells indicate that a large variation occurred during assembly of reactions and aliquots among wells.*

3. Save the results and export the result to a terminal computer (if necessary) for further analysis.
4. Generate a table and/or figure of real-time RT PCR results to compare the expression levels of genes of interest using Microsoft Excel or equivalent software (Table 19.1 and Figures 19.7 and 19.8).

#### 19.6.4 VALIDATION

Validate real-time RT-PCR data by traditional northern blotting or RNA protection assays (optional).



**FIGURE 19.8** mRNA level % change as compared to control group.



## REFERENCES

1. Innis, M. A., K. B. Myambo, D. H. Gelfand, and M. A. Brow. 1988. DNA sequencing with *Thermus aquaticus* DNA polymerase and direct sequencing of polymerase chain reaction amplified DNA. *Proceedings of the National Academy of Sciences of the United States of America* 85: 9436.
2. Holland, P. M., R. D. Abramson, R. Watson, and D. H. Gelfand. 1991. Detection of specific polymerase chain reaction product by utilizing the 5'→3' exonuclease activity of *Thermus aquaticus* DNA polymerase. *Proceedings of the National Academy of Sciences of the United States of America* 88: 7276.
3. Srarnaki, O., M. Tanner, and T. Visakorpi. 2002. Amplification and overexpression of elongin C gene discovered in prostate cancer by cDNA microarrays. *Laboratory Investigations* 82(5): 629.
4. Witney, A., J. D. Haynes, J. K. Moch, D. J. Carucci, and J. H. Adams. 2002. Transcripts of developmentally regulated *Plasmodium falciparum* genes quantified by real-time RT-PCR. *Nucleic Acids Research* 15: 2224.
5. Lin, C. Y., K. H. Chao, M. Y. Wu, Y. S. Yang, and H. N. Ho. 2002. Defective production of interleukin-11 by decidua and chorionic villi in human anembryonic pregnancy. *Journal of Clinical Endocrinology & Metabolism* 87: 2320.
6. Leclerc, G. J., G. M. Leclerc, and J. C. Barredo. 2002. Real-time RT-PCR analysis of mRNA decay: half-life of beta-actin mRNA in human leukemia CCRF-CEM and Nalm-6 cell lines. *Cancer Cell International* 2(1): 1.
7. Dotsch, J., R. Repp, W. Rascher, and H. Christiansen. 2001. Diagnostic and scientific applications of TaqMan real-time PCR in neuroblastomas. *Expert Review of Molecular Diagnostics* 1: 233.
8. Gleissner, B., and E. Thiel. 2001. Detection of immunoglobulin heavy chain gene rearrangements in hematologic malignancies. *Expert Review of Molecular Diagnostics* 1: 191.
9. Pfaffl, M. W., T. M. Georgieva, I. P. Georgiev, E. Ontasouka, M. Hageleit, and J. W. Blum. 2002. Real-time RT-PCR quantification of insulin-like growth factor (IGF)-1, IGF-1 receptor, IGF-2, IGF-2 receptor, insulin receptor, growth hormone receptor, IGF-binding proteins 1, 2 and 3 in the bovine species. *Domest Animal Endocrinology* 22: 91.
10. Mansson, E., E. Liliemark, S. Soderhall, G. Gustafsson, S. Eriksson, and F. Albertioni. 2002. Real-time quantitative PCR assays for deoxycytidine kinase, deoxyguanosine kinase and 5'-nucleotidase mRNA measurement in cell lines and in patients with leukemia. *Leukemia* 16: 386.




---

# 20 High-Throughput Analysis of Gene Expression by Cutting-Edge Technology—DNA Microarrays (Gene Chips)

## 20.1 INTRODUCTION

We are living in an era of biotechnology and bioinformation revolution. The flood of bioinformation on human genome is particularly overwhelming. With the genome sequences of several organisms now in public databases, we have realized that the next logical step is to reveal and understand the biological systems and mechanisms. Achieving these goals mandates high-throughput methodologies. Certainly, microarray technology plays a major role in genomic and proteomic profiling. DNA microarray or gene chip technology makes it possible to simultaneously analyze thousands of genes combined with a dozen of parameters within a single experiment, and to significantly increase the speed and efficiency of scientific research and/or drug discovery.<sup>1–10</sup> The major principle of this technology is that hundreds and thousands of genes (i.e., oligonucleotides, EST, cDNA, etc.) are immobilized or arrayed onto small slides or chips via an appropriate technology; the chip is then hybridized with complimentary probes usually generated from mRNA samples. After washing, the slide or chip is scanned into a computer and analyzed using the appropriate software.<sup>1–5,7–12</sup> The procedure is similar to traditional Southern blot or northern blot hybridization except for the high throughput. The major merit of DNA microarray technology is that a single chip in a single experiment can reveal thousands of gene expression profiles, including up-regulated, down-regulated, or unchanged genes, compared to a control group. Hence, this powerful technology is widely utilized in new gene discovery, DNA–DNA interaction, DNA–RNA interaction, and DNA–protein interaction.<sup>2–6,12–15</sup>

This chapter describes the technology and, via step-by-step protocols, helps readers to use DNA microarrays or chips for research and drug discovery ([Figure 20.1](#)).



**FIGURE 20.1** A general procedure of gene expression profiling via DNA microarray.

## 20.2 ISOLATION OF TOTAL RNA FROM CELLS OR TISSUES

1. Add an appropriate volume of RNA isolation buffer such as Trizol reagents to the tube containing cells or tissue, at approximately 1 ml per  $10^{5-6}$  cells or 1 mg tissue.

*Warning: Trizol or phenol is very toxic and should be handled carefully. For protection, gloves, laboratory coat, and safety glasses should be worn while handling this material. Gloves should be changed periodically during RNA isolation to minimize RNase activities. Whenever possible, Trizol reagents or phenol should be handled in a fume hood with a glass door placed between one's face and the inside of the hood.*

2. Suspend the cells or homogenize the tissue to a fine homogenate, and allow the cells to lyse for 5 to 10 min at room temperature.
3. Add 0.2 ml of chloroform to each 1 ml of lysate, tightly cap the tubes, and vigorously shake each tube for approximately 30 s to optimize the lysis of cells and shear genomic DNA. Place the tubes on a bench for 2 min.
4. Centrifuge for 10 min at 4°C. Label a set of clean microcentrifuge tubes.
5. Carefully transfer the top aqueous phase to fresh tubes.

*Tips: This is a critical step in terms of RNA purity. One should transfer the liquid a little at a time (e.g., 100 to 150  $\mu$ l/transfer) starting from the top portion to close to the interphase. In general, 250 to 350  $\mu$ l of the liquid can be transferred. Whenever possible during the transfer, the interphase containing proteins, lipids, carbohydrates, genomic DNA, etc., should not be disturbed. Once the top transferring liquid lowers approximately 2 mm to the interphase, stop. Do not to be greedy! Otherwise, the RNA will be contaminated, which will be evidenced by a low ratio of  $A_{260}/A_{280}$  (e.g.,  $<1.5$ ).*

6. Add cold isopropanol to each tube (0.8 volume of the transferred liquid) and allow RNA to be precipitated for 1 to 2 h at  $-20^{\circ}\text{C}$ . Longer precipitation will be acceptable.
7. Centrifuge for 10 min at  $4^{\circ}\text{C}$ . Decant the liquid and RNA pellet should be visible at the bottom of the tube. Add 1 ml of 75% of ethanol to each tube to wash residual salt.
8. Centrifuge for 5 min at  $4^{\circ}\text{C}$ .
9. Dry the RNA samples in a SpeedVac for about 20 min. Avoid overdrying the samples.
10. Dissolve RNA in 100 to 200  $\mu\text{l}$  RNase-free water or TE buffer for 40 min at RT or 20 min at  $50^{\circ}\text{C}$ .
11. Determine the concentrations of RNA samples using a spectrophotometer according to the instructions.  
*Note: An excellent RNA sample should have a ratio of  $A_{260}/A_{280}$  of  $>1.9$  to  $2.0$ . In contrast, a ratio of  $A_{260}/A_{280}$  of  $<1.5$  indicates a poor RNA preparation that contains proteins.*
12. Run 5  $\mu\text{g}$  RNA of each sample in 1% agarose denaturing gel with ethidium bromide and carry out electrophoresis until the first blue dye reaches approximately 2 cm from the end of the gel. Take a picture of the gel.  
*Tips: A good RNA preparation should display a sharp band of 28S rRNA, a sharp band of 18S rRNA, and a smear in each lane. The signal intensity of 28S rRNA/18S rRNA bands should be approximately 3:1. In case of RNA degradation, no visible or very weak rRNA bands or only 18S rRNA band is visible.*
13. Store RNA samples at  $-80^{\circ}\text{C}$  until use.

### 20.3 PREPARATION OF FLUORESCENT PROBES FROM mRNA

Once high quality of RNA is obtained, synthesis of cDNA probes can be performed using mRNAs as templates. A standard reaction is a total of 25  $\mu\text{l}$  using 0.2 to 2  $\mu\text{g}$  mRNA or 5 to 10  $\mu\text{g}$  total RNAs. For each additional 1  $\mu\text{g}$  mRNA, increase the reaction volume by 10  $\mu\text{l}$ .

1. Anneal 2  $\mu\text{g}$  of mRNAs as templates with 1  $\mu\text{g}$  of primer of oligo(dT) in a 1.5-ml sterile, RNase-free microcentrifuge tube. Add nuclease-free dd.H<sub>2</sub>O to total 19  $\mu\text{l}$ . Heat the tube at  $65^{\circ}\text{C}$  for 5 min to denature the secondary structures of mRNAs and allow it to slowly cool to room temperature to complete the annealing. Briefly spin down the mixture.
2. To the annealed primer/template, add the following in the order listed.
  - 8  $\mu\text{l}$  5 $\times$  first strand buffer
  - 4  $\mu\text{l}$  0.1 M DTT
  - 4  $\mu\text{l}$  10 $\times$  dNTP
  - 4  $\mu\text{l}$  Cy3 or Cy5 dUTP or biotin dUTP
  - 1  $\mu\text{l}$  RNase inhibitor
  - 2  $\mu\text{l}$  Superscript-RT (AMV reverse transcriptase)
  - Incubate at  $42^{\circ}\text{C}$  for 60 min
  - Heat at  $94^{\circ}\text{C}$  for 5 min

Function of components: *The 5× reaction buffer contains components for the synthesis of cDNAs. Ribonuclease inhibitor serves to inhibit RNase activity and protect the mRNA templates. Sodium pyrophosphate suppresses the formation of hairpins commonly generated in traditional cloning methods, thus avoiding the S1 digestion step that is difficult to carry out. AMV reverse transcriptase catalyzes the synthesis of the first strand cDNAs from mRNA templates according to the rule of complementary base pairing.*

3. To completely remove RNAs, add RNase A (DNase-free) to a final concentration of 20 µg/ml or 1 µl of RNase (Boehringer Mannheim, 500 µg/ml) per 10 µl of reaction mixture. Incubate at 37°C for 30 min, followed by inactivation of RNase A by heating at 94°C for 5 min.
4. (Optional) Extract the probes from the unlabeled reaction mixture with 1 volume of TE-saturated phenol/chloroform. Mix well and centrifuge at 11,000 *g* for 5 min at room temperature.
5. Carefully transfer the top, aqueous phase to a fresh tube. Do not take any white materials at the interphase between the two phases. To the supernatant, add 0.5 volume of 7.5 M ammonium acetate or 0.15 volume of 3 M sodium acetate (pH 5.2), mix well, and add 2.5 volumes of chilled (at -20°C) 100% ethanol. Gently mix and precipitate cDNAs at -20°C for 2 h.
6. Centrifuge in a microcentrifuge at 12,000 *g* for 5 min. Carefully remove the supernatant, then briefly rinse the pellet with 1 ml of cold 70% ethanol. Centrifuge for 4 min and carefully aspirate the ethanol.
7. Dry the cDNAs under vacuum for 15 min. Dissolve the probe pellet in 15 to 25 µl of TE buffer. Take 2 µl of the sample to measure the concentration of probes before the next reaction. Store the sample at -20°C until use.

### Materials needed

- 50 mM EDTA
- 7.5 M Ammonium acetate
- Ethanol (100% and 70%)
- Chloroform/isoamyl alcohol (24:1)
- 2 M NaCl
- 0.2 M EDTA
- 1 mg/ml carrier DNA (e.g., salmon sperm)
- Trichloroacetic acid (5% and 7%)
- *First strand 5× buffer*
  - 250 mM Tris-HCl, pH 8.3 (at 42°C)
  - 250 mM KCl
  - 2.5 mM spermidine
  - 50 mM MgCl<sub>2</sub>
  - 50 mM DTT
  - 5 mM each of dATP, dCTP, dGTP, and dTTP
- *TE buffer*
  - 10 mM Tris-HCl, pH 8.0
  - 1 mM EDTA

- *TE-saturated phenol/chloroform*

Thaw phenol crystals at 65°C and mix an equal part of phenol and TE buffer. Mix well and allow the phases to separate at room temperature for 30 min. Take 1 part of the lower, phenol phase to a clean beaker or bottle and mix with 1 part of chloroform/isoamyl alcohol (24:1). Mix well and allow phases to be separated, and store at 4°C until use.


## 20.4 GENERATION OF DNA MICROARRAYS OR CHIPS

DNA chips, which are commercially available (Affymatrix: rat array, mouse array, human array, etc.), can be very costly. However, it is possible to produce arrays by spotting appropriate DNA (cDNA, PCR products, oligos) onto precoated glass slides using an appropriate spotter (Figure 20.2). The spotted slides should be compatible with a commercial scanner. The authors provide the following conditions for arraying slides.

- Corning CMT-GAPS silane-coated slides
- Spotting buffer: 50% DMSO, 20 mM Tris-HCl, 50 mM KCl, pH 6.5
- 72°F (22°C) with 40% to 50% relative humidity
- UV cross-linking at 90 mJ, bake at 80°C for 2 h

## 20.5 PREHYBRIDIZATION OF GENE CHIPS OR ARRAYS

1. Mark the chip (array or slide) with a pencil.
2. Vapor moisturize the chip (array side facing down) over boiling water for 1 min.
3. Quickly place the chip in a UV cross-linker (i.e., Stratalinker, 250 mJ, setting 2500 silane slides) with array-side up.
4. Remoisturize the chip over steam as in step 2.
5. Rinse the chip/slide in 0.1% SDS for 20 s, and in ddH<sub>2</sub>O for 20 s.
6. Heat the chip/slide (i.e., boil in water bath) at 95°C for 3 min. (This is necessary for spotted dsDNA chips. However, it is optional for ssDNA chips.)



**FIGURE 20.2** A diagram of arraying DNA onto slides.

7. Add 60  $\mu\text{l}$  of prehybridization buffer onto the chip, and place a coverslip over the array.
8. Add 10  $\mu\text{l}$  dd  $\text{H}_2\text{O}$  to each corner of the chamber to maintain humidity.
9. Place the chip or slide in the hybridization chamber and incubate in a 50°C water bath for 1 h.

## 20.6 HYBRIDIZATION

1. Remove water from the array slide.
2. Add 60  $\mu\text{l}$  of hybridization solution over the array (40  $\mu\text{l}$  hybridization buffer, 1  $\mu\text{l}$  blocking solution, 19  $\mu\text{l}$  probes).
3. Place a new coverslip on the array and place the array in hybridization chamber.
4. Perform hybridization overnight in a 50°C water bath.

## 20.7 WASHING

1. Place the slide in 50 to 100 ml of wash solution containing 2 $\times$  SSC and 0.1% SDS, and carefully remove the coverslip from the array.
2. Shake the array for 10 min.
3. Replace 2 $\times$  SSC with 100 ml of 0.2 $\times$  SSC solution, then shake the array for 15 min.
4. Place the slide in a 50-ml tube and spin for 5 min at 1000 rev/min to dry the slide.
5. Keep the array in a dark place until scanning.

### Materials needed


- *1 $\times$  dNTP solution*
  - 25  $\mu\text{l}$  dGTP
  - 25  $\mu\text{l}$  dATP
  - 25  $\mu\text{l}$  dCTP
  - 10  $\mu\text{l}$  dTTP
  - 415  $\mu\text{l}$  DEPC- $\text{H}_2\text{O}$
  - 500  $\mu\text{l}$  Total
- *Prehybridization buffer*
  - 7.0 ml Formamide
  - 0.4 ml ss salmon sperm DNA
  - 1.0 ml 50 $\times$  Denhardt's solution
  - 4 ml 20 $\times$  SSPE
  - 1.0 ml 10% SDS
  - 6.6 ml dd $\text{H}_2\text{O}$
  - 20 ml Total
- *Hybridization buffer*
  - 0.7 ml Formamide (3%)
  - 50  $\mu\text{l}$  20% SDS (0.5%)




- 100  $\mu$ l 50 $\times$  Denhardt's solution (2.5 $\times$ )
  - 400  $\mu$ l 20 $\times$  SSPE (4 $\times$ )
  - 1.25 ml Total
  - *Blocking solution (20 $\times$  stock)*
    - 80  $\mu$ l polydA (1  $\mu$ g/ $\mu$ l)
    - 16  $\mu$ l tRNA (10  $\mu$ g/ $\mu$ l)
    - 400  $\mu$ l Human/mouse Cot1 DNA (1  $\mu$ g/ $\mu$ l)
    - 480  $\mu$ l Total
- Precipitate the combined reagents with ethanol  
Resuspend in 40  $\mu$ l ddH<sub>2</sub>O

## 20.8 SCANNING OF GENE CHIPS USING GENEPIX 4000a MICROARRAY SCANNER

1. Turn on the scanner and start GenePixPro 3.0 software.
2. Open scanner door and insert the chip into the scanner with the hybridized side down and the label facing toward you.
3. In the "Hardware Settings" window, set PMTs at 600 in both 635 nm (Cy 5) and 532 nm (Cy 3) channels.
4. Click "Preview scan" to determine location of scanning areas/spots and signal intensities.
5. Draw a "scan area" around the entire array and perform a quick visual inspection of hyb and make initial adjustment of PMTs.
6. For gene expression hybs, set the ratio over the entire scan area to be 1.0 by raising or lowering the red and green PMTs to obtain the color balance.
7. In the "hardware settings" window, change the "lines to average" to 2 before performing data scan. This will allow the scanner to scan each pixel twice and average the collected data counts, which can reduce background noise.
8. Click "Data Scan" to perform a high-resolution scanning. During the scanning, click the "histogram" tab located at the top of the screen to dynamically view the relative intensities of both channels as scanning takes place. The histogram settings should be: Image: Both, X-axis: Fullscale, Y-axis: Log Axis on Fullscale. The histogram displays the percentage of normalized counts at a given intensity or quanta. The histogram only shows the pixels that can be affected by artifacts and dirt. If there a lot of dirt and/or artifacts are present, try to zoom in on a clean portion of the array to determine accurate PMT settings.




**FIGURE 20.3** A diagram of scanned DNA microarray chip.



**FIGURE 20.4** High-throughput analyses of effects of new drugs on gene expression profile in mice.

9. Based on the histograms, adjust the PMTs so that the pixels can represent the entire intensity range. In some cases, saturated pixels (i.e., counts >70,000) will be thrown out and spots with pixel counts close to background will be given poor data.
10. Once the PMT levels are set to make the intensity ratio near 1.00, click “data scan” over the scan area and save the results.
11. Go to the “open/save” button and select “save images” to save the images at 635 nm or 532 nm (type=Multi-image tiff).
12. Assign spot identities and calculate results using GenePixPro software. The software can deconvolute the identities of PCR products from a 96-well text file into a 384-well format (save this information in the form of GAL file, GenepixArrayList). The 384-well files will then be changed to a grid (the GPS, GenePixSettingFile). The GPS will assign each spot on the chip its



**FIGURE 20.5** Fold-changes in gene expression in mice treated with new drugs.

identity based on printing parameters (the number of tips used to print, the spacing between spots, number of plates printed).

13. Go to the Help section, and press the Image tab and then “Array List Generator” to create the GAL.
14. After creation of a GAL and GPS files, obtain and analyze results (Figures 20.3 to 20.5).

## REFERENCES

1. Wolfgang, M. C., V. T. Lee, M. E. Gilmore, and S. Lory. 2003. Coordinate regulation of bacterial virulence genes by a novel adenylate cyclase-dependent signaling pathway. *Developmental Cell* 4(2): 253–263.
2. Martinez, M. J., A. D. Aragon, A. L. Rodriguez, J. M. Weber, J. A. Timlin, M. B. Sinclair, D. M. Haaland, and M. Werner-Washburne. 2003. Identification and removal of contaminating fluorescence from commercial and in-house printed DNA microarrays. *Nucleic Acids Research* 31(4): e18.
3. Lopez, I. P., A. Marti, F. I. Milagro, M. M. Zulet, M. J. Moreno-Aliaga, J. A. Martinez, and C. De Miguel. 2003. DNA microarray analysis of genes differentially expressed in diet-induced (cafeteria) obese rats. *Obesity Research* 11(2): 188–194.
4. Chen, X., E. M. Whitney, S. Y. Gao, and V. W. Yang. 2003. Transcriptional profiling of Kruppel-like factor 4 reveals a function in cell cycle regulation and epithelial differentiation. *Journal of Molecular Biology* 326(3): 665–677.
5. Hatfield, G. W., S. P. Hung, and P. Baldi. 2003. Differential analysis of DNA microarray gene expression data. *Molecular Microbiology* 47(4): 871–877.
6. Nam, J. H., C. H. Yu, K. A. Hwang, S. Kim, S. H. Ahn, J. Y. Shin, W. Y. Choi, Y. R. Joo, and K. Y. Park. 2002. Application of cDNA microarray technique to detection of gene expression in host cells infected with viruses. *Acta Virologica* 46(3):141–146.
7. Yeatman, T. J. 2003. The future of clinical cancer management: One tumor, one chip. *American Surgeon* 69(1): 41–44.
8. Le, B. S., S. Demolombe, A. Chambellan, C. Bellocq, F. Aimond, G. Toumaniantz, G. Lande, S. Siavoshian, I. Baro, A. L. Pond, J. M. Nerbonne, J. J. Leger, D. Escande, and F. Charpentier. 2003. Microarray analysis reveals complex remodeling of cardiac ion channel expression with altered thyroid status: Relation to cellular and integrated electrophysiology. *Circulation Research* 92(2): 234–242.
9. Hedges, J. F., D. Cockrell, L. Jackiw, N. Meissner, and M. A. Jutila. 2003. Differential mRNA expression in circulating gammadelta T lymphocyte subsets defines unique tissue-specific functions. *Journal of Leukocyte Biology* 73(2): 306–314.
10. Borucki, M. K., M. J. Krug, W. T. Muraoka, and D. R. Call. 2003. Discrimination among *Listeria monocytogenes* isolates using a mixed genome DNA microarray. *Veterinary Microbiology* 92(4): 351–362.
11. Andersen, P. S., C. Jespersgaard, J. Vuust, M. Christiansen, and L. A. Larsen. 2003. High-throughput single strand conformation polymorphism mutation detection by automated capillary array electrophoresis: Validation of the method. *Human Mutation* 21(2): 116–122.
12. Baran, M. F., R. Fagard, B. Girard, B. S. Camkilleri, F. Zeng, G. M. Lenoir, M. Raphael, and J. Feuillard. 2002. Gene array identification of Epstein Barr virus-regulated cellular genes in EBV-converted Burkitt lymphoma cell lines. *Laboratory Investigation* 82(11): 1463–1479.

13. Yang, I. V., E. Chen, J. P. Hasseman, W. Liang, B. C. Frank, S. Wang, V. Sharov, A. I. Saeed, J. White, J. Li, N. H. Lee, T. J. Yeatman, and J. Quackenbush. 2002. Within the fold: Assessing differential expression measures and reproducibility in microarray assays. *Genome Biology* 3(11).
14. Goda, H., Y. Shimada, T. Asami, S. Fujioka, and S. Yoshida. 2002. Microarray analysis of brassinosteroid-regulated genes in *Arabidopsis*. *Plant Physiology* 130(3):1319–1334.
15. Haupl, T., G. R. Burmester, and B. Stuhlmüller. 2002. New aspects of molecular biology diagnosis. Array technology and expression profile for characterization of rheumatic diseases. *Zeitschrift für Rheumatologie* 61(4): 396–404.

---

# 21 Construction and Screening of Human Antibody Libraries Using Phage Display Technology

## 21.1 INTRODUCTION

Antibodies are widely utilized in almost all aspects of life sciences, including novel research and development, pharmaceutical discoveries, vaccines, and treatment of human diseases.<sup>1-3</sup> Antibodies can be divided into two major categories: monoclonal and polyclonal antibodies. Traditionally, monoclonal antibodies are generated from mice and hybridoma cell lines. Polyclonal antibodies can be produced in rabbits, sheep, dogs, goats, etc. In terms of specificities, monoclonal antibodies have been demonstrated to be much higher than those of polyclonal antibodies.<sup>2-4</sup> However, generation of monoclonal antibodies takes longer (approximately 6 to 9 months) than polyclonal antibodies (about 1.5 to 3 months). Until recently, production of antibodies was limited to very time-consuming and laborious processes. Monoclonal antibodies, in particular, involve animal immunization schemes and generation of hybridoma cell lines, namely, monoclonal cells. Even so, such traditional methodologies can hardly produce human antibodies using animal systems. This problem has been resolved by the invention of phage display technology,<sup>2,5</sup> which is considered a revolutionary breakthrough in immunology. The technology involves current DNA recombination and gene amplification and makes it possible to clone and produce monoclonal antibodies including human antibodies in bacteria.<sup>5-7</sup>

This chapter describes in detail how to utilize phage display technology to produce monoclonal antibodies such as human antibody libraries. Successful cloning of antibody genes mandates understanding of antibody structure, function, and the principles of phage display technology. Native antibodies have a tetrameric structure consisting of two identical heavy chains (55 kDa/440 amino acids) and light chains (24 kDa/220 amino acids). The N-terminal end of each chain contains the variable domain that defines the binding specificity of an antibody. The variable domains of heavy chain (VH) and light chains (VL) give rise to a heterodimeric molecule: an Fv fragment. The C-terminal region of each chain contains constant regions,

the C region. In mice, there are five classes of constant heavy (CH) chain genes ( $\alpha$ ,  $\delta$ ,  $\epsilon$ ,  $\gamma$ ,  $\mu$ ) and two classes of constant light (CL) chain genes ( $\kappa$ ,  $\lambda$ ). The DNA and amino acid sequences are relatively conserved within each class. Based on CH regions, antibodies can be grouped into five major classes: IgA, IgD, IgG, IgE, and IgM. Furthermore, an antibody is distinguished by the light chain ( $\kappa$ ,  $\lambda$ ) paired with its heavy chain. The classes of antibodies can be isotyped with commercially available reagents.

Antibody display was initially demonstrated using antibody variable region fragments. Genes encoding VH and VL can be fused together with a DNA fragment encoding a flexible linker peptide, generating a single protein with covalently linked VH and VL termed a single-chain Fv molecule (scFv). Alternatively, antibodies can be expressed in the form of an FAb fragment composed of a whole light chain (LC) and variable heavy chain (VH), along with its first constant domain (CH1). All three forms, Fv, scFv, and FAb, have been expressed on the surface of phage.<sup>5-6</sup> A number of functional antibodies have been successfully expressed on the surface of phage, including alkaline phosphatase, protein A, CD4, and growth hormone.<sup>4-11</sup>

There are conservative sequences within the variable regions of antibody genes among species. Alignment and analysis of variable domains can lead to the determination of species-specific consensus sequences, which will be used for design of polymerase chain reaction (PCR) primers. Hence, the whole repertoires of antibody genes can be prepared by PCR. In this way, recombinant phage antibody technology has the power and versatility to mimic the features of immune diversity and monoclonal selection.

Phage display of recombinant antibodies takes advantages of the unique features of the M13 phage life cycle and the expression of a couple of phage proteins on the surface of the M13 phage.<sup>2-4</sup> The M13 phage is filamentous and approximately 895 nm long and 9 nm in diameter. Its genome is single-stranded DNA that contains 6.4 kb encoding 10 different proteins. The genome encodes a coat protein composed of approximately 2700 copies of the gene 8 protein (g8p). I, the M13 phage expresses three to five copies of the gene 3 adsorption protein (g3p) on its tip.<sup>2-3</sup> Phage display technology utilizes the features of g3p and engineered recombinant gene III, generating fusion g3p and expression of recombinant proteins or antibodies on the surface of the M13 phage. When these antibodies bind to the antigen, they bind the phage to the antigen as well, indicating that antigen-reactive antibodies are expressed on the tips of the M13 phage. The phage particles can be detected by an enzyme-labeled antibody against the g8 coat proteins (g8p).

M13 phage does not produce lytic infection in *Escherichia coli* as seen in most of other bacteriophage life cycle. M13 phage induces a state in which the infected host cells produce and secrete phage particles without undergoing lysis. Initially, infection takes place when the phage attaches to the f pilus of a male *E. coli*, which is mediated by the phage g3p. As the phage enters the cell, its coat protein is removed and deposited in the inner membrane. Meanwhile, the host DNA replication machinery changes the single-stranded (ss) phage parental DNA into the double-stranded (ds) plasmid-like replicative form (RF). The dsDNA is replicated and undergoes rolling circle replication to produce ssDNA for packaging into new phage particles. The RF also serves as the template for transcription of phage mRNA. The leader sequences

of g3p and g8p direct the transport of these proteins into the inner membrane of the bacterial cell. The ssDNA extrudes through the inner membrane and is assembled into a mature phage particle that extrudes through the cell wall into the medium without disrupting host cell growth. Phage replication continues until the host cell dies.

There are many types of commercially available vectors, which include those from Cambridge Antibody Technology and Novagen Corporation. In recent years, phagemid vector system has been developed that combines the features of phage and plasmid vectors. The phagemid carries both the M13 (ssDNA) and plasmid (dsDNA) origins of replication. Phagemids can be grown conveniently as plasmids or packaged as recombinant phage with the aid of a helper phage (i.e., M13K07). Despite that the phagemid contains the M13 origin of replication, it lacks the phage protein genes required to generate a complete phage. Hence, cells transformed with phagemid need to be infected with a helper phage that encodes proteins for replication and package ss phagemid DNA into an M13 phage particle, namely, phage rescue. The presence of a resistance marker such as ampicillin facilitates the selection of a transformed cell using an antibiotic medium. Because the M13K07 helper phage contains a defective origin of replication (IG region), the phagemid DNA is more efficiently replicated and packaged than the helper phage genome. Therefore, the majority of the phage produced contain phagemid DNA. The K07 origin is sufficient to replicate the helper phage genome in the absence of a competing phagemid. The kanamycin resistance marker on the K07 genome allows cells infected with the helper phage to be specifically selected over noninfected cells. In this way, after infection with the helper phage, the culture of phagemid-containing *E. coli* can be grown in a medium containing both ampicillin and kanamycin. Ampicillin selects for cell carrying phagemid and kanamycin selects for cells infected with K07 helper phage. The detail procedures are described as follows.

## 21.2 PREPARATION OF WHITE BLOOD CELLS (WBCS) OR LYMPHOCYTES FOR RNA ISOLATION

### 21.2.1 PREPARATION OF WBCs FROM BLOOD

1. Dilute 20 ml of heparinized blood with 20 ml PBS.
2. Divide the diluted blood into two 20-ml fractions and overlay each onto 15 ml of Ficoll-Plaque as a “cushion.”
3. To separate red blood cells (RBCs), centrifuge for 30 min at approximately 1000 rev/min at room temperature.
4. Carefully collect the peripheral blood lymphocytes from the interface by aspiration with a Pasteur pipette.
5. Dilute the cells with an equal volume of PBS and centrifuge as described in step 3.
6. Resuspend the cells in 1 ml of PBS and centrifuge as described in step 3.
7. Aspirate the supernatant; cells can be used for RNA isolation immediately or frozen at  $-70^{\circ}\text{C}$  until use.

*Note: In human blood, there are approximately  $5$  to  $11 \times 10^6$  WBCs/ml, of which about 30% are lymphocytes.*

### 21.2.2 PREPARATION OF LYMPHOCYTES FROM TISSUES

1. Place spleen or lymphonote tissues in a sterile Petri dish containing 15 ml of PBS.
2. Under a scope, tease the tissue apart using sterile forceps and a disposable syringe needle to produce a single-cell suspension of lymphocytes and erythrocytes.
3. Transfer the mixture to a tube using a 22-gauge needle and syringe and allow the clumps to settle to the bottom.
4. Transfer the supernatant to a fresh, sterile container.
5. Centrifuge for 10 min at approximately 1000 rev/min at room temperature.
6. Discard the supernatant and resuspend the cells in 10 ml of PBS and centrifuge as described in step 5.
7. Aspirate the supernatant and cells can be used for RNA isolation immediately or frozen at  $-70^{\circ}\text{C}$  until use.

Note: *There are approximately  $11 \times 10^8$  WBCs in mouse spleen or equivalent size of human spleen, of which about 35% are B cells.*

### 21.3 ISOLATION OF TOTAL RNA FROM LYMPHOCYTES

Please see the protocol described in Chapter 20.


### 21.4 SYNTHESIS OF cDNAs

#### 21.4.1 SYNTHESIS OF FIRST STRAND cDNAs FROM mRNAs

Once high quality of RNA is obtained, synthesis of cDNAs can be performed using mRNAs as templates (Figure 21.1). It is recommended that two reactions that will be carried out separately all the way to the end be set up in two microcentrifuge tubes. The benefit is that if one reaction is somehow stopped by an accident during the experiments, the other reaction can be used as a backup. Otherwise, one must start all over again, thus wasting time and money. A standard reaction is total 25  $\mu\text{l}$  using 0.2 to 2  $\mu\text{g}$  mRNA or 5 to 10  $\mu\text{g}$  total RNAs. For each additional 1  $\mu\text{g}$  mRNA, increase the reaction volume by 10  $\mu\text{l}$ . A control reaction is recommended to be carried out whenever possible under the same conditions.

1. Anneal 2  $\mu\text{g}$  of mRNAs as templates with 1  $\mu\text{g}$  of primer of oligo(dT) in a 1.5-ml sterile, RNase-free microcentrifuge tube. Add nuclease-free dd.H<sub>2</sub>O to 15  $\mu\text{l}$ . Heat the tube at  $70^{\circ}\text{C}$  for 5 min to denature the secondary structures of mRNAs and allow it to slowly cool to room temperature to complete the annealing. Briefly spin down the mixture.
2. To the annealed primer/template, add the following in the order listed. To prevent precipitation of sodium pyrophosphate when adding it to the reaction, the buffer should be preheated at 40 to  $42^{\circ}\text{C}$  for 4 min before the addition of sodium pyrophosphate and AMV reverse transcriptase. Gently mix well after each addition.





**FIGURE 21.1** Isolation of mRNAs and synthesis of cDNAs containing mRNAs/cDNAs encoding light chains and heavy chains of antibodies.

First strand 5× buffer	5 μl
rRNasin ribonuclease inhibitor	50 units (25 units/μg mRNA)
40 mM sodium pyrophosphate	2.5 μl
<u>AMV reverse transcriptase</u>	<u>30 units (15 units/μg mRNA)</u>
Add nuclease-free dd.H <sub>2</sub> O to a final	25 μl

Function of components: *The 5× reaction buffer contains components for the synthesis of cDNAs. Ribonuclease inhibitor serves to inhibit RNase activity and to protect the mRNA templates. Sodium pyrophosphate suppresses the formation of hairpins commonly generated in traditional cloning methods, thus avoiding the S1 digestion step, which is difficult to carry out. AMV reverse transcriptase catalyzes the synthesis of the first strand cDNAs from mRNA templates according to the rule of complementary base pairing.*

- Transfer 5 μl of the mixture to a fresh tube, as a tracer reaction, which contains 1 μl of 4 μCi of [ $\alpha$ -<sup>32</sup>P]dCTP (>400Ci/mmol, less than 1 week old). The synthesis of the first strand cDNAs will be measured by trichloroacetic acid (TCA) precipitation and alkaline agarose gel electrophoresis using the tracer reaction.

Caution! [ $\alpha$ - $^{32}\text{P}$ ]dCTP is a toxic isotope. Gloves should be worn when carrying out the tracer reaction, TCA assay, and gel electrophoresis. Waste materials such as contaminated gloves, pipette tips, solutions, and filter papers should be put in special containers for disposal of waste radioactive materials.

4. Incubate both reactions at 42°C for 1 to 1.5 h and then place the tubes on ice. At this point, the synthesis of the first strand cDNAs has been completed. To the tracer reaction mixture, add 50 mM EDTA solution up to a total volume of 100  $\mu\text{l}$  and store on ice until use for TCA incorporation assays and analysis by alkaline agarose gel electrophoresis.
5. To completely remove RNAs, add RNase A (DNase-free) to a final concentration of 20  $\mu\text{g/ml}$  or 1  $\mu\text{l}$  of RNase (Boehringer Mannheim, 500  $\mu\text{g/ml}$ ) per 10  $\mu\text{l}$  of reaction mixture. Incubate at 37°C for 30 min.
6. Extract the cDNAs from the unlabeled reaction mixture with 1 volume of TE-saturated phenol/chloroform. Mix well and centrifuge at 11,000 g for 5 min at room temperature.
7. Carefully transfer the top, aqueous phase to a fresh tube. Do not take any white materials at the interphase between the two phases. To the supernatant, add 0.5 volume of 7.5 M ammonium acetate or 0.15 volume of 3 M sodium acetate (pH 5.2), mix well, and add 2.5 volumes of chilled (at -20°C) 100% ethanol. Gently mix and precipitate cDNAs at -20°C for 2 h.
8. Centrifuge in a microcentrifuge at 12,000 g for 5 min. Carefully remove the supernatant, then briefly rinse the pellet with 1 ml of cold 70% ethanol. Centrifuge for 4 min and carefully aspirate the ethanol.
9. Dry the cDNAs under vacuum for 15 min. Dissolve the cDNA pellet in 15 to 25  $\mu\text{l}$  of TE buffer. Take 2  $\mu\text{l}$  of the sample to measure the concentration of cDNAs before the next reaction. Store the sample at -20°C until use.

### Materials needed

- [ $\alpha$ - $^{32}\text{P}$ ]dCTP (>400 Ci/mmol)
- 50 mM EDTA
- 7.5 M Ammonium acetate
- Ethanol (100% and 70%)
- Chloroform/isoamyl alcohol (24:1)
- 2 M NaCl
- 0.2 M EDTA
- 1 mg/ml carrier DNA (e.g., salmon sperm)
- Trichloroacetic acid (5% and 7%)
- *First strand 5 $\times$  buffer*
  - 250 mM Tris-HCl, pH 8.3 (at 42°C)
  - 250 mM KCl
  - 2.5 mM spermidine
  - 50 mM MgCl<sub>2</sub>

- 50 mM DTT  
5 mM each of dATP, dCTP, dGTP, and dTTP
- *TE buffer*  
10 mM Tris-HCl, pH 8.0  
1 mM EDTA
  - *TE-saturated phenol/chloroform*  
Thaw phenol crystals at 65°C and mix an equal part of phenol and TE buffer. Mix well and allow the phases to separate at room temperature for 30 min. Take 1 part of the lower, phenol phase to a clean beaker or bottle and mix with 1 part of chloroform/isoamyl alcohol (24:1). Mix well and allow phases to be separated, and store at 4°C until use.
  - *Alkaline gel running buffer (fresh)*  
30 mM NaOH  
1 mM EDTA
  - *2× Alkaline buffer*  
20 mM NaOH  
20% Glycerol  
0.025% Bromophenol blue (use fresh each time)

#### 21.4.2 SYNTHESIS OF DOUBLE-STRANDED cDNAs FROM SUBTRACTED cDNAs

1. Set up the following reaction:

Subtracted first strand cDNAs	1 µg
Second strand 10× buffer	50 µl
Poly(A) <sub>12-20</sub> primers	0.2 µg
<i>E. coli</i> DNA polymerase I	20 units
Nuclease-free dd.H <sub>2</sub> O to a final volume	50 µl

2. Set up a tracer reaction for the second strand DNA by transferring 5 µl of the mixture to a fresh tube containing 1 µl 4 µCi [ $\alpha$ -<sup>32</sup>P]dCTP (>400 Ci/mmol). The tracer reaction will be used for TCA assay and alkaline agarose gel electrophoresis to monitor the quantity and quality in the synthesis of the second strand DNA, as described above.
3. Incubate both reactions at 14°C for 3.5 h and then add 95 µl of 50 mM EDTA to the 5-µl tracer reaction.
4. Heat the unlabeled (nontracer portion) double strand DNAs sample at 70°C for 10 min to stop the reaction. At this point, the double strand DNAs should be produced. Briefly spin down to collect the contents at the bottom of the tube and place on ice until use.
5. Add 4 units of T4 DNA polymerase (2 u/µg input cDNA) to the mixture and incubate at 37°C for 10 min. This step functions to make the blunt-end double-stranded cDNAs by T4 polymerase. The blunt ends are required for later adapter ligations.
6. Terminate the T4 polymerase reaction by adding 3 µl of 0.2 M EDTA and place on ice.

7. Extract the cDNAs with 1 volume of TE-saturated phenol/chloroform. Mix well and centrifuge at 11,000 *g* for 4 min at room temperature.
8. Carefully transfer the top aqueous phase to a fresh tube and add 0.5 volume of 7.5 M ammonium acetate or 0.15 volume of 3 M sodium acetate (pH 5.2). Mix well and add 2.5 volumes of chilled ( $-20^{\circ}\text{C}$ ) 100% ethanol. Gently mix and precipitate the cDNAs at  $-20^{\circ}\text{C}$  for 2 h.
9. Centrifuge at 12,000 *g* for 5 min and carefully remove the supernatant. Briefly rinse the pellet with 1 ml of cold 70% ethanol, centrifuge at 12,000 *g* for 5 min, and aspirate the ethanol.
10. Dry the cDNA pellet under vacuum for 15 min. Dissolve the cDNA pellet in 20  $\mu\text{l}$  of TE buffer. Measure the concentration of the cDNAs as described above. Store the sample at  $-20^{\circ}\text{C}$  until use.

Note: *Before adapter ligation, it is strongly recommended that the quantity and quality of the double-stranded cDNAs be checked by TCA precipitation and gel electrophoresis as described previously.*

### Materials needed

- [ $\alpha$ - $^{32}\text{P}$ ]dCTP (>400Ci/mmol)
- 50 mM EDTA
- 3 M sodium acetate buffer, pH 5.2
- Ethanol (100% and 70%)
- Chloroform/isoamyl alcohol (24:1)
- 0.2 M EDTA
- Trichloroacetic acid (5% and 7%)
- *Hybridization buffer* (2 $\times$ )
  - 40 mM Tris-HCl, pH 7.7
  - 1.2 M NaCl
  - 4 mM EDTA
  - 0.4% SDS
  - 1  $\mu\text{g}/\mu\text{l}$  Carrier yeast tRNA (optional)
- *Phosphate buffer* (stock)
  - 0.5 M Monobasic sodium phosphate
  - Adjust the pH to 6.8 with 0.5 M dibasic sodium phosphate

## 21.5 DESIGN OF PRIMERS FOR CONSTRUCTION OF ANTIBODY V GENE REPERTOIRE

PCR and/or reverse transcription (RT)-PCR amplification of antibody variable regions (V genes) are carried out using primers complementary with the ends of VH and VL. The products of VH and VL PCR can be linked by PCR to form recombinant, single-chain Fv fragment. Tables 21.1 and 21.2 list a series of primers that have been tested.

**TABLE 21.1****Series of Primers for PCR Amplification of Human Antibody Variable Regions (V gene)***1. Primers for human V gene PCR***A. Human heavy chain variable region (VH) forward primers**

5' CAGGTGCAGCTGGTGCAGTCTGG 3'

5' GAGGTGCAGCTGGTGGAGTCTGG 3'

5' CAGGTCAACTTAAGGGAGTCTGG 3'

5' CAGGTGCAGCTGCAGGAGTCGGG 3'

5' CAGGTACAGCTGCAGCAGTCAGG 3'

**B. Human join region of heavy chain (JH) reverse primers**

5' TGAAGAGACGGTGACCATTTGCC 3'

5' TGAGGAGACGGTGACCAGGGTGCC 3'

5' TGAGGAGACGGTGACCGTGGTCCC 3'

5' TGAGGAGACGGTGACCAGGGTTC 3'

**C. Human V kappa forward primers**

5' GAAATTGTGCTGACTCAGTCTCC 3'

5' GACATCCAGATGACCCAGTCTCC 3'

5' GATGTTGTGATGACTCAGTCTCC 3'

5' GAAATTGTGTTGACGCAGTCTCC 3'

5' GAAACGACACTCACGCAGTCTCC 3'

5' GACATCGTGATGACCCAGTCTCC 3'

**D. Human J kappa reverse primers**

5' ACGTTTGATTTCCACCTTGGTCCC 3'

5' ACGTTTAATCTCCAGTCGTGTCCC 3'

5' ACGTTTGATCTCCAGCTTGGTCCC 3'

5' ACGTTTGATATCCACTTTGGTCCC 3'

5' ACGTTTGATCTCCACCTTGGTCCC 3'

**E. Human V lambda forward primers**

5' AATTTTATGCTGACTCAGCCCCA 3'

5' CAGTCTGTGTTGACGCAGCCGCC 3'

5' CAGTCTGCCCTGACTCAGCCTGC 3'

5' TCCTATGTGCTGACTCAGCCACC 3'

5' CAGGCTGTGCTCACTCAGCCGTC 3'

5' TCTTCTGAGCTGACTCAGGACCC 3'

**F. Human J lambda reverse primers**

5' ACCTAAAACGGTGAGCTGGGTCCC 3'

5' ACCTAGGACGGTGACCTTGGTCCC 3'

5' ACCTAGGACGGTCAGCTTGGTCCC 3'

*2. Primers for linker fragment PCR***G. Forward primers of JH for scFv linker**

-----Heavy chain region----- --Linker-----

5' GGACCACGGTCACCGTCTCCTCAGGTGG 3'

5' GCACCCTGGTCACCGTCTCCTCAGGTGG 3'

*(continued)*

**TABLE 21.1 (Continued)****Series of Primers for PCR Amplification of Human Antibody Variable Regions (V gene)**

## G. Forward primers of JH for scFv linker

5' GGACAATGGTCACCGTCTCTTCAGGTGG 3'

5' GAACCCTGGTCACCGTCTCCTCAGGTGG 3'

## H. Reverse primers of V kappa for scFV linker

-----Light chain region----- --Linker-----

5' GGAGACTGAGTCAGCACAAATTCGGATCCGCC 3'

5' GGAGACTGCGTGAGTGTCTGTTCCGATCCGCC 3'

5' GGAGACTGGGTCATCTGGATGTCCGATCCGCC 3'

5' GGAGACTGCGTCAACACAATTCGGATCCGCC 3'

## I. Reverse primers of V lambda linker

-----Light chain region----- --Linker -----

5' GGCGGCTGCGTCAACACAGACTG CGATCCGCCACCGCCAGAG 3'

5' GCAGGCTGAGTCAGAGCAGACTG CGATCCGCCACCGCCAGAG 3'

5' GGTGGCTGAGTCAGCACATAGGA CGATCCGCCACCGCCAGAG 3'

5' TGGGGCTGAGTCAGCATAAAATT CGATCCGCCACCGCCAGAG 3'

3. Primers for generation of full-length ( $V_H + Linker + V_L$ ) fragment with restriction enzyme sitesJ. Human VH forward primer with *Sfi*I site

-----Heavy chain V region-----

5' GTCCTCGCAACTGCGGCCAGCCGGCC ATGGCCCAGGTGCAGCTGGTGCAGTCTGG 3'5' GTCCTCGCAACTGCGGCCAGCCGGCC ATGGCCCAGGTCAACTTAAGGGAGTCTGG 3'5' GTCCTCGCAACTGCGGCCAGCCGGCC ATGGCCGAGGTGCAGCTGGTGGAGTCTGG 3'5' GTCCTCGCAACTGCGGCCAGCCGGCC ATGGCCCAGGTACAGCTGCAGCAGTCAGG 3'K. Human J kappa reverse primers with *Not*I sites

-----Light chain V region-----

5' GAGTCATTCTCGACTTGCGGCCGCACGTTTGATTCCACCTTGGTCCC 3'5' GAGTCATTCTCGACTTGCGGCCGCACGTTTGATCTCCAGCTTGGTCCC 3'5' GAGTCATTCTCGACTTGCGGCCGCACGTTTAATCTCCAGTCGTGTCCC 3'5' GAGTCATTCTCGACTTGCGGCCGCACGTTTGATCTCCACCTTGGTCCC 3'L. Human J lambda reverse primers with *Not*I sites

-----Light chain V region-----

5' GAGTCATTCTCGACTTGCGGCCGCACCTAGGACGGTGACCTTGGTCCC 3'5' GAGTCATTCTCGACTTGCGGCCGCACCTAGGACGGTCAGCTTGGTCCC 3'5' GAGTCATTCTCGACTTGCGGCCGCACCTAAAACGGTGAGCTGGGTCCC 3'

**TABLE 21.2**  
**Primer Series For PCR Amplification of Mouse Antibody Variable Regions (V Gene)**

*1. Primers for V gene PCR*

A. Mouse VH forward primer

5' AGGTGCACAAGCTGCAGGCAGTCATGG 3'

B. Mouse JH reverse primer

5' TGAGGAGACGGTGACCGTGGTCCCTTGGCCCC 3'

C. Mouse V kappa reverse primer

5' GACATTGAGCTCACCCAGTCTCCA 3'

D. Mouse V lambda reverse primers

5' CCGTTTGATTTCAGCTTGGTGCC 3'

5' CCGTTTCAGCTCCAGCTTGGTCCC 3'

*2. Primer for Linker fragment PCR*

E. Mouse JH: for scFv linker

5' GGGACCAC GGTCACCGTCTCCTCA 3'

F. Mouse V kappa reverse primer

5' TGGAGACTGGGTGAGCTCAATGTC 3'

*3. Primers for generation of full-length fragment PCR*

G. Mouse VH forward primer with *Sfi*I site

-----Heavy chain V region-----

5' TCCTCGCAACTGCGGCCAGCCGGCCATGGCCCAGGTGCACAAGCTGCAGGCAGTC 3'

H. Mouse V lambda reverse primer

----- Light chain V region-----

5' GAGTCATTCTGCGGCCGCCGTTTGATTTCAGCTTGGTGCC 3'


5' GAGTCATTCTGCGGCCGCCGTTTCAGCTCCAGCTTGGTCCC 3'

## 21.6 PCR AMPLIFICATION OF HEAVY- AND LIGHT-CHAIN VARIABLE REGIONS (VH, VL), LINKER, AND ASSEMBLY OF RECOMBINANT SINGLE-CHAIN DNA VIA PCR

Figure 21.2 illustrates the procedures for amplification and assembly of VH–linker–VL using PCR technology. Using appropriate forward and reverse primers listed in Section 21.5, the variable regions of heavy chain (VH), light chain (VL), and a linker fragment can be amplified in separate PCR reactions. The PCR products for VH and VL are approximately 350 and 325 base pairs in length, respectively. A typical PCR reaction is described below.

1. Prepare a PCR cocktail in a 0.5 microcentrifuge tube as follows:

Forward primer	5–8 pmol (30–40 ng) depending on the size of primer
Reverse primer	5–8 pmol (30–40 ng) depending on the size of primer
cDNAs	1–2 µg
10× Amplification buffer	4 µl



**FIGURE 21.2** Amplification of variable regions of heavy chain (HC) and light chain (LC) cDNAs and assembly of recombinant single chain cDNA.

dNTPs (2.5 mM each)	4 $\mu$ l
<i>Taq</i> or <i>Tth</i> DNA polymerase	5–10 units
Add dd.H <sub>2</sub> O to a final volume of	40 $\mu$ l


Note: The DNA polymerase should be high fidelity and long expand, which is commercially available.

- Carefully overlay the mixture with 30  $\mu$ l of mineral oil to prevent evaporation of the samples during PCR amplification. Place the tubes in a thermal cycler and perform PCR.

Profile	Predenaturation	Cycling (35 cycles)			Hold
		Denaturation	Annealing	Extension	
Template	94°C, 3 min	94°C, 0.5 min	55°C, 0.5 min	72°C, 1.5 min	4°C

- Purify PCR products using appropriate reagents (i.e., a kit from Qiagen).
- Carry out PCR amplification and agarose gel purification of recombinant, single-chain ( $V_H$ -linker- $V_L$ ) using forward and reverse primers with restriction enzyme sites at the ends, as illustrated in Figure 21.3.
- Perform restriction enzyme digestion and purification of the single-chain DNA (Figure 21.4).






**FIGURE 21.3** Addition of appropriate adaptor ends to recombinant single chain DNA via PCR amplification and agarose gel purification.

## 21.7 GENERATION OF RECOMBINANT DNA CONSTRUCTS FOR EXPRESSING RECOMBINANT ANTIBODIES ON SURFACE OF PHAGE

As shown in Figure 21.5, after restriction enzyme digestion of recombinant, single-chain DNA (V<sub>H</sub>–linker–V<sub>L</sub>), the DNA needs to be ligated with appropriate vectors, which are commercially available. For details on protocols (ligation, bacterial transformation, isolation of plasmid DNA, and validation of cloned sites), please refer to Chapter 4 of this book.

## 21.8 EXPRESSION, BIOPANNING, AND CHARACTERIZATION OF PHAGE PRODUCES MONOCLONAL ANTIBODIES ON ITS TIP

The general procedure is illustrated in Figure 21.6. It is recommended that a vector carrying an inducible *Lac* promoter be utilized for cloning and expression of recombinant antibodies. The *Lac* promoter itself is in turn regulated by the *lac I*<sup>q</sup> gene that encodes the *lac* repressor. Under appropriate conditions, the transcription of cloned gene under the *lac* promoter by the *E. coli* DNA-dependent RNA polymerase is inhibited by the




**FIGURE 21.4** Generation of incompatible sticky ends by restriction enzyme digestion with *SfiI* and *NotI* as an example.


*lac* repressor, blocking the expression of the g3p fusion protein or recombinant antibodies. Given the fact that accumulation of g3p is toxic to the host cell, the *lac* promoter needs to be tightly controlled before infection with K07 helper phage to block the expression of g3p. Bacterial strains such as *E. coli* TG1 and HB2125 should be used as they contain the *lac* repressor gene. Additionally, low temperature (i.e., 30°C) and culture medium containing 5% glucose can be used to minimize the “leaky” status of the *lac* promoter. The glucose forces the transformed bacteria to shut down alternate metabolic pathways, repressing the *lac* operon. During K07 helper phage infection, the glucose medium is removed and the *lac* promoter is allowed to express the ScFv–g3p fusion protein. Such residual, low level of g3p will be sufficient for phage assembly. Alternatively, some commercial vectors have both the *lac* promoter and the *lac* repressor gene. In this case, expression of ScFv–g3p fusion protein can be induced with 1 mM IPTG. It should be noted that such IPTG induction needs to be controlled because over-expression of fusion proteins can kill the infected cells, producing no phage particles.

### 21.8.1 INFECTION OF BACTERIA CARRYING RECOMBINANT DNA CONSTRUCTS AND RESCUING PHAGEMID LIBRARIES

1. Inoculate a putative bacterial colony in 50 ml of Luria–Bertani (LB) medium containing 3% to 5% (w/v) glucose and 100 µg/ml of ampicillin in a 250-ml sterile flask.
2. Grow the cells for approximately 6 to 12 h at 30°C until the OD<sub>600</sub> is about 0.5.



**FIGURE 21.5** Cloning and generation of recombinant DNA construct for expressing recombinant antibodies and/or proteins of interest.



**FIGURE 21.6** Expression and purification of phages that produce monoclonal antibodies against proteins of interest.

Notes: *Bacteria are in mid-log phase and express the F pilus. If the OD exceeds 0.5, dilution can be done.*

3. Perform infection by adding  $2 \times 10^{10}$  pfu M13K07 helper phage to 50 ml of LB culture and grow the cells at 37°C for 1 h.

Note: *The helper phage/bacteria ratio is approximately 1:1.*

4. Centrifuge at 3000 g for 10 min and resuspend the cells in 500 ml LB medium containing 100 µg/ml of ampicillin and 50 µg/ml of kanamycin in a 2-l flask.  
Note: *The culture medium at this point should not contain glucose. Removing glucose serves to induce intact fusion g3p.*

5. Incubate at 30°C overnight with vigorous shaking.

6. Harvest the phage–antibody particles by centrifugation and PEG precipitation. Add 0.2 volume of precipitation solution (20% PEG, 2.5 M NaCl) and allow to precipitate for 30 to 60 min at 4°C, followed by centrifugation at 5000 g for 10 min.

7. Resuspend the particles in 0.5 ml PBS or TE buffer.

Note: *This usually gives rise to  $5 \times 10^{11}$  pfu/ml infectious particles.*

### 21.8.2 SELECTION OF PHAGE–ANTIBODY PARTICLES BY BIOPANNING

1. Coat a 96-well microtiter/ELISA plate overnight with 150 µl/well of antigen solution at 4°C or for 2 to 3 h at room temperature.

Note: *The antigen of interest can be dissolved in 20 mM Tris buffer (pH 7.5) or 50 mM sodium hydrogen carbonate, pH 9.5. The concentration of antigen can be 0.1 to 1 mg/ml.*

2. Briefly rinse the plate with PBS and block wells with 0.35 ml/well of PBS containing 5% (w/v) nonfat dry milk for 2 h at room temperature.

3. Add approximately  $1 \times 10^6$  pfu phage/well and allow incubation to proceed for 1 to 2 h at room temperature with shaking.

4. Wash the plate 3 × 5 min with PBS containing 0.1% Tween-20.

Note: *This step serves to wash away nonspecific phage particles. Those particles with recombinant antibodies on their surface should bind to the coated antigen.*

5. Add 150 µl of detection antibody solution [i.e., labeled antibodies against g8p on the surface of phage diluted at 1:5000 in PBS. The antibodies can be labeled with alkaline phosphatase, AP or horseradish peroxidase (HRP)] to each well, and incubate at room temperature for 2 h with agitation.

6. Wash the plate as described in step 4.

7. Detect positive wells by adding 100 µl of the substrate solution for AP or HRP for 20 min at room temperature. Colored wells indicate the presence of antibody–phage particles.

8. Elute the phage from the positive wells by adding 0.2 ml/well of elution buffer (100 mM triethylamine or 100 mM glycine (pH 3.0)). Elute for 15 min at room temperature with agitation.

Note: *Once the phage particles are eluted, the solution should be neutralized immediately using 0.1 ml of 1 M Tris buffer (pH 7.5). Store the viral particles at 4°C until use.*

9. Reinfect bacteria with the eluted phage particles as described in Section 21.8.1 and further selection of putative phage particles as described in steps 1 to 8 in Section 21.8.2.
10. Characterize recombinant antibodies via western blotting and/or ELISA.
11. Following putative phage (monoclonal) identified, production and validation of monoclonal antibodies can be scaled up against specific proteins of interest.

## REFERENCES

1. McCafferty, J., A. D. Griffiths, G. Winter, and D. J. Chiswell. 1990. Phage antibodies: Filamentous phage displaying antibody variable domains. *Nature* 348: 552–554.
2. Hoogenboom, H. R., and G. Winter. 1992. By-passing immunization: Human antibodies from synthetic repertoires of germline VH gene segments rearranged *in vitro*. *Journal of Molecular Biology* 227: 381–388.
3. McCafferty, J., and K. S. Johnson. 1996. Construction and screening of antibody display libraries. In *Phage Display of Peptides and Proteins*. San Diego, CA: Academic Press, 79–110.
4. Huston, J. S., D. Levinson, H. M. Mudgett, M. S. Tai, J. Novotny, M. N. Margolies, R. J. Ridge, R. E. Bruccoleri, E. Haber, R. Crea, and H. Opperman. 1988. Protein engineering of antibody binding sites: Recovery of specific activity in an anti-digoxin single-chain Fv analogue produced in *E. coli*. *Proceedings of the National Academy of Sciences of the United States of America* 85: 5879–5883.
5. Willats, W. G. 2002. Phage display: Practicalities and prospects. *Plant Molecular Biology* 50(6): 837–854.
6. Steinhauer, C., C. Wingren, A. C. Hager, and C. A. Borrebaeck. 2002. Single framework recombinant antibody fragments designed for protein chip applications. *Biotechniques* (Suppl): 38–45.
7. Wu, W. 1997. Construction and screening of subtracted and complete expression cDNA libraries. In *Methods in Gene Biotechnology*, ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang, 29–65. Boca Raton, FL: CRC Press.
8. Wu, W., and H. Zhang. 1997. Subcloning of gene or DNA fragments. In *Methods in Gene Biotechnology*, ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang, 67–88. Boca Raton, FL: CRC Press.
9. Sidhu, S. S., W. J. Fairbrother, and K. Deshayes. 2003. Exploring protein–protein interaction with phage display. *Chembiochem* 4(1): 14–25.
10. Krichevsky, A., A. Graessmann, A. Nissim, S. C. Piller, N. Zakai, and A. Loyter. 2003. Antibody fragments selected by phage display against the nuclear localization signal of the HIV-1 Vpr protein inhibit nuclear import in permeabilized and intact cultured cells. *Virology* 305(1): 77–92.
11. Hartley, O. 2002. The use of phage display in the study of receptors and their ligands. *Journal of Receptors and Signal Transduction Research* 22(1): 373–392.

---

# 22 Down-Regulation of Gene Expression in Mammalian Systems via siRNA Technology

## 22.1 INTRODUCTION

Short-interfering RNA (siRNA)—double-stranded RNA (dsRNA) with approximately 21 nt in length—is a powerful tool that has been widely used for down-regulation of expression of specific genes.<sup>1–5</sup> Introduction of siRNAs to mammalian cells leads to the sequence-specific destruction of endogenous mRNA molecules that are complementary to siRNAs (Figure 22.1). The cellular process that undergoes degradation of target mRNA via siRNA is termed RNA interference (RNAi). During RNAi, siRNAs appear to serve as guides for enzymatic cleavage of complementary RNAs. In addition, in some systems, siRNAs can function as primers for an RNA-dependent RNA polymerase that can synthesize additional siRNAs, which can enhance the effects of RNAi.<sup>1,4–8</sup> Nevertheless, the mechanism by which complementary RNAs can be destroyed by siRNAs is not well understood, and the specific enzyme(s) that mediate siRNA functions remain to be identified.

It has been demonstrated that relatively long siRNAs (>30 nt in length) do not work well in mammalian cells in terms of RNAi because of the nonspecificity of siRNAs. However, siRNAs 19 to 21 nt in length are very effective as they are too short to trigger nonspecific dsRNA response.<sup>5,9–11</sup> Therefore, 19- to 21-nt double-stranded siRNAs have been widely utilized for down-regulation or knocking-down of expression of genes of interest.

Initially, siRNAs were synthesized *in vitro* and then applied to specific cells to inhibit the mRNA of interest. Although this technique has been successful, it is time consuming, costly, and less effective. Recently, development of vectors has overcome the limitations of traditional methodology. Double-stranded siRNA oligonucleotides can be cloned downstream U2, U6, or Hi RNA polymerase III promoter that leads to expression of siRNAs *in vivo*. This chapter provides a guide on how to utilize siRNA technology to inhibit the expression of genes of interest.




FIGURE 22.1 Down-regulation of mRNA expression via siRNA.

## 22.2 DESIGN OF OLIGONUCLEOTIDES FOR HAIRPIN siRNA

### 22.2.1 SELECTION OF siRNA TARGET SITE

It is imperative to select an optimal target site of specific mRNA. The criteria and recommendations can be summarized as follows:

1. Target region to be considered:
  - (a) The upstream nucleotide sequence from the initiation codon AUG and the first codon AUG should be selected as the most effective target region when designing an oligomer for siRNA. The hybridization of the oligomers may prevent the small subunit of the ribosome from interacting with the upstream region of the initiating AUG codon, thus blocking the initiation of translation.
  - (b) SiRNA oligonucleotides can also be designed to be complementary to the coding regions to block the chain elongation of the specific polypeptide. However, this will be less effective compared to the selection described in (a).
  - (c) The terminal region of translation is a good target to block the termination of translation. The partial-length polypeptide may not be folded properly and will be rapidly degraded.
  - (d) Unlike design of primers for polymerase chain reaction (PCR), which involves the  $T_m$  value, the siRNA oligomers for inhibition of gene expression do not need computer analysis of  $T_m$ .



2. Target sequences: For targeting a single mRNA, it is necessary to analyze the full-length cDNA among other cDNAs of the family using DNA software such as Lasergene. To avoid inhibiting nontargeting genes, it is important to identify unique sequences as the target site of specific cDNA of interest. It would be a big mistake to select highly homologous sequences.

### 22.2.2 SELECTION OF OLIGOMER SIZE AND ORIENTATION FOR siRNAs

1. To effectively down-regulate the expression of a specific gene, it is recommended to design a 53- to 55-nt oligonucleotide fragment for generation of hairpin siRNA, which is composed of 19- to 21-nt target sequence (sense orientation) + 9 nt loop + 19- to 21-nt target sequence (antisense orientation) + 3- to 4-nt 3' terminal thymidine tract (Figure 22.1). An example would be as follows:

5' GCTGGACCTGACGTAACCGTA (sense target sequence)  
 TTCAAGAGA (a loop) TGACCTGGACTGCATTGGCAC (antisense  
 target sequence) TTTT (terminal sequence) 3'.

Additionally, specific restriction enzyme sites may be added at 5' and 3' ends for cloning into the appropriate vector.

2. Given that it is more effective for RNA polymerase III to initiate transcription of siRNAs if the 5' end of oligonucleotides is a purine, it is recommended that a G or A be designed at the 5' end of sense target sequence.
3. Design another oligonucleotide fragment that is complementary to the sequence listed in (a). For instance, 3' CGACCTGGACTGCATTGGCAT (sense target sequence) AAGTTCTCT (loop) ACTGGACCTGACGTAACCGTC (antisense target orientation) AAAA 5'. This oligonucleotide fragment will hybridized to the fragment in (a), generating a double-stranded DNA fragment to be cloned into expression vector (Figure 22.1).

### 22.2.3 SYNTHESIS OF HAIRPIN siRNA-ENCODING OLIGONUCLEOTIDES

Based on the design of oligonucleotides, an appropriate scale of oligos can be ordered and chemically synthesized; no extra purification is necessary.

## 22.3 PREPARATION OF DOUBLE-STRANDED OLIGONUCLEOTIDE FRAGMENT FOR CLONING

1. Dissolve the oligonucleotides synthesized in Section 22.2.3 in TE buffer (10 mM Tris, pH 8.0, 1 mM EDTA) to a final concentration of 1  $\mu\text{g}/\mu\text{l}$ .
2. Anneal both strands of hairpin siRNA oligonucleotides as follows:

Annealing solution	25 $\mu\text{l}$
Sense strand oligonucleotide fragment solution	1 $\mu\text{l}$
Antisense strand oligonucleotide fragment solution	1 $\mu\text{l}$
<hr/> Total volume	<hr/> 25 $\mu\text{l}$

- Heat the mixture to 92°C for 5 min and slowly cool to room temperature, then incubate for 1 h at room temperature. Store the annealed double-stranded oligonucleotide fragment or hairpin siRNA oligo insert at 4°C until use.

## 22.4 CLONING HAIRPIN siRNA OLIGO INSERT INTO APPROPRIATE VECTORS

As illustrated in Figure 22.2, double-stranded hairpin siRNA oligo insert can be ligated to an appropriate vector for expressing hairpin siRNA. The procedure is as follows:

- Assemble a ligation reaction in an Eppendorf tube

Restriction enzyme digested vector DNA	1 µg
Hairpin siRNA oligo insert DNA	20–50 ng
10× Ligase buffer	2 µl
T4 DNA ligase	10 units
(Weiss units)	
<hr/>	
Add dd.H <sub>2</sub> O to a final volume of	20 µl

- Incubate the ligation for 2 h to overnight at 4°C. The ligated mixture is ready for transformation to bacteria.

Note: *Double-stranded hairpin siRNA oligonucleotides can be fused with a reporter gene system so that inhibition of reporter gene activity can be*





FIGURE 22.2 Cloning and generation of DNA construct for expression of siRNA.



**FIGURE 22.3** Cloning and generation of reporter gene constructs for siRNA or fluorescent assays.

*rapidly and accurately measured or observed under a fluorescent microscope (Figure 22.3).*

3. Thaw a 0.2-ml aliquot of frozen  $\text{CaCl}_2$ -treated competent cells on ice.
4. Assemble transformation as follows:

Components	Tube #1	Tube #2
Cells	50 $\mu\text{l}$	50 $\mu\text{l}$
DNA	50 ng in 5 $\mu\text{l}$	200 ng in 5 $\mu\text{l}$

5. Incubate on ice for 50 to 60 min.
6. Heat shock at  $42^\circ\text{C}$  for 1 to 1.5 min and quickly place the tubes on ice for 1 min.  
*Tip: Heat-shock and chilling on ice should not exceed the length of time indicated. Otherwise, the efficiency of transformation will decrease 10- to 20-fold.*
7. Transfer the cell suspension to sterile culture tubes containing 1 ml of LB medium without antibiotics. Incubate at  $37^\circ\text{C}$  for 1 to 2 h with shaking at 140 rev/min to recover the cells.
8. Transfer 50 to 150  $\mu\text{l}$  of the cultured cells per plate onto the center of LB plates containing 50  $\mu\text{g}/\text{ml}$  ampicillin (or 0.5 mM IPTG and 40  $\mu\text{g}/\text{ml}$  X-Gal

for color selection). Immediately spread the cells over the entire surface of the LB plates using a sterile, bent glass rod.

9. Invert the plates and incubate them at 37°C overnight. Selected colonies should be visible 14 h later.

## 22.5 PURIFICATION OF PLASMID DNA CARRYING HAIRPIN siRNA INSERT

1. Inoculate a single colony in 5 ml LB medium and 50 µg/ml of appropriate antibiotics (e.g., ampicillin), depending on the specific antibiotic-resistant gene carried by the specific plasmid. Culture the bacteria at 37°C overnight with shaking at 200 rev/min.
2. Transfer the overnight culture into microcentrifuge tubes (1.5 ml/tube) and centrifuge at 6000 rev/min for 4 min. Carefully aspirate the supernatant.  
*Note: If the plasmid carried by bacteria is a high-copy number plasmid, 1.5 ml of cell culture usually gives a yield of approximately 40 µg plasmid DNA using the present method. In this way, 10 tubes of preparation can generate about 400 µg plasmid DNA, which is equivalent to a large-scale preparation. Therefore, the volume of bacterial culture used for purification of plasmid DNA depends on a particular experiment.*
3. Add 0.1 ml of ice-cold lysis buffer to each tube and gently vortex for 1 min. Incubate at room temperature for 5 min.  
*Note: The purpose of this step is to lyse the bacteria by hyperlytic osmosis, releasing DNA and other contents.*
4. Add 0.2 ml of a freshly prepared alkaline solution to each tube and mix by inversion. **Never vortex.** Place the tubes on ice for 5 min.  
*Note: This step denatures chromosomal DNA and proteins.*
5. Add 0.15 ml of ice-cold potassium acetate solution to each tube. Mix by inversion for 10 s and incubate on ice for 5 min.  
*Note: The principle of this step is to selectively precipitate proteins, polysaccharides, and genomic DNA. Under this particular buffer condition, plasmid DNA remains in the supernatant without being precipitated.*
6. Centrifuge at 12,000 g for 5 min and carefully transfer the supernatant to fresh tubes.
7. To degrade total RNAs from the sample, add RNase (DNase-free, Boehringer Mannheim) into the supernatant at 1.5 µl/10 µl supernatant. Incubate the tubes at 37°C for 30 min.
8. Transfer the RNase-treated supernatant into a minifilter cup (0.4 ml/cup) placed in an Eppendorf tube. Cap the tube and centrifuge at 12,000 g for 30 s. Remove the filter cup; the collected supernatant in the Eppendorf tube is ready for DNA precipitation.  
*Note: The membrane filter at the bottom of the cup is specially designed to retain proteins and allow nucleic acids to pass through. One cup can be reused for four to five times if it is used for the same supernatant pool. However, it is not wise to reuse it for different plasmid samples due to potential contamination. The author routinely utilizes this type of filter for*

*plasmid DNA preparation. DNA obtained is pure and high yield with a  $A_{260}/A_{280}$  ratio of approximately 2.0.*

9. Add 2 to 2.5 volumes of 100% ethanol to each tube. Mix by inversion and allow the plasmid DNA to precipitate for 10 min at  $-80^{\circ}\text{C}$  or 30 min at  $-20^{\circ}\text{C}$ .
  10. Centrifuge at 12,000  $g$  for 10 min. Carefully decant the supernatant, add 1 ml of prechilled 70% ethanol, and centrifuge at 12,000  $g$  for 5 min. Carefully aspirate the ethanol and dry the plasmid DNA in under vacuum for 15 min.
  11. Dissolve the plasmid DNA in 15  $\mu\text{l}$  of TE buffer or sterile deionized water. Take 1  $\mu\text{l}$  to measure the concentration and store the sample at  $-20^{\circ}\text{C}$  until use.
- Note: *At this point, the DNA is ready for transfection into cells of interest.*

### Reagents needed

- *LB (Luria–Bertani) medium (per liter)*
  - 10 g Bacto-tryptone
  - 5 g Bacto-yeast extract
  - 5 g NaCl
  - Adjust pH to 7.5 with 2 N NaOH and autoclave. If needed, add antibiotics after the autoclaved solution has cooled to below  $50^{\circ}\text{C}$ .
- *TE buffer*
  - 10 mM Tris–HCl, pH 8.0
  - 1 mM EDTA
- *Lysis buffer*
  - 25 mM Tris–HCl, pH 8.0
  - 10 mM EDTA
  - 50 mM Glucose
- *Alkaline solution*
  - 0.2 N NaOH
  - 1% SDS
- *Potassium acetate solution (pH 4.8)*
  - Prepare 60 ml of 5 M potassium acetate. Add 11.5 ml glacial acetic acid and 28.5 ml  $\text{H}_2\text{O}$  to a total volume of 100 ml. This solution is 3 M with respect to potassium and 5 M with respect to acetate. Store on ice before use.
- *RNase (DNase-free)*
  - Boehringer Mannheim, Cat. No: 119915, 500  $\mu\text{g}/\text{ml}$ .

## 22.6 TRANSIENT TRANSFECTION OF CELLS OF INTEREST WITH PURIFIED PLASMID DNA TO EXPRESS siRNAs FOR INHIBITING TARGET mRNA

Mammalian cells can be transfected with commercially available reagents/kits (available from manufacturers such as Roche Molecular Chemicals and Invitrogen).

Calcium phosphate methods may be used. The principle of calcium phosphate transfection is that the DNA to be transferred is mixed with  $\text{CaCl}_2$  and phosphate buffer to form a fine calcium phosphate precipitate. The precipitated complexes or particles are then placed on a cell monolayer. They bind or attach to the plasma membrane and are taken into the cell by endocytosis. This is one of the most widely used methods for both transient and stable transfection.

1. Perform trypsinization to remove adherent cells for subculture or cell counting as well as for monolayer cell preparation.
  - (a) Aspirate the medium from the cell culture or the tissue culture dish and wash the cells twice with 10 to 15 ml of PBS buffer or other calcium- and magnesium-free salt solutions.
  - (b) Remove the washing solution and add 1 ml of trypsin solution per 100-mm dish. Quickly overlay the cells with the solution and incubate at  $37^\circ\text{C}$  for 5 to 10 min, depending on the cell type (e.g., NIH 3T3, 2 min; CHO, 2 min; HeLa, 2.5 min; COS, 3 min).
  - (c) Closely monitor the cells. Once they begin to detach, immediately remove the trypsin solution and tap the bottom and sides of the culture flask or dish to loosen the remaining adherent cells.
  - (d) Add culture medium containing 10% serum (e.g., FBS or FCS) to the cells to inactivate the trypsin. Gently shake the culture dish. The cells can be used for cell subculturing or counting.
2. Prepare cell monolayers the day before the transfection experiment. The cell monolayers should be at 60% to 70% confluence. Aspirate the old culture medium and feed the cells with 5 to 10 ml of fresh culture medium.
 

Notes: (1) *It is recommended that this procedure be carried out in a sterile laminar flow hood. Gloves should be worn to prevent contamination of the cells.* (2) *Common cell lines used for transfection are NIH 3T3, CHO, HeLa, COS, and mouse embryonic stem (ES) cells. Other mammalian cells of interest can also be transfected in this manner.* (3) *The cell density to be seeded depends on the particular cell line. A general guideline is 1 to  $5 \times 10^6$  cells per 100-mm culture dish.* (4) *All of the solutions and buffers should be sterilized by autoclaving or by sterile-filtration.*
3. Prepare a transfection mixture for each 100-mm dish as follows:

2.5 M $\text{CaCl}_2$ solution	50 $\mu\text{l}$
<u>DNA construct or constructs (cotransfection)</u>	<u>15–30 <math>\mu\text{g}</math></u>
Add dd. $\text{H}_2\text{O}$ to a final volume of	0.5 ml

Mix well and slowly add the DNA mixture dropwise to 0.5 ml of well-suspended  $2\times$  HBS buffer with continuous mixing by vortexing. Incubate the mixture at room temperature for 30 to 45 min to allow coprecipitation to occur.

Note: *After the DNA mixture has been added to the  $2\times$  HBS buffer, the mixture should be slightly opaque as a result of the formation of fine coprecipitate particles of DNA with calcium phosphate.*


4. Slowly add the precipitated mixture dropwise to the dish containing the cells with continuous swirling of the plate. For each 100-mm dish, add 1 ml of the DNA mixture or 0.5 ml of the DNA mixture to each 60-mm dish.
5. Place the dishes in a culture incubator overnight at 37°C and provide 5% CO<sub>2</sub>.
6. Aspirate the medium and wash the monolayer once with 10 ml of serum-free Dulbecco's modified Eagle's medium (DMEM) medium and once with 10 ml of PBS. Add fresh culture medium and return the dishes to the incubator. In general, cells can be harvested 36 to 48 h after transfection for transient expression analysis.

### Reagents needed

- *10× HBS buffer*
  - 5.94% (w/v) HEPES [4-(2-hydroxyethyl)-1-piperazine ethanesulfonic acid], pH 7.2
  - 8.18% (w/v) NaCl
  - 0.2% (w/v) Na<sub>2</sub>HPO<sub>4</sub>
- *2× HBS buffer*
  - Dilute the 10× HBS in dd.H<sub>2</sub>O
  - Adjust the pH to 7.2 with 1 N NaOH solution.
- *DNA to be transferred*
  - Circular or linear recombinant DNA constructs in 50 µl of TE buffer, pH 7.5
- *2.5 M CaCl<sub>2</sub>*
- *DMEM culture medium*
  - Dissolve one bottle of DMEM powder in 800 ml dd.H<sub>2</sub>O; add 3.7 g NaHCO<sub>3</sub>; adjust the pH to 7.2 with 1 N HCl. Add dd.H<sub>2</sub>O to 1 l. Sterile filter the medium (do not autoclave) in a laminar flow hood. Aliquot the medium into 200- to 500-ml portions in sterile bottles. Add 10% to 20% FBS, depending on the particular cell type, to the culture medium. Store at 4°C.
- *PBS buffer*
  - 0.137 M NaCl
  - 4.3 mM Na<sub>2</sub>HPO<sub>4</sub>
  - 2.7 mM KCl
  - 1.47 mM KH<sub>2</sub>PO<sub>4</sub>
  - The final pH is 7.2 to 7.4
- *1× Trypsin–EDTA solution*
  - 0.05% (w/v) Trypsin
  - 0.53 mM EDTA, pH 7.6
  - Dissolve in PBS buffer, pH 7.4 to 7.6

## 22.7 ISOLATION OF TOTAL RNA FROM TRANSFECTED CELLS

Please see the protocol described in Chapter 20.



**FIGURE 22.4** Northern blot analysis of inhibition of target mRNA via siRNA. Lane 1: nontransfected cells; lane 2: cells transfected with vector without siRNA construct; lane 3: cells transfected with siRNA constructs.

## 22.8 ANALYSIS OF INHIBITION OF SPECIFIC mRNA VIA siRNAs BY NORTHERN BLOTTING

Once RNAs are isolated from the transfected and/or nontransfected cells, analysis of inhibition of target mRNA can be performed using northern blot hybridization or other methodologies. Details of the protocols for northern blot hybridization are described in Chapter 10. As shown in Figure 22.4, if siRNA experiment goes well, the target mRNA level in cells transfected with vector without hairpin siRNA oligonucleotide fragment should be similar to that in nontransfected cells, which serve as a control group. In contrast, the mRNA level in cells transfected with DNA construct containing hairpin siRNA oligonucleotide fragment should be significantly inhibited (approximately 70% to 90% reduction) compared to nontransfected cells as control. It should be noted that if the reduction level of the targeting mRNA is less than 30% of that in the control group, it may be necessary to optimize conditions so that siRNA effects can exceed 50%. It is recommended to simultaneously hybridize the membrane with both probe for target mRNA and probe for internal control, such as actin or GAPDH, that can serve to normalize the mRNA level of the target gene.

## 22.9 EXTRACTION OF PROTEINS FOR PROTEOMIC AND/OR REPORTER GENE ANALYSIS

### 22.9.1 ISOLATION OF PROTEINS FOR WESTERN BLOTTING

After aspiration of culture medium, cells can be lysed with 1 ml/100-mm Petri dish of lysis buffer (100 mM Tris, pH 6.8, 1% SDS, 5%  $\beta$ -mercaptoethanol). Overlay the entire dish and allow cells to lyse for approximately 5 min. Transfer the protein solution to a tube that is ready for protein concentration determination (see Chapter 11 for the detailed procedures<sup>7-8</sup>).



### 22.9.2 EXTRACTION OF PROTEINS FOR REPORTER ACTIVITY ASSAYS


For reporter gene activity assays, it is recommended to use a mild lysis buffer without detergents such as SDS and mercaptoethanol to preserve enzymatic activities. After aspiration of culture medium, add 1 ml/100-mm Petri dish of lysis buffer (e.g., 100 mM Tris, pH 7.0, 1.5% Triton 100-X, 0.5M urea) to dish. Overlay the entire surface of the dish with buffer, scrap the cells of the dish, and transfer the mixture into a tube. Allow the cells to lyse for approximately 1 to 2 h with shaking at 4°C. Proceed to determination of protein concentration (see Chapter 11 for detailed protocols).

### 22.10 ANALYSIS OF siRNA-MEDIATED INHIBITION OF GENE EXPRESSION AT PROTEOMIC LEVEL BY WESTERN BLOTTING


To characterize down-regulation of gene expression via siRNAs, it is recommended to use western blot hybridization, which not only provides information about the expression level of target protein but also reveals the molecular weight of the protein. Chapter 11 describes in detail the protocols for performing western blotting. Figure 22.5 illustrates the effects of siRNAs on a target protein. The protein levels in nontransfected cells and cells transfected with vector without siRNA-encoding oligonucleotides should be similar to each other. However, there is a significant reduction of protein in cells transfected with DNA constructs containing hairpin siRNA oligonucleotide fragment, indicating that siRNAs caused significant inhibition of target mRNA, which in turn led to a reduction in translation of the protein of interest because of insufficient mRNA template available.

### 22.11 REPORTER GENE ASSAYS OF DOWN-REGULATION OF GENE EXPRESSION VIA siRNAs

As illustrated in Figure 22.3, one may generate DNA constructs containing a reporter gene such as luciferase, green fluorescent protein (GFP) fused with the 3'-UTR of luciferase gene, and hairpin siRNA-encoding oligonucleotide fragment. Moreover,



**FIGURE 22.5** Western blot analysis of inhibition of protein of interest via siRNA. Lane 1: nontransfected cells; lane 2: cells transfected with vector without siRNA construct; lane 3: cells transfected with siRNA constructs.



**FIGURE 22.6** Analysis of gene expression by siRNA/reporter gene assays. Group A: cells transfected with control DNA construct (Luc-GFP-target gene without mismatch bases). Group B: cells transfected with control DNA construct (Luc-GFP-target gene with mismatch bases). Group C: cells cotransfected with control A construct (Luc-GFP-target gene without mismatch bases) plus siRNA constructs as illustrated in Figure 22.2. Group D: cells cotransfected with siRNA construct (Figure 22.2) plus control B construct (Luc-GFP-target gene 1 to 2 bases mismatch).

the hairpin siRNA oligonucleotide fragment may be manipulated as one or two bases mismatch as control. If all goes well, the mismatch control will not facilitate mRNA degradation via siRNAs. The strategy and the power of this type of construct are to provide rapid quantification of target protein using the reporter gene assay and/or fix the cells for confocal, fluorescent localization of the target protein in cells. Additionally, a beta-galactosidase is included in the vector, which will provide a tool for normalization of reporter gene assays downstream. For luciferase assays, commercial kits and the dual-light system (Applied Biosystem) may be used. As shown in Figure 22.6, luciferase activities in control groups (A and B) are very similar. However, cells cotransfected with control plasmid DNA and construct containing hairpin siRNA-encoding oligonucleotide fragment caused a significant reduction in luciferase (group C). Cells cotransfected with control plasmid with mismatch in the target region and DNA construct containing hairpin siRNA-encoding oligonucleotide fragment did not alter luciferase activity compared to groups A and B.

## REFERENCES

1. Amarzguioui, M., T. Holen, E. Babaie, and H. Prydz. 2003. Tolerance for mutations and chemical modification in siRNA. *Nucleic Acids Research* 31(2): 589–595.
2. Czauderna, F., M. Fechtner, H. Aygun, W. Arnold, A. Klippel, K. Giese, and J. Kaufmann. 2003. Functional studies of the PI(3)-kinase signalling pathway employing synthetic and expressed siRNA. *Nucleic Acids Research* 31(2): 670–682.
3. Randall, G., A. Grakoui, and C. M. Rice. 2003. Clearance of replicating hepatitis C virus replicon RNAs in cell culture by small interfering RNAs. *Proceedings of the National Academy of Sciences of the United States of America* 100(1): 235–240.

4. Qin, X. F., D. S. An, I. S. Chen, and D. Baltimore. 2003. Inhibiting HIV-1 infection in human T cells by lentiviral-mediated delivery of small interfering RNA against CCR5. *Proceedings of the National Academy of Sciences of the United States of America*, 100(1): 183–188.
5. Vickers, T. A., S. Koo, C. F. Bennett, S. T. Crooke, N. M. Dean, and B. F. Baker. 2002. Efficient reduction of target RNAs by siRNA and RNase H dependent antisense agents: A comparative analysis. *Journal of Biological Chemistry* 278: 7108–7118.
6. Couzin, J. 2002. Breakthrough of the year. *Science* 298(5602): 2283.
7. Wu, W. 1997. Analysis of gene expression at the RNA level. In *Methods in Gene Biotechnology*, ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang, 225–240. Boca Raton, FL: CRC Press.
8. Wu, W. 1997. Analysis of gene expression at the protein level. In *Methods in Gene Biotechnology*, ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang, 241–258. Boca Raton, FL: CRC Press.
9. Siegmund, D., P. Hadwiger, K. Pfizenmaier, H. P. Vornlocher, and H. Wajant. 2002. Selective inhibition of FLICE-like inhibitory protein expression with small interfering RNA oligonucleotides is sufficient to sensitize tumor cells for TRAIL-induced apoptosis. *Molecular Medicine* 8(11): 725–732.
10. Xu, Z., N. V. Kukekov, and L. A. Greene. 2003. POSH acts as a scaffold for a multi-protein complex that mediate JNK activation in apoptosis. *EMBO Journal* 22(2): 252–261.
11. Robert, M. F., S. Morin, N. Beaulieu, F. Gauthier, I. C. Chute, A. Barsalou, and A. R. MacLeod. 2003. DNMT1 is required to maintain CpG methylation and aberrant gene silencing in human cancer cells. *Nature Genetics* 33(1): 61–65.



---

# 23 Strategies for Gene Cloning, Expression, and Identification of Protein–Protein Interaction


## 23.1 INTRODUCTION

Protein–protein interactions have become an important research element of proteomics and functional genomics. Identification and characterization of binding proteins and transcription factors or cofactors have provided us a powerful approach to study and understand the mechanisms of regulation of gene express.<sup>1–5</sup> Initially, interaction among transcriptional factors was established from yeast two-hybrid screening systems. Recently, several methods and technologies have been developed for protein binding and/or interaction assays *in vitro* as well as *in vivo*. For example, coimmunoprecipitation (co-IP) assays using specific antibodies, fluorescence resonance energy transfer in living cells, and cutting edge technologies such as protein–antibody chips and DNA–protein chips can provide speedy and relatively large scales of identification and characterization of protein interaction partners.<sup>3–9</sup>

This chapter describes strategies for a relatively rapid cloning of cDNAs or genes of interest and for the expression and identification of protein binding partners using specific antibodies in co-IP, the widely used approach.<sup>10–13</sup> This chapter provides ideas and methods as outlined in Figure 23.1 (from hypothesis, testing, to verification).

## 23.2 RAPID AND HIGH-EFFICIENCY PCR-TA CLONING WITHOUT DNA LIGASE


Single 3'-thymidine (T) and a single deoxyadenosine (A) overhangs or TA cloning has been widely used for rapid cDNA or gene cloning and the expression and purification of proteins of interest. The principles underlying this technique are that a commercially available vector (i.e., TOPO vector from Invitrogen, Carlsbad, CA) was linearized with single 3'-T overhangs and PCR products driven by *Taq* polymerase has a single deoxyadenosine (A) overhang. *Taq* polymerase adds a single deoxyadenosine (A) to the 3' end of PCR products due to the polymerase nontemplate-dependent terminal transferase activity. Therefore, PCR products can be efficiently ligated to the vector based on T = A pairing without using traditional DNA ligase (Figure 23.2). The formation of bonds between hydroxyl and phosphate groups is driven by topoisomerase I during transformation.



**FIGURE 23.1** Diagram of procedures for cloning, identification, and mapping of the binding or interacting site between proteins of interest.

### 23.2.1 SELECTION OF CLONING VECTOR

Depending on one's research interest, a number of plasmid DNA vectors can be utilized for cloning and expression of proteins. Some vectors are commercially available. Appropriate vectors may also be requested from other research laboratories (in collaboration). We recommend PCR-TA cloning vectors (available from Invitrogen), which can speed up the procedures. Regardless of the type of vectors used, the critical elements should exist or be engineered in the vector, including protein detection



**FIGURE 23.2** T = A cloning and expression of PCR product. The protein of interest can be purified and/or detected using His tag or myc contained in the vector.

tag such as *myc* peptide and protein purification tag (i.e., 6xHis). The detailed diagram or vector map is shown in Figure 23.2.

### 23.2.2 PCR PRIMER DESIGN

Primer design is an important step for successful PCR cloning of cDNA or gene of interest. A couple of free or commercially available software (i.e., Lasergene) can be used for primer design. As shown in Figure 23.1, 5' PCR primer can be designed such that the PCR product will be cloned in the frame with the C terminus of *myc* in order to fuse the gene to the C terminus of *myc*.

*Note: It is imperative that there should be no stop codon between the gene or cDNA and myc and/or His tag. Do not add 5' phosphates to the primers for PCR. Otherwise, the PCR products cannot be efficiently cloned and fused with the vector or tags.*

### 23.2.3 PERFORMANCE OF PCR REACTIONS

Once primers, DNA template, PCR reagents, and thermocycler are available, turn on the PCR thermocycler and set up the reaction parameters according to the instructions.

- (1) Set up the PCR reaction in a thin-wall microtube as follows on ice.

10× PCR buffer	5 $\mu$ l
DTT (100 mM)	1.5 $\mu$ l
DNA or RNA template (i.e., 1 $\mu$ g/ $\mu$ l)	0.5 $\mu$ l
Forward primer (0.1 $\mu$ M/ $\mu$ l)	1 $\mu$ l
Reverse primer (0.1 $\mu$ M/ $\mu$ l)	1 $\mu$ l
dNTPs mixture (50 mM)	0.5 $\mu$ l
sterile water	40 $\mu$ l
<u>Taq polymerase mixture (2 unit/<math>\mu</math>l)</u>	<u>0.5 <math>\mu</math>l</u>
Total volume:	50 $\mu$ l

*Taq* polymerase mixture contains reverse transcriptase activity for reverse reaction in case RNA is used as a template. Detailed components are usually provided in commercial PCR kits.

- (2) Place the tube into the PCR thermocycler and proceed to PCR reaction according to the preset conditions.

For DNA template: 94°C, 4 min  $\rightarrow$  25 to 35 cycles (94°C, 1 min  $\rightarrow$  55°C, 1 min  $\rightarrow$  72°C, 3 min)  $\rightarrow$  72°C, 10 min.

For RNA template: 50 to 60°C, 60 min (this is the reverse transcription reaction)  $\rightarrow$  94°C, 4 min (denaturing DNA strands)  $\rightarrow$  25 to 35 cycles (94°C, 1 min for denaturing  $\rightarrow$  55°C, 1 min for primers and DNA annealing  $\rightarrow$  72°C, 3 min for primer extension)  $\rightarrow$  72°C, 10 min (extraextension to ensure all full-length PCR products and 3' adenylation of the PCR products).

*Note: Ten to 20 min of extension at the end of PCR cycles is recommended to ensure full-length and 3' adenylation of the PCR products. Extremely high proofreading Taq polymerase may not be good for 3' adenylation.*

- (3) Check the PCR products by 1% agarose gel electrophoresis. A strong band should be seen. If not, reset the PCR parameters and rerun PCR reactions, and/or purify the right size PCR band out of the gel if necessary. In our experience, the PCR reaction can be directly used for ligation without any purification. Proceed to TA cloning.

### 23.2.4 TA CLONING

As described previously, the vector contains T overhangs and the PCR products have A overhangs. The overhangs can facilitate ligation at the cloning site without the use of DNA ligase.

- (1) Set up TA cloning reaction on ice.

Salt solution (0.1 M NaCl <sub>2</sub> , 10 mM MgCl <sub>2</sub> )	1 $\mu$ l
PCR product	2 $\mu$ l
TA vector	1 $\mu$ l
Sterile water	6 $\mu$ l
Total volume:	10 $\mu$ l

- (2) Mix the reaction gently and incubate at room temperature for 5 to 7 min.  
 (3) Place the tube on ice and proceed to transformation.

### 23.2.5 TRANSFORMATION OF CHEMICALLY TREATED *E. COLI* ONE-SHOT TOP10 COMPETENT CELLS

Before transformation, place the SOC or LB medium without antibiotics at room temperature. Warm LB plates containing 0.1 mg/ml ampicillin to room temperature for 40 min and equilibrate a water bath to 42°C. Thaw one vial of TOP10 cells on ice.

- (1) Add 2 to 3  $\mu$ l of the TA cloning reaction prepared above into a vial containing 50 to 100  $\mu$ l of TOP10 chemically treated competent cells and mix gently. *Do not warm the tube by hands or at room temperature.*
- (2) Incubate the tube on ice for 30 to 40 min.
- (3) Quickly place the tube in the 42°C water bath for heat shock of the cells for 0.5 to 1 min without shaking.
- (4) Quickly place the tube on ice for 2 to 3 min.
- (5) Transfer the bacterial mixture into a tube containing 0.5 ml SOC or LB medium at room temperature.
- (6) Cap and place the tube in a shaker. Incubate the tube for 1 h at 250 rev/min at 37°C.
- (7) Spread 20 to 60  $\mu$ l of the transformation mixture on a prewarmed LB plate containing ampicillin. Cover, invert, and place the plate at 37°C overnight. *Colonies should be visible. Bacteria transformed with noncloned or linearized DNA will be eliminated by antibiotics such as ampicillin.* Proceed to preparation and purification of plasmid DNA as described in Chapter 4 (plasmid DNA purification kits are also commercially available).



### 23.2.6 CONFIRMATION OF DNA SEQUENCES OF COLONIES

Once plasmid DNA isolated from individual bacterial colonies is available, the DNA should be analyzed by sequencing. Some researchers analyze plasmid DNA by restriction enzyme digestion and agarose electrophoresis. We strongly recommend that DNA be sequenced and analyzed because the restriction enzyme pattern is not sufficient. Nowadays, DNA sequencing is rapid and relatively cheap. Almost all major universities in the United States have such facilities. Most importantly, the orientation and DNA sequence of the cloned cDNA or genes play a critical role in protein expression and interaction of interest. Any single nucleotide mutation, deletion, or addition in open reading frame (ORF) will result in incorrect proteins and/or protein interaction. Therefore, one may need to repeat sequencing. Based on the primer design, cloning vector map, and cDNA or gene of interest, carefully analyze the orientation, DNA sequences, and/or the restriction enzyme sites at the cloning site before proceeding to transfection of eukaryotic cell lines. Once the correct plasmid DNA are obtained, the correct bacterial colonies should be inoculated to 100 to 200 ml of LB medium containing antibiotics such as ampicillin; next, prepare and purify more plasmid DNA for transfection (plasmid DNA purification kits are commercially available). The bacterial aliquot should be stored at  $-80^{\circ}\text{C}$  freezer until use.

For appropriate buffers, solutions, and reagents, please see Chapters 3 and 4.

## 23.3 TRANSFECTION OF EUKARYOTIC CELLS FOR EXPRESSION OF PROTEINS OF INTEREST

There are different methods for transfection. We recommend that commercially available FuGene 6 reagent (Roche Applied Science) or Lipofectamine 2000 (Invitrogen) be used for a variety of cell lines.

### 23.3.1 USE OF FUGENE 6 REAGENT

1. One day before transfection (about 2:00 to 4:00 P.M.), grow cells in culture plates (6-, 12-, or 24-well) or culture dishes (35, 60, or 100 mm) with a plating density of approximately  $1 \times 10^5$  cells/35-mm dish containing 2 ml cell culture medium. Incubate the cells overnight at  $37^{\circ}\text{C}$ .
2. Next morning, label three Eppendorf tubes to indicate the different ratios of transfection: 3:1, 3:2, and 6:1. Add serum-free culture medium to the tubes (volume per 35-mm culture dish): 97  $\mu\text{l}$  (3:1), 97  $\mu\text{l}$  (3:2), and 94  $\mu\text{l}$  (6:1), respectively. Then, pipette the FuGene 6 reagent into the medium (do not touch the wall of the plastic tubes): 3  $\mu\text{l}$  (3:1), 3  $\mu\text{l}$  (3:2), and 6  $\mu\text{l}$  (6:1). Mix and incubate at room temperature for 5 min.
3. Add the purified plasmid DNA (1  $\mu\text{g}/\mu\text{l}$ ) to the tubes as follows: 1  $\mu\text{l}$  (3:1), 2  $\mu\text{l}$  (3:2), and 1  $\mu\text{l}$  (6:1). Mix well, cap, and incubate the tubes at room temperature for 25 to 40 min.
4. In the culture hood, add the incubated mixture to culture dishes or plates containing growing cells prepared the previous day, 100  $\mu\text{l}/\text{dish}$  (35 mm). Swirl the dish and place the dish into the incubator to allow the cells to

be transfected and cultured for 24 to 72 h, depending on the desired assay conditions. Proceed to protein extraction.

### 23.3.2 USE OF LIPOFECTAMINE 2000

1. One day before transfection (about 2:00 to 4:00 P.M.), grow cells in culture plates (6-, 12-, or 24-well) or culture dishes (35, 60, or 100 mm) with a plating density of approximately  $1 \times 10^5$  cells/35-mm dish containing 2 ml cell culture medium. Incubate the cells overnight at 37°C.
2. Next morning, add 1  $\mu$ g of the purified plasmid DNA (1  $\mu$ g/ $\mu$ l) to a tube containing 50  $\mu$ l/dish or plate of culture medium (serum-free) and mix well. Dilute an appropriate amount of Lipofectamine 2000 in 50  $\mu$ l/dish or plate serum-free medium, mix, and incubate the tubes at room temperature for 5 min.
3. In the culture hood, combine the diluted DNA and Lipofectamine and add the incubated mixture to culture dishes or plates containing growing cells prepared the previous day, 100  $\mu$ l/dish (35 mm). Swirl the dish then place it in the incubator to allow the cells to be transfected and cultured for 24 to 72 h, depending on the desired assay conditions. Please read the instructions on the reagents for detailed information. Proceed to protein extraction.

*Note: For protein–protein interaction experiments, it should be noted that two plasmid constructs (each with a particular cDNA or gene of interest) may be used for simultaneous cotransfection or sequential transfection.*

### 23.4 PROTEIN EXTRACTION

Unlike protein extracts directly subjected to SDS-PAGE and western blot analysis, proteins expressed for identification and analysis of protein–protein interaction or transcription factors or cofactors *cannot* be extracted from transfected cells using strong detergents such as SDS. Instead, the proteins should be extracted on ice using nonionic detergents (P-40, Triton X-100, or Nonidet P-40 or NP-40) and/or protease inhibitors in the lysis buffer to preserve the integrity of the interacted or bound proteins. The protein–protein complexes will be isolated from the protein extract by either co-IP using specific antibodies or commercially available affinity columns such as His tag. Hence, despite the hard work and effort entailed in these processes, protein extraction, purification, and analysis should be performed very carefully.

1. When the transfected cells are ready for harvest and protein extraction, rinse the cells twice briefly in serum-free culture medium and place the dish or plate on ice. Add 1 ml/dish (35 mm) lysis buffer, gently scrape the cells from the culture dish or plate, and allow lysis to occur on ice for 20 to 40 min.

*Lysis buffer: 150 mM NaCl, 50 mM Tris–HCl (pH 7.4), 10 mM MgCl<sub>2</sub>, 2 mM EDTA, 1% Triton X-100, 1 mM dithiothreitol (DTT), 2 mM  $\beta$ -glycerophosphate, and complete protease inhibitors (Roche Applied Science).*

2. Transfer the lysate into a tube and sonicate briefly ( $2 \times 15$  s on ice using a Soniprobe sonicator at 20% output, 40% duty cycle).
3. Incubate on ice for 15 to 30 min and centrifuge at 10,000 g for 25 min at 4°C.
4. Transfer the supernatant for immunoprecipitation (IP).

### 23.5 COIMMUNOPRECIPITATION


1. Place tubes on ice and set up co-IP as follows:
  - Tube #1 (for interactive protein A)
    - 50  $\mu$ l of the supernatant
    - 1 to 4  $\mu$ l of monoclonal antibody against protein A or
    - 10 to 15  $\mu$ l of polyclonal antibody against protein A
    - Mix well
  - Tube #2 (for interactive protein B)
    - 50  $\mu$ l of the supernatant
    - 1 to 4  $\mu$ l of monoclonal antibody against protein B or
    - 10 to 15  $\mu$ l of polyclonal antibody against protein B
    - Mix well
  - Tube #3 (as negative control)
    - 50  $\mu$ l of the supernatant
    - 30 to 40  $\mu$ l of pre-serum or normal serum
    - Mix well
2. Incubate on ice for 2 h with occasional agitation.
3. Add 5 to 7  $\mu$ l of protein G- or protein A-sepharose beads to each tube, gently mix, and incubate at 4°C for 45 to 60 min.
4. Centrifuge at approximately 100 to 500 g for 10 s and remove the supernatant.
5. Wash the pellet with 1 ml lysis buffer, gently resuspend, and centrifuge at 100 to 500 g and remove the supernatant.
6. Repeat step 5 twice.
7. Resuspend the pellet in 20 to 30  $\mu$ l of SDS-lysis buffer, boil the mixture for 5 min, and load 2 to 5  $\mu$ l per lane into SDS-PAGE for western blot analysis.

*SDS-lysis buffer: 50 mM Tris-HCl (pH 6.8), 2% SDS, 10 mM  $\beta$ -mercaptoethanol, 100 mM DTT, 20% glycerol, 0.001% bromphenol blue.*

*Recommendation: The concentration of antibodies against the interactive protein A or B should be predetermined or optimized for co-IP. For details on the method of SDS-PAGE western blotting, please refer to Chapter 11.*


### 23.6 ANALYSIS AND IDENTIFICATION OF BINDING PROTEINS

Based on the detected band(s) on western blots and initial cloning designs, the user should be able to analyze and identify whether the proteins of interest bind to or



**FIGURE 23.3** (a) Diagram of interaction between full-length proteins A and B. (b) Analysis and identification of interacted or bound protein A and protein B. Coimmunoprecipitated proteins were analyzed by SDS-PAGE followed by western blotting. Lane 1: protein markers. Lane 2: co-IP proteins with Ab1: antibody against the N-terminal region of full-length protein A. Lane 3: co-IP proteins with Ab3: antibody against the C-terminal region of full-length protein B. Lane 4: negative control.

interact with each other and in what region of the proteins. For example, as shown in Figure 23.3, full-length cDNAs or genes coding for the full-length of protein A and protein B were individually cloned as shown in Figure 23.2. The DNA constructs were cotransfected into cells (i.e., COS7, HeLa) and full-length proteins A and B were expressed. Protein A or protein B was coimmunoprecipitated by antibody 1 (Ab1: anti-N-terminal region of protein A) and antibody 3 (Ab3: anti-C-terminal region of protein B), respectively (Figure 23.3a). The immunoprecipitated proteins



**FIGURE 23.4** (a) Diagram of interaction between full-length protein A and N-terminal deletion protein B. (b) Analysis and identification of interacted or bound protein A and protein B. Coimmunoprecipitated proteins were analyzed by SDS-PAGE followed by western blotting. Lane 1: protein markers. Lane 2: co-IP proteins with Ab2: antibody against the C-terminal region of protein A. Lane 3: co-IP proteins with Ab4: antibody against the deleted N-terminal region of protein B. Lane 4: negative control.

were analyzed by western blotting. Based on the results shown in Figure 23.3b, either Ab1 or Ab3 can detect protein A and protein B (Figure 23.3b, lanes 2 to 3), indicating that proteins A and B bind to and/or interact with each other.

Furthermore, the binding or interacting regions of proteins A and B can be identified. As shown in Figure 23.4, the full-length cDNA or gene coding for protein A and the partial-length with N-terminal truncated cDNA or gene for protein B were separately cloned. The cells were cotransfected with the cDNAs or genes. The full length of protein A and partial length (mutant) protein B were expressed. The proteins A and B were coimmunoprecipitated with antibody 2 (Ab2: anti-C-terminal region of protein A) and antibody 4 (Ab4: anti-deleted N-terminal region of protein B), respectively (Figure 23.4a). Based on the western blot data, Ab2 detected both proteins A and B whereas Ab4 detected neither because of the deleted N-terminal region of protein B, which can be recognized by Ab4 (Figure 23.4b, lanes 2 to 3)—indicating that proteins A and B can bind to or interact with each other between the N-terminal region of protein A and the C-terminal region of protein B.

## 23.7 DIFFERENT STRATEGIES FOR CLONING, IDENTIFICATION, MAPPING, AND CHARACTERIZATION OF PROTEIN–PROTEIN INTERACTION

### 23.7.1 USE OF FLUORESCENT PROTEIN AS A FUSION TAG AND ANALYSIS BY FLUORESCENT MICROSCOPY

Some researchers clone and fuse proteins of interest with fluorescent proteins with different colors (i.e., RFP, CFP, YFP) and monitor the potential binding or interaction between the proteins of interest *in vitro* under a fluorescent microscope without using western blot analysis. We do not recommend this approach because of several drawbacks: (1) It is very difficult to quantify the fluorescent signals. (2) It is very difficult to conclude if binding has occurred. Even though two types of fluorescent signals are observed in the same cell, it is difficult to prove that bleaching has taken place regardless of the signal bleaching method used because the fluorescent signals are very dynamic. (3) Fluorescent proteins fused with the proteins of interest could affect the structures, folding, and/or binding of the proteins of interest. Therefore, we think that proteins of interest should be analyzed by western blotting and the data should be correlated with fluorescent observations.

### 23.7.2 CLONING AND EXPRESSION OF PROTEINS OF INTEREST WITH A DETECTION MINTAG

We highly recommend that a detection mintag (i.e., *myc* with approximately 10 to 11 amino acids) be fused with proteins of interest. This option offers several advantages. (1) *myc* is very small so one can easily design a fusion primer for cloning (*myc* epitope: GAA CAA AAA CTC ATC TCA GAA GAG GAT CTG). (2) Specific antibodies against *myc* are commercially available for western blot analysis and detection. (3) Because of its small fragment, *myc* can be fused at N-terminal, C-terminal,

or any region of the protein of interest. (4) In general, the overall charge of the *myc* amino acids does not affect the structures and/or binding properties of the fused proteins of interest.

### 23.7.3 HOW TO DESIGN, CLONE, AND MAP BINDING REGIONS OF PROTEINS OF INTEREST

If you want to test the hypothesis that protein A may bind and interact with protein B at their C-terminal regions and if there is no antibody available for detecting these two proteins, it may be necessary to carry out the following procedures.


Procedure 1. Design, clone, and confirm DNA sequences of different plasmid DNA constructs using the backbone of the vector shown in Figure 23.2 and express the different proteins as shown in Figure 23.5.

Procedure 2. Perform co-IP of each protein using an antibody against *myc* tag as described previously.


Procedure 3. Carry out western blot analysis as described previously.

Procedure 4. Analyze and map the binding site(s) between proteins A and B as shown in Figure 23.6.

If the hypothesis is correct and if all goes well, there should be binding between full-length proteins A and B and there is no binding or interaction between these two proteins if either of their C-terminal regions are deleted or sequence mutated.



**FIGURE 23.5** Diagram of designing, cloning, and expression for identification and mapping protein-protein interaction.



**FIGURE 23.6** Diagram of interaction between proteins A and B.

## 23.8 EXPLORING THE BIOLOGY OR POTENTIAL MECHANISMS OF THE INTERACTIVE PROTEINS

Having identified and mapped the binding or interacting regions between proteins of interest, it is highly recommended that research be conducted on the biological mechanisms of the proteins. For instance, if it is hypothesized that protein *X* interacting with protein *Y* can result in inhibition of the formation and/or progression of brain tumors in patients, experiments should be conducted using animal model to obtain some preliminary data that are important for your publications and grant applications.

## REFERENCES

1. Brown, D. A., and J. K. Rose. 1992. Sorting of GPI-anchored proteins to glycolipid-enriched membrane subdomains during transport to the apical cell surface. *Cell* 68: 533–544.
2. Pentek, J., L. Parker, A. Wu, and K. Arora. 2009. Follistatin preferentially antagonizes activin rather than BMP signaling in *Drosophila*. *Genesis* 47(4): 261–273.
3. Wu, W., and M. J. Welsh. 1996. Expression of HSP27 correlates with resistance to metal toxicity in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Applied Toxicology and Pharmacology* 141: 330–339.
4. Zhou, J., M. Liao, T. Hatta, M. Tanaka, X. Xuan, and K. Fujisaki. 2006. Identification of a follistatin-related protein from the tick *Haemaphysalis longicornis* and its effect on tick oviposition. *Gene* 10(372): 191–198.
5. Tsuchida, K., K. Y. Arai, Y. Kuramoto, N. Yamakawa, Y. Hasegawa, and H. Sugino. 2000. Identification and characterization of a novel follistatin-like protein as a binding protein for the TGF-beta family. *Journal of Biological Chemistry* 275(52): 40788–40796.
6. Nickel, J., M. K. Dreyer, T. Kirsch, and W. Sebald. 2001. The crystal structure of the BMP-2:BMPr-1A complex and the generation of BMP-2 antagonists. *Journal of Bone and Joint Surgery American Volume* 83-A Suppl 1(Pt 1): S7–S14.
7. Thompson, T. B., T. F. Lerch, R. W. Cook, T. K. Woodruff, and T. S. Jardetzky. 2005. The structure of the follistatin:activin complex reveals antagonism of both type I and type II receptor binding. *Developmental Cell* 9(4): 535–543.

8. Stamler, R., H. T. Keutmann, Y. Sidis, C. Kattamuri, A. Schneyer, and T. B. Thompson. 2008. The structure of FSTL3-activin A complex. Differential binding of N-terminal domains influences follistatin-type antagonist specificity. *Journal of Biological Chemistry* 283(47): 32831–32838.
9. Fazzini, M., G. Vallejo, A. Colman-Lerner, R. Trigo, S. Campo, J. L. Barañao, and P. E. Saragüeta. 2006. Transforming growth factor beta1 regulates follistatin mRNA expression during *in vitro* bovine granulosa cell differentiation. *Journal of Cellular Physiology* 207(1): 40–48.
10. Schnell, J. R., and J. J. Chou. 2008. Structure and mechanism of the M2 proton channel of influenza A virus. *Nature* 451: 591–595.
11. Kaiser, H. J., D. Lingwood, I. Levental, J. L. Sampaio, L. Kalvodova, L. Rajendran, and K. Simons. 2009. Order of lipid phases in model and plasma membranes. *Proceedings of the National Academy of Sciences of the United States of America* 106: 16645–16650.
12. Amarzguioui, M., T. Holen, E. Babaie, and H. Prydz. 2003. Tolerance for mutations and chemical modification in siRNA. *Nucleic Acids Research* 31(2): 589–595.
13. Robert, M. F., S. Morin, N. Beaulieu, F. Gauthier, I. C. Chute, A. Barsalou, and A. R. MacLeod. 2003. DNMT1 is required to maintain CpG methylation and aberrant gene silencing in human cancer cells. *Nature Genetics* 33(1): 61–65.



---

# 24 Conditional Gene Knockout

## 24.1 INTRODUCTION

Conditional gene knockout (CKO) is a new technique that allows researchers to conditionally knock out the expression of the gene of interest in specific cell-, tissue-, or organ-type and/or at specific development stages, namely, “temporal and spatial knockout,” which is particularly important when investigating the biology of some lethal genes. A lethal gene means that its expression during development can result in death of the animals bearing the lethal gene. Therefore, conditional gene knockout confers advantages over the conventional type in that genetically and conditionally modified mice are not only able to survive but also that these genes—to be scientifically precise—can be “turned on/off.”

The general principle of conditional gene knockout is the Cre–Lox recombination process.<sup>1–3</sup> Cre–Lox recombination, a unique type of site-specific recombination developed by Brian Sauer,<sup>1–2</sup> targets a specific DNA sequence or gene of interest, and splices it out with the help of Cre recombinase. The Cre (cyclization recombination) protein is a site-specific DNA recombinase that catalyzes the recombination of DNA between specific sites in DNA. These specific sites, known as *loxP* (locus of X-over P1, bacteriophage P1) sequences, contain specific Cre binding sites. The Cre surrounds a directional core sequence where recombination takes place. As such, when cells or tissues containing *loxP* sites in their genome express Cre, a recombination will occur between the *loxP* sites. The double-stranded DNA is cut at both *loxP* sites by the Cre recombinase and the strands are then rejoined by DNA ligase. Depending on the orientation of the *loxP* sites, there will be different possible results of recombination: (1) If two *loxP* sites on the same chromosome arm, (a) a direct repeat of *loxP* sites can cause a deletion event and (b) inverted *loxP* sites can cause an inversion. (2) If *loxP* sites are on different chromosomes, translocation events could occur catalyzed by Cre-induced recombination.

The Cre recombinase is a type I topoisomerase from bacteriophage P1 and catalyzes site-specific recombination of DNA between *loxP* sites. Cre recombinase is widely used to delete a segment of DNA or gene *flanked* by *LoxP* sites (known as “floxed”) in transgenic animals. The Cre recombinase consists of four subunits and two domains: the larger C-terminal domain and the smaller N-terminal domain. The protein has 343 amino acids. The C-terminal domain has a similar structure to the domain of the Integrase family of enzymes and is the catalytic site of the enzyme. *LoxP* is a site on the bacteriophage P1 consisting of 34 bp: an asymmetric 8 bp sequence flanked by two sets of palindromic 13-bp sequences: ATAACCTTCGTATA (13 bp)-GCATACAT (8 bp)-TATACGAAGTTAT (13 bp).

*Mechanism of the recombination of the Cre-loxP system.* During site-specific DNA recombination, genetic rearrangement will occur in processes such as viral integration and excision and chromosomal segregation. Cre recombinase recognizes specific DNA sequences and catalyses the reciprocal exchange of DNA strands between these sites. Initially, Cre recombinase recognizes and binds to each of the two recombination sites on the same DNA or two different DNA molecules. At the specific site on the DNA, the hydroxyl group of the tyrosine attacks a phosphate group in the DNA via direct transesterification mechanism linking the recombinase to the DNA by a phospho-tyrosine linkage. This conserves the energy of the phosphodiester bond so no high-energy cofactor is needed for the reaction. The tyrosine residue of the Cre recombinase is phosphorylated after the DNA strand is cleaved, generating a free 5' phosphate group. Thus, cleavage on the other strand also produces a phospho-tyrosine bond between the DNA and the Cre. The bonding of the phosphate group to tyrosine residues generates a free 3' OH group. The recombinase-DNA complex becomes an intermediate stage and then ligation occurs between the 3' OH group of one DNA strand and the 5' phosphate group of the other DNA strand, which is covalently bonded to the tyrosine residue. The reaction produces the so-called Holliday junction, where opposite DNA strands are joined together, followed by cleavage and rejoining and then DNA strands exchange their segments. As a result, the Cre-loxP system allows site-specific recombination to occur and results in the excision of the flanked gene or DNA fragment of interest from the genomic DNA.


Because Cre recombinase is known to be expressed only in a few or limited target cell or tissue types, depending on a specific promoter in a DNA construct, a specific gene knockout can be directed and controlled in the right place and at the right time. This system allows researchers to manipulate a variety of genetically modified organisms and control the expression of the gene of interest, delete undesired DNA sequences, and/or modify chromosome architecture. This chapter describes the procedures for generating conditional gene knockout DNA constructs and transgenic mice.

## 24.2 GENERATION OF CRE-LOXP DNA CONSTRUCTS

Generation of correct conditional gene knockout DNA construct will greatly impact on the success of transgenic animals. As outlined in Figure 24.1, there are several steps in producing CKO cassettes, and each step is relatively sophisticated and requires technical skills to perform. Depending on the availability of specific DNA fragments and vectors in a laboratory, the entire procedures can be divided into several steps.

### 24.2.1 SELECTION OF GENE OR EXON(S) OF INTEREST TO BE TARGETED

If cDNA or genomic DNA is available with known restriction enzyme cutting sites (i.e., exons 2 to 3 in gene X) in this example, one may carry out restriction enzyme digestion followed by purification or amplify the targeting region by PCR. If it is not available but the sequences are known, one may design specific primers flanking the targeting region and perform PCR using genomic DNA or RT-PCR using RNA. For detailed restriction enzyme digestion and PCR protocols, please refer to the



**FIGURE 24.1** Diagram of generation of gene conditional knockout (CKO) DNA constructs. (a) *loxP*-exons/gene-*loxP* or “flox” construct; BAC, bacterial artificial chromosome. (b) Cre-recombinase expression construct containing a promoter of interest (i.e., cell- or tissue-specific, developmental stage specific, inducible, or constitutive).

appropriate chapters in this book. If one prefers to generate CKO constructs using the RT-PCR approach, the standard protocols for isolation of RNA and RT-PCR are as follows.

### 24.2.1.1 Rapid Isolation of Total RNAs Using Trizol Reagent™

1. *From tissue.* Harvest tissue and immediately drop it in liquid nitrogen. Store at  $-80^{\circ}\text{C}$  until use. Homogenize 0.3 g tissue in 1 ml of Trizol reagent solution (Gibco BRL Life Technologies) using a polytron at top speed for three 30-s bursts. Allow the cells to be lysed/solublized for 5 min at room temperature. Proceed to step 2.

*From cultured cells grown in suspension culture or in a monolayer.* Collect  $1 \times 10^7$  cells in a sterile 50-ml polypropylene tube by centrifugation at 400 g for 5 min at  $4^{\circ}\text{C}$ . Wash the cell pellet with 25 ml of ice-cold, sterile  $1 \times$  PBS or serum-free medium (e.g., DMEM) and centrifuge at 400 g for 5 min at  $4^{\circ}\text{C}$ . Repeat washing and centrifugation once more to remove all traces of serum that contains RNases. Aspirate the supernatant and lyse the cells in 1 ml of Trizol reagent solution for 3 to 5 min at room temperature. Proceed to step 2.

Note: Isolation of RNAs can be scaled up using 0.3 g tissue or  $1 \times 10^7$  cells per 1 ml of Trizol reagent.

Caution: Trizol reagent contains phenol, which is toxic.

2. Add 0.2 ml of chloroform per 1 ml of the Trizol reagent used. Cap the tube and vigorously shake the tube for 20 s to shear genomic DNA. Incubate at room temperature for 3 min for phase separation.
3. Centrifuge at 12,000 *g* for 20 min at 4°C in an Eppendorf tube or at 7000 to 8000 rev/min for 30 to 40 min at 4°C using a 14-ml polypropylene tube in a swing-out rotor. Carefully transfer the top, aqueous phase to a fresh tube. Decant the bottom, phenol phase into a special container for disposal.
4. Add 1 ml of isopropanol, mix, and precipitate RNAs at -20°C for 2 h.
5. Centrifuge at 12,000 *g* for 15 min at 4°C. Briefly rinse the total RNA pellet with 1 ml of 75% ethanol. Partially dry the RNA pellet at room temperature for 15 min.
6. Dissolve the total RNAs in 20 to 50 µl of 0.1% SDS solution. Take 2 µl to measure the concentration with the spectrophotometer at 260 and 280 nm.

#### 24.2.1.2 Design of Primers for RT-PCR Using mRNA as Template


In general, exons encoding the core functional domain of the protein are selected to be targeted via CKO. As illustrated in Figure 24.2, assuming that exons 3 to 4 encode the domain of the protein X for brain tumor development, a pair of primers can be designed so that the forward primer (FP) anneals close to the upstream region (i.e., exon 2) of exon 3 and that the reverse primer (RP) will anneal to downstream (e.g., exon 5 region) of exon 4. Therefore, the RT-PCR product will contain exons 3 and 4, which will be utilized for generating the CKO construct.

#### 24.2.1.3 Performance of RT-PCR

##### 1. Assembly of RT-PCR reactions

Prepare the reaction mixture in an Eppendorf tube on ice as follows (i.e., 10 reactions):

dd.H <sub>2</sub> O	120 µl
dNTPs (10 mM each)	6 µl
DTT (100 mM)	20 µl
Target forward primer (20 µM)	10 µl
Target reverse primer (20 µM)	10 µl
Internal control forward primer (5 µM)	12 µl
Internal control reverse primer (5 µM)	12 µl
Reverse transcription buffer (5×)	50 µl
<u>Enzyme mixture</u>	<u>5 µl</u>
Total volume	245 µl



**FIGURE 24.2** Design of primers for RT-PCR using mRNA as template. E1 to E5: exons 1 to 5. Exons 3 and 4 to be targeted (CKO). FP, forward primer; RP, reverse primer.

Label thin-wall PCR tubes according to samples and place the tubes on ice.

Add 0.5  $\mu\text{l}$  of RNA sample (1  $\mu\text{g}/\mu\text{l}$ ) to the appropriate tube.

Transfer 24.5  $\mu\text{l}$  of the reaction mixture to each tube and mix well.

2. *Set up RT-PCR*

55°C, 50 min  $\rightarrow$  30 $\times$  (94°C, 30 s  $\rightarrow$  58°C, 30 s  $\rightarrow$  72°C, 1.5 min)  $\rightarrow$  72°C,  
7 min  $\rightarrow$  4°C, hold

3. *Analyze RT-PCR products using 1.2% agarose gel*

### 24.2.2 SELECTION OF CLONING VECTOR(S)

This may include vector(s) for initial genomic DNA cloning such as BAC (bacterial artificial chromosomes) and plasmid DNA vectors for subcloning (reporter genes such as *lacZ*, GFP, drug selection gene *neo<sup>r</sup>*, negative selection marker tk, *loxP* sites, Cre, etc.).

### 24.2.3 SELECTION OF PROMOTER FOR EXPRESSION OF CRE


This is an important part of the entire CKO. Depending on the specific research interest, the promoter controlling the expression of Cre recombinase may be cell-, tissue-, or organ-specific (e.g., brain, eyes, liver, kidney, etc.), developmental stage specific, or specific chemical or compound inducible (Figure 24.1b). This allows the user to conditionally target the gene of interest in temporal and spatial manner.

### 24.2.4 CLONING

As illustrated in Figure 24.1, *loxP-neo<sup>r</sup>* cassette and *neo<sup>r</sup>-loxP* cassette may be sequentially cloned on the left and right arms of the gene or exon(s) to be conditionally targeted.<sup>4-6</sup> For cloning or subcloning, please refer to the appropriate chapters in this book.

*It is highly recommended that DNA sequences from each step of cloning be verified by DNA sequencing because any mutation may negatively impact on the next procedure and the success of the entire process. As explained in the mechanisms of CKO, in order to delete or target the exon(s) of interest, it is imperative that both loxP sites be in the same direction (not inverted) and should flank the targeting region (in particular, targeting the intronic regions flanking the exon(s) of interest).*

In addition to the *loxP* site cassettes, depending on the availability, it may be necessary to separately generate a Cre cassette for the expression of Cre recombinase in transgenic mice. The conditional knockout vectors described here will generate an inducible reporter-null-conditional allele in transgenic mice. The mice containing the CKO alleles should be phenotypically normal until they are bred to a Cre recombinase-expressing transgenic mouse line.<sup>6-8</sup> Using a specific promoter (i.e., tissue-specific and/or development stage-specific, ubiquitous, inducible, or constitutive) controlling the expression of Cre recombinase, one may be able to direct and control the deletion of the *loxP* sites-flanked (“floxod”) exons or region in specific cell-, tissue-, or organ-type in a temporal and spatial manner. When Cre recombinase



**FIGURE 24.3** Diagram of *loxP*-Cre system for CKO. Cre recombinase binds to *loxP* sites flanking the exons to be targeted and cuts the flanked region between *loxP* sites.

is expressed in a specific cell or tissue, the enzyme binds to and cuts *loxP* sites flanking the targeting exons or gene of interest, splicing the exons or gene (Figure 24.3).

## 24.3 GENERATION OF TRANSGENIC MOUSE LINE CONTAINING *LOXP* CASSETTE, CRE CASSETTE, OR BOTH

Once the desired *loxP*-Cre system cassettes of interest are obtained, one can proceed to generation of three transgenic mouse lines: (A) mice containing Reporter Gene-*loxP*-targeting Exon(s)-*loxP* DNA cassette; (B) mice containing Specific Promoter-Cre DNA cassette; and (C) CKO mice containing both Reporter Gene-*loxP*-targeting Exon(s)-*loxP* and Specific Promoter-Cre DNA cassettes, also known as the *loxP*-Cre system. If all goes well, mouse lines A and B should display normal development, normal function(s), and normal phenotype. However, if mouse line A is allowed to be bred with mouse line B, the selected offspring, mouse line C, should contain the *loxP*-Cre system DNA cassette. Depending on the specific promoter with the Cre gene (e.g., a brain-specific promoter), the expression of Cre in the expected tissue(s) (e.g., brain) will bind to and cut the *loxP* sites flanking the targeted gene or exon(s) of interest, deleting or splicing the targeted gene or exon(s) that is usually the core functional domain of the targeted protein of interest. As a result, the recombined mutant gene with deleted exon(s) encodes a mutant or truncated protein that has lost its normal functions. Thus, the specific tissues (i.e., brain) may reveal unusual phenotype (i.e., tumor development). However, other tissues or organs function normally, generating CKO mice. On the other hand, if the promoter controlling the expression of Cre recombinase is nontissue-specific and constitutive, the Cre recombinase could express, cut, and splice *loxP* sites in all tissues in the mouse, which could be lethal during the development of the mouse. In general, this might not be an appropriate purpose for an investigator.

Generation of transgenic mice can be carried out by commercial services or university transgenic core facilities. If these services are not available nearby, one may refer to the following procedures.

There are two approaches to producing transgenic mice. One is to develop stably transfected mouse embryonic stem (ES) cells with: (A) Reporter Gene-*loxP*-targeting Exon(s)-*loxP* DNA cassette or (B) Specific Promoter-Cre DNA cassette.

Next, the ES cells can be injected into female mice to generate genetically altered mouse lines A or B, respectively. The other approach is to directly inject the DNA cassettes (A) or (B) into mouse oocytes by microinjection. The injected oocytes are then transferred into the oviduct of a female mouse to produce the transgenic mouse line A or B, respectively. If mouse line A is allowed to be bred with mouse line B, the offspring will contain both DNA cassettes, the *loxP*-Cre system, generating mouse line C.

### 24.3.1 METHOD 1. PRODUCTION OF TRANSGENIC MICE FROM STABLY TRANSFECTED OR MICROINJECTED ES CELLS

For transfection and selection of ES cells with DNA constructs, please refer to appropriate chapters in this book.

#### 24.3.1.1 Selection of C57BL/6J Estrous Females

The C57BL/6J mouse is a well-established strain and is widely used to host embryo for ES cell chimeras and germline transmission. The fact that these mice have a coat color that is different from 129 SVJ mice can be used as a coat color selection marker. In order to relatively synchronize the estrous cycle and simplify female selection, it is recommended that female mice be caged together without a male. Their estrous cycle is approximately 3 to 4 days and ovulation usually occurs at about the midpoint of the dark period in a light/dark cycle. This light-and-dark cycle can be altered to meet one's schedule. For example, the cycle may be adjusted to 14 h light and 10 h darkness. In this way, most strains of mice produce blastocysts that can be utilized for injection in the late morning of the third or fourth day. The question here is how to identify proestrous or estrous females for mating. The basic criteria are the external vaginal epithelial features. At the proestrous stage, the vaginal epithelium is usually moist, folded, pink/red, and swollen. At the estrous stage, the vaginal epithelium, in general, is dry but not wet, pink but not red or white, wrinkled on both upper and lower vaginal lips, and swollen. After the females have been caged for a while and have reached the predicted proestrous stage, they should be monitored on a daily basis. Once they are at the estrous stage, mating should be allowed to occur.

An alternative way to promote the estrous cycle is through hormonal regulation of ovulation with exogenous hormones. This procedure is termed superovulation. Injection of pregnant mice with mare serum gonadotropin (PMSG, Sigma) can stimulate and induce immature follicles to develop to the mature stage. Superovulation can be achieved by further administration of human chorionic gonadotropin (HCG, Sigma). The procedure is outlined as follows:

1. Three days or 72 to 75 h before mating, induce superovulation of 10–15 female mice (3–4 weeks old) by injecting 5 to 10 units PMSG intraperitoneally into each female between 9:00 A.M. and noon on day 1.
2. Two days or 48 to 50 h later, inject 5 to 10 units of HCG intraperitoneally into each female between 9:00 A.M. and noon on day 3. After injection, cage the females and allow them to mate with sterile males.

*Tip: Superovulation will occur about 12 h after HCG administration. The injection time at step (b) will coincide with the midpoint of the dark cycle.*

### 24.3.1.2 Preparation of a Bank of Sterile Males by Vasectomy

While females undergo their estrous cycle, prepare a stock of sterile males to mate with the estrous female chosen as the embryo transfer host so as to generate pseudo-pregnancy. The following procedures are recommended to be performed in as sterile conditions as possible.

1. Weigh a mouse and use 0.2 to 25 ml of tribromoethanol anesthesia to anesthetize the mouse. Swab the abdomen with 70% ethanol using cotton.
2. Lift the skin free of the peritoneum with forceps and carefully make a 1-cm transverse skin incision at approximately 1 cm rostra to the penis. Carefully make another similar incision through the peritoneum.
3. Use blunt forceps and reach laterally into the peritoneum and carefully grasp the testicular fat pad located ventral to the intestine and attached to the testis. Through the incision, gently pull out the pad together with the testis.
4. Distinguish the vas deferens from the corpus epididymis and carefully separate the vas deferens from the mesentery by inserting the closed tips of the iridectomy scissors through the mesentery. Next, open the scissors and leave the scissors at this position to support the isolation of a length of the vas deferens.
5. Insert two pieces of suture under the vas deferens with forceps, tie up the vas deferens, with forceps, at two sites approximately 2 cm apart, and cut out a piece of the vas deferens (about 1 cm in length) between the two knots.
6. Return the testis to the peritoneum and perform the same procedures on the other side.
7. Suture the peritoneal wall and clip the skin incision with a couple of small wound clips. Leave the vasectomized males for 10 to 14 days to clear the tract of viable sperm and make sure that the males are sterile before they are used for mating.

### Materials needed

- Small blunt, curved forceps
- Three pairs watchmaker's forceps
- Small sharp scissors
- Iridectomy scissors  
(These surgical instruments can be wrapped in foil and kept in a 120 to 140°C oven for at least 6 h before use).
- Surgical gloves
- Small wound clips
- Tribromoethanol anesthesia
- 70% ethanol and cotton
- Surgical silk suture and needle



### 24.3.1.3 Pairing of Estrous Females and Sterile Males

1. Once the estrous females and stud males are ready for mating, cage them together overnight.
2. Check for vaginal plugs in the morning on day 4 and record that this is the first day of pregnancy.

*Tips: If mating takes place, a white or yellow vaginal plug composed of male secretions from the vesicular and coagulating glands should be present within 12 h after mating. The plug may be visible at the surface or out of sight deep in the vagina. Therefore, a narrow, clean steel spatula or its equivalent (3 to 4 mm wide) may be used to detect the plug(s) in the vagina, which feel(s) harder compared with the surrounding soft tissue. Nonetheless, pseudopregnancy has been induced because the males are sterile.*

### 24.3.1.4 Preparation of Blastocyst-Stage Embryos from Pseudopregnant Mice

Approximately 4 days after the presence of vaginal plugs has been detected, blastocysts are usually present in the uterine lumen, which can be removed by flushing the uterine horns with embryo culture medium. Surgical gloves should be worn during the procedure.

1. Kill the pregnant females on the fourth day (84 to 96 h) of pregnancy by cervical dislocation.
2. Briefly clean the abdomen with 70% ethanol and make a small, transverse incision in the middle area of the abdomen. Remove the cut hairs with alcohol-soaked cotton.
3. At the incision site, tear the skin and pull it away to the front and hind legs, respectively. At this point, the peritoneum should be exposed.
4. Make a large, transverse incision in the peritoneum to expose the abdominal cavity.
5. Identify the reproductive tract by pushing aside the intestines and use blunt forceps to grasp the point of bifurcation of the uterus near the base of the bladder.
6. Carefully lift the uterus with blunt forceps, remove the supporting mesentery on both sides of the uterus, and cut across the cervix at the base.
7. Remove the entire tract by cutting it between the oviduct and the ovary and place the tract in a sterile Petri dish.
8. Under the low power of a dissecting microscope, carefully remove any mesentery and fat. At the utero-tubal junction site, cut off the oviduct and make an approximately 0.5 cm longitudinal clip at the end of each horn. Finally, cut across the cervix, exposing the entrances to both uterine horns.
9. Rinse the tract with embryo culture medium and place it in a sterile Petri dish. Take up 0.5 ml of the embryo culture medium using a small Pasteur pipette or a pipette attached to a sterile 1-ml tip, insert the tip into the cervical end, and gently flush the lumen a few times. The uterus should be

slightly inflated and the medium containing embryos should flow through the tract.

10. Under the low power of a dissecting microscope, quickly transfer the blastocyst-stage embryos that have settled to the bottom of the flush dish into a micromanipulation chamber or dish using a sterile Pasteur pipette or pipette tip.

### Materials needed

- Small blunt, curved forceps
- Watchmaker's forceps
- Small sharp scissors
- Iridectomy scissors
- Surgical gloves
- 70% ethanol and cotton
- *Embryo culture medium (1 l)*
  - 3.0 g  $\text{Na}_2\text{HPO}_4 \cdot 12\text{H}_2\text{O}$
  - 6.2 g NaCl
  - 0.2 g KCl
  - 0.2 g  $\text{KH}_2\text{PO}_4$
  - 0.1 g  $\text{CaCl}_2 \cdot 2\text{H}_2\text{O}$
  - 0.1 g  $\text{MgCl}_2$
  - 0.05 g Na pyruvate
  - 62 mg Penicillin
  - 1.04 g D-Glucose
  - 100 mg Phenol red

Dissolve well after each addition in 1000 ml distilled water. Add 10% (v/v) of heat-inactivated fetal calf serum to the medium. Filter-sterilize and aliquot before use. The medium can be stored at 4°C for up to 5 weeks.

#### 24.3.1.5 Preparation of Micromanipulation Apparatus

Micromanipulation can be set up with a micromanipulator system, including (1) an inverted microscope or a standard microscope (Leitz Instruments, Ltd.), (2) two sets of micromanipulators (Leitz Instruments Ltd.), (3) Kopf needle puller model 750 (David Kopf Instruments), (4) a finer needle and a pipette holder, and (5) a Schott-KL-1500 cold light source (Schott).

##### 1. Holding pipette

To hold and stabilize a blastocyst during the injection of ES cells, a holding pipette needs to be prepared as follows:

- (a) Pull out a length of glass capillary with a pipette puller according to the manufacturer's instructions or by hand over a low flame.
- (b) Break the pipette at a point of 70 to 90  $\mu\text{m}$  with a microforge according to the manufacturer's instructions. Fire-polish the tip of the pipette and close it down to a diameter of approximately 15  $\mu\text{m}$ . The pipette may

be further bent so that it can be placed horizontally in the microscope field.

2. *ES cell injection pipettes*

These pipettes will be used to inject ES cells into the blastocyst. The procedures are similar to those described for holding pipettes except that the tip should be broken off to generate about 12 to 15  $\mu\text{m}$  for ES cells to pass through. No fire polishing and bending is necessary.

3. *Blastocyst injection pipettes*

This type of pipette will be utilized to transfer blastocyst embryos for injection of ES cells into the embryos. The procedures are similar to those described for holding pipettes except that the tip should be broken off to generate a relatively large inside diameter (about 130  $\mu\text{m}$ ) for the blastocyst to pass through, and that fire polishing should be very brief to eliminate the sharp edges.

4. *Embryo transfer pipettes*

These pipettes will be used to transfer the blastocyst embryos containing the injected ES cells back to the uterus of the host. The procedures are similar into those described for holding pipettes except that the tip should be broken off to generate a relatively large inside diameter (about 130  $\mu\text{m}$ ) for the blastocyst to freely pass through, and that fire polishing should be very brief to eliminate the sharp edges.

#### 24.3.1.6 Injection of Stably Transfected ES Cells into Blastocysts

1. Set up a suitable schedule so that the ES cells may be trypsinized and gently suspend them to maintain them as a single cell suspension in embryo culture medium at 4°C before use. The blastocysts may be prepared in the morning.
2. Take up a tiny volume of light liquid paraffin (optional) by positive pressure and then take up blastocysts or ES cells into an embryo transfer pipette by capillary suction. Under the microscope, introduce the blastocysts into drops of embryo culture medium in a chamber, a dish, or a depression slide.
3. Assemble all parts that are necessary for the injection according to the manufacturer's instructions.
4. Position the pipette tips so that they are parallel in the field using the coarse adjustments of the manipulator. The holding pipette and ES cell injection pipette should be placed in opposite directions (e.g., north and south). Focus and place them in the same plane by making fine adjustments.
5. Carefully pull out the pipettes far enough to allow the introduction of a chamber, a dish, or a slide containing the blastocysts onto the stage.
6. Carefully reposition the pipettes and focus. Position and place the relatively dark side of the blastocysts in the center of the field, then carefully bring the ES cell pipette closer to the blastocyst.
7. Carefully insert the ES cell pipette and expel one to five ES cells into the blastocoelic cavity (relatively light part of the blastocyst). Slightly remove the ES cell pipette and place aside the injected blastocyst.
8. Repeat the procedure for other blastocysts.

### **24.3.1.7 Reimplantation of Injected Blastocysts into the Uterus of Recipient Females**

1. Prepare the third- or fourth-day pseudopregnant females as described above. It is recommended that these mice be prepared 1 day later than the mice prepared as the blastocyst donors.
2. Weigh and anesthetize a couple of females as described above.
3. Clean the back of a female with 70% ethanol and make an approximately 1-cm transverse incision in the skin in the area of the first lumbar vertebra. Clean the cut hairs with cotton wetted in alcohol.
4. Carefully slide the skin incision to both sides until the left ovarian fat pad and the ovary can be seen through the peritoneal wall.
5. Make a 4-mm incision through the peritoneum. Locate the ovary, oviduct, and uterus using blunt forceps. Grasp the fat pad and carefully pull it out together with the uterus through the opening.
6. Under a dissecting microscope, hold a pipette loaded with the embryos and a hypodermic needle in the right hand and carefully hold the uterus with forceps in the left hand. Insert the needle through the muscle layers of the uterus and position the needle parallel to the long axis of the uterus in order to allow the tip to enter the lumen.
7. Pull out the needle and insert the tip of the embryo transfer pipette through the hole made by the needle into the lumen of the uterus. Carefully expel all of the blastocysts into the lumen and remove the pipette. Bubbles should be avoided as much as possible.
8. Replace the uterus and perform the same procedure for the other side if bilateral transfer is necessary.
9. Seal the incision or close it with a small wound clip.
10. Recover the foster mothers by briefly warming them under an infrared lamp (do not overheat), and house two or three in one cage. Live offspring are usually born 18 days after the surgery. The initial offspring are called the founder animals or the FO animals in terms of genetics. The offspring can be allowed to breed to maintain the animals.

### **24.3.2 METHOD 2. PRODUCTION OF TRANSGENIC MICE FROM OOCYTES INJECTED WITH DNA CONSTRUCTS**

#### **24.3.2.1 Preparation of Oocytes**

1. Four days (94 to 96 h) before removing the eggs, induce superovulation of 10 to 15 three- to four-week-old female mice by injecting 5 units/female of pregnant mare's serum (PMS) as a stimulating hormone.
2. From 75 to 76 h after the injection of PMS, inject 5 units of HCG to each female. This injection should be administered 19 to 20 h before harvesting the eggs.
3. After the injection of HCG, cage the females with males overnight by maintaining them on a 12-h light/12-h dark cycle.
4. On the next morning, check the females for vaginal plugs. The mated females should have vaginal plugs within 24 h after mating.

5. Kill the superovulated females that have visible, vaginal plugs by cervical dislocation.
6. Clean the body surface with 70% ethanol, dissect the oviducts, and transfer them to disposable Petri dishes containing 30 ml of Medium A. Carefully transfer the oocytes from the oviducts to the medium.  
*Note: Under a dissecting microscope, the fertilized eggs can be identified as containing two nuclei, which are called pronuclei. The male pronucleus is bigger than that of the female pronucleus.*
7. Aspirate medium A, carefully transfer the oocytes to a fresh Petri dish, and incubate the oocytes with hyaluronidase for an appropriate period to remove the cumulus cells.
8. Rinse the oocytes extensively with four changes of medium A and carefully transfer the oocytes to a fresh Petri dish containing 10 to 30 ml of medium B. Place the dish in a 37°C incubator with 5% CO<sub>2</sub>.

### Reagents needed

- *Medium A*
  - 4.78 mM KCl
  - 94.66 mM NaCl
  - 1.19 mM KH<sub>2</sub>PO<sub>4</sub>
  - 1.19 mM MgSO<sub>4</sub>
  - 1.71 mM CaCl<sub>2</sub>
  - 4.15 mM NaHCO<sub>3</sub>
  - 23.38 mM Sodium lactate
  - 0.33 mM Sodium pyruvate
  - 5.56 mM Glucose
  - 20.85 mM HEPES, pH 7.4 (adjust with 0.2 N NaOH)
  - 4 g/l BSA
  - 100,000 units/l Penicillin G (potassium salt)
  - 50 mg/l Streptomycin sulfate
  - 10 mg/l Phenol Red
  - Dissolve well after each addition. Filter-sterilize and store at 4°C. Warm up the medium to 37°C before use.
- *Medium B*
  - 4.78 mM KCl
  - 94.66 mM NaCl
  - 1.71 mM CaCl<sub>2</sub>
  - 1.19 mM KH<sub>2</sub>PO<sub>4</sub>
  - 25 mM NaHCO<sub>3</sub>
  - 1.19 mM MgSO<sub>4</sub>
  - 23.38 mM Sodium lactate
  - 0.33 mM Sodium pyruvate
  - 5.56 mM Glucose
  - 4 g/l BSA
  - Penicillin G (potassium salt), 100,000 units/l

50 mg/l Streptomycin sulfate

10 mg/l Phenol Red

Dissolve well after each addition. Filter-sterilize and store at 4°C. Warm up to 37°C before use.

#### **24.3.2.2 Microinjection of DNA Constructs into Oocytes**

The equipment used for microinjection includes the following: (1) an injection microscope on a vibration-free table (Diaphot TMD microscope with Nomarski optics is available from Nikon Ltd); (2) an inverted microscope for setting up the injecting chamber, holding pipette, and needle (A SMZ-2B binocular microscope available from Leitz Instruments Co); (3) two sets of micromanipulators (Leitz Instruments, Ltd.); (4) Kopf needle puller model 750 (David Kopf Instruments); (5) a finer needle and a pipette holder; and (6) a Schott-KL-1500 cold light source (Schott).

1. Thoroughly clean a depression slide with Teepol-based detergent and rinse it extensively with tap water and distilled water. Rinse it with ethanol and air-dry. Add a drop of culture medium to the depression slide and a drop of liquid paraffin on the top of the medium drop.
2. Assemble all the parts necessary for the injection according to the manufacturer's instructions. Carry out a pretest of the procedure before injection of the DNA sample.
3. Carefully transfer the eggs into the medium drop using a handling pipette that can take up the cells by suction under the microscope.
4. Prepare microinjection needles with Kopf needle puller model 750. Slowly take up the DNA sample into the injection needle by capillary action.
5. Under the microscope, hold the suspended eggs with the holding pipette and use the micromanipulator to individually insert the needle into the male pronucleus, which is larger than the female pronucleus. Slowly inject the DNA sample into the pronucleus. The pressure can be maintained on the DNA sample in the needle by a syringe connected to the needle holder. As soon as swelling of the pronucleus occurs, immediately remove the needle a short distance from the cell. The volume injected is approximately 1 to 2 pl.
6. Transfer the injected eggs to one side and perform injections for the others. About 40 to 60 eggs can be injected in 1 to 2 h, depending on the individual's experience.
7. Transfer the injected eggs into a fresh dish containing medium B and place it in the incubator.

#### **24.3.2.3 Reimplantation of Injected Eggs into Recipient Female Mice and Generation of Founder Mice**

The injected eggs can be reimplanted into recipient female mice right after injection (one-cell stage embryo) or after being incubated in the incubator overnight (two-cell stage embryo). It is recommended that the injected eggs be transferred at the one-cell stage so that the introduced DNA integrates into chromosomes at the same site. Thus, all of the cells in transgenic animals contain the injected DNA. In general,

the introduced DNA integrates randomly at a single site. In some cases, however, multiple copies of DNA insertion may occur.

1. Prepare pseudopregnant females by caging four to eight females (6 to 9 weeks old) with vasectomized males (two females per male) on the day they are needed. Thus, the females will be in the correct hormonal stage to allow the introduced embryos to be implanted but none of their own eggs can form embryos. The pseudopregnant females can be distinguished by inspecting the vaginal area for swelling and moistness (see Section 24.3.1).
2. Carefully make a small incision in the body wall of a half-day of pseudopregnant female (e.g., C57B1/CBA F1), and gently pull out the ovary and oviduct from the incision. Hold the oviduct in place with a clip placed on the fat-pad attached to the ovary.
3. Under a binocular dissecting microscope, place the injected eggs or embryos into the infundibulum using a sterile glass transfer pipette. Generally, 10 to 15 injected eggs can be transferred into an oviduct.
4. Carefully place the oviduct and ovary back in place and seal the incision.
5. Recover the foster mothers by briefly warming them under an infrared lamp (do not overheat), and keep two or three in one cage. Live offspring are usually born 18 days after the surgery. These initial offspring are named the founder animals or FO animals in genetics parlance.
6. Allow the offspring to breed in order to maintain the transgenic mice.

#### **24.4 GENERATION AND CHARACTERIZATION OF STABLE TRANSGENIC MOUSE LINES A AND B**

The selected offspring mice are allowed to breed to produce genetically and stably altered mouse lines, heterozygous or homozygous. These mice need to be well characterized. Detailed protocols for isolation of DNA, RNA, extraction of proteins, and Southern blot, northern blot, and western blot hybridizations are described in Chapters 10, 11, and 15, respectively. If a phenotypic feature is altered (e.g., color of eyes, color of fur, size of head), it is relatively easy to identify those animals. Otherwise, the commonly used procedure is genotyping. Briefly, genomic DNA is isolated from mouse tail pieces and PCR is carried out using specific primers for amplifying the target exons or reporter gene, followed by agarose gel analysis of the PCR products.

If all goes well, the stably transgenic mouse line A should contain Reporter Gene–*loxP*-targeting Exon(s)-*loxP* DNA cassette; mouse line B should contain Specific Promoter–Cre DNA cassette.

#### **24.5 GENERATION AND CHARACTERIZATION OF TRANSGENIC MOUSE LINE C**

After mouse lines A and B are obtained, one may proceed to generation of mouse C by allowing the mouse line A to breed with the mouse line B at the time or

developmental stages of interest. If all goes well, the offspring should contain both the Reporter Gene-*loxP*-targeting Exon(s)-*loxP* DNA from the mouse line A and the Specific Promoter-Cre DNA from the mouse line B, also known as the *loxP*-Cre system, thus generating the CKO mice (assuming that the expression of the Cre and its action will not be lethal to the animals).


Depending on the particular research interest of an investigator, the mouse line C or the CKO mice can be analyzed in several aspects. For detail protocols, please refer to appropriate chapters in this book.

### 24.5.1 GENOTYPIC ANALYSIS

A common procedure is to isolate genomic DNA from the mouse tail or the killed mice and to perform PCR analysis using specific primers, which is also known as genotyping. For example, if a tissue-specific promoter (e.g., brain-specific) was used to control the expression of the Cre enzyme, the deleted or “floxod” exons or gene should not be detectable in the mouse brain of a successfully bred CKO mouse compared with other tissues of the mouse or with the mouse line A or B (Figure 24.4b).

### 24.5.2 FUNCTIONAL GENOME ANALYSIS

Based on genotyping data, the mRNA of interest should not contain the deleted region in the CKO mice. To obtain these data, one can isolate RNA from the CKO mice and perform RT-PCR using the same primers used in genotyping or other



**FIGURE 24.4** Analyses of transgenic mice. (a) Diagram of exons to be targeted. (b) Genotyping by PCR using genomic DNA from the mouse tail or other specific tissues. (c) RT-PCR analysis using RNA isolated from the specific tissue(s). Primers are specific to amplify the exons to be targeted in panel (a). Lane 1, CKO mouse brain (no band, a specific promoter used); lane 2, CKO mouse liver; lane 3, CKO mouse heart; lane 4, mouse line A brain as a control (with *loxP*-exons-*loxP* DNA); lane 5, mouse line A liver as a control; lane 6, mouse line B brain as a negative control (with Cre DNA but not *loxP*-exons-*loxP* DNA).



specific primers. In specific tissue(s) of interest, there should be no detectable “exon” region, meaning that the mRNA should be much shorter compared to other tissues of the same mouse (Figure 24.4c).

### 24.5.3 REPORTER GENE

Depending on specific reporter gene (e.g., lacZ, GFP) used in the DNA constructs, one can monitor under a fluorescent microscopy and/or assay the expression of the report gene using appropriate reagents.

### 24.5.4 IMMUNOSTAINING

Because the CKO mice contain the *loxP*–Cre DNA cassettes, depending on the specific promoter with the Cre gene (e.g., a brain-specific promoter), the expression of Cre in the expected tissue(s) (e.g., brain) will bind to and cut the *loxP* sites flanking the targeted gene or exon(s) of interest, deleting or splicing the targeted exons that encode the functional domain of the targeted protein of interest. Therefore, the resultant protein is a mutant or truncated protein that its size can be detected via western blotting using a specific antibody against the full-length protein of interest. The protein can also be detectable via immunostaining of tissue sections from the CKO mice using specific antibodies against the targeted or truncated region.

### 24.5.5 FUNCTIONAL AND PHENOTYPIC ANALYSES

This is the central data of the research. As noted previously, the conditional gene knockout will alter the function of the protein of interest. As a result, the CKO mice will display unusual phenotypic changes. Depending on the specific promoter used in the Cre DNA construct (i.e., brain-specific) and the possible role of the targeted gene/protein of interest (e.g., tumor development), the successful CKO mouse could have a bigger brain compared to wild-type or the mouse line A or B due to tumor development. This indicates that the protein truncated in the targeted region could be a causal factor for brain tumor formation in mice.

## REFERENCES

1. Sauer, B. 1987. Functional expression of the Cre–Lox site-specific recombination system in the yeast *Saccharomyces cerevisiae*. *Molecular and Cellular Biology* 7: 2087–2096.
2. Sauer, B., and N. Henderson. 1988. Site-specific DNA recombination in mammalian cells by the Cre recombinase of bacteriophage P1. *Proceedings of the National Academy of Sciences of the United States of America* 85: 5166–5170.
3. Wang, Y., J. Yang, H. Zheng, G. J. Tomasek, P. Zhang, P. E. McKeever, E. Y. Lee, and Y. Zhu. 2009. Expression of mutant p53 proteins implicates a lineage relationship between neural stem cells and malignant astrocytic glioma in a murine model. *Cancer Cell* 15: 514–526.
4. Datsenko, K. A., and B. L. Wanner. 2000. One-step inactivation of chromosomal genes in *Escherichia coli* K-12 using PCR products. *Proceedings of the National Academy of Sciences of the United States of America* 97: 6640–6645.

5. Wu, W. 2004. Subcloning of gene or DNA fragments. In *Gene Biotechnology*, ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang. Boca Raton, FL: CRC Press.
6. Wu, W. 2004. New strategies for gene knockout. In *Gene Biotechnology*, ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang. Boca Raton, FL: CRC Press.
7. Liu, P., N. A. Jenkins, and N. G. Copeland. 2003. A highly efficient recombineering-based method for generating conditional knockout mutations. *Genome Research* 13: 476–484.
8. Zhang, Y., F. Buchholz, J. P. Muyrers, and A. F. Stewart. 1998. A new logic for DNA engineering using recombination in *Escherichia coli*. *Nature Genetics* 20: 123–128.

---

# 25 How to Write a Research Manuscript for Publication in an English Journal

## 25.1 INTRODUCTION

After expending a tremendous amount of time and effort, hard work, and countless days and nights in research laboratories, your goal is to publish your research findings in a scientific journal.<sup>1-6</sup> Publications not only inform others about your work, they also demonstrate your achievements in science, which could serve as a key element in your career, especially in terms of job searching and promotion, obtaining research grants, and/or becoming well known in your field.


Writing a scientific manuscript mandates good ethics and good writing practice (GWP) and the skill of scientific and logical thinking. Although different authors have different writing skills and styles, the general process and format are more or less similar.<sup>5-10</sup> This chapter provides guidance, ideas, tips, advice, or comments on how to write a successful scientific manuscript and is designed for those who are interested in writing a manuscript in English for publication in journals (e.g., *Science*, *Nature*, *Cell*, *JBC*, etc., each with its own specific format and set of guidelines). The general outline and order can be listed as follows:

- Title
- Author(s) and affiliation
- Abstract (Summary in some journals)
- Introduction
- Materials and Methods
- Results
- Discussion
- Acknowledgment
- References

Where to start? It depends on the author's skills and preference. We recommend that one write Materials and Methods first, followed by Results, because this could be relatively easy. In particular, this is helpful for beginners. The writing order can be as follows:

- Title
- Author(s) and affiliation
- Materials and Methods
- Results
- Abstract or Summary
- Introduction
- Discussion
- Acknowledgments
- References

Nevertheless, while you are writing one section, you need to go back and forth to review and edit other parts or sections of the manuscript. Additionally, writing requires concentration and focus as well as a quiet environment. So closing your office door would be a good idea to avoid any form of disturbance. Writing is a long process and could be considered as a process of “brain cell consuming and regeneration.” As such, taking a break and having a cup of coffee every once in a while is very necessary to refresh your brain and/or recharge your “batteries,” resulting in clear and logical thinking to help you compose a well-written manuscript. Furthermore, whenever possible, it is imperative that you request other individuals, including coauthors, to read and comment on your manuscript. However, if there is a potential conflict of interest or some competition issues, then you should not let the person read your manuscript. The general outline and criteria are outlined in Figure 25.1.



**FIGURE 25.1** Diagram of preparation of manuscript, criteria, submission, reviewing, revision, resubmission, in press, and publication.

## 25.2 TITLE

Title may be described as the “face” of your manuscript. This is very important because it represents the entire manuscript. The title should be short, unique, and scientific but attractive to readers.<sup>6–12</sup> It may be difficult to judge whether a title is the best or “perfect,” but a good title should be interesting to readers and encourage them to read the entire paper. Different people may come up with different titles for the same manuscript. Hence, it may be imperative that the writer consult with others, coauthor(s) in particular, to decide the title for submission. Here are a few examples (just for illustration, not from published articles):

Deletion of gene X protects against HIV infection in patients  
 Deletion of gene X can protect patients against HIV infection  
 Targeted gene X protects human against HIV infection  
 Gene X causes HIV infection in patients  
 Gene X is discovered to be responsible for HIV infection in human  
 Gene X is responsible for HIV infection in human  
 Gene X causes HIV infection in human

## 25.3 AUTHORS AND AFFILIATION

Nowadays, a high-quality paper published in a highly ranked journal such as *Science*, *Nature*, and *Cell* usually has multiple authors because of the magnitude of research and collaborations. Therefore, the listing order of authors may be important. Although different professors or principle investigators (PIs) have different rules, the general guideline is based on each author’s contributions and may be determined by the PI of the laboratory.

The first author (sometimes there is a co-first author) is the person who contributed the most in terms of research and findings. In addition, the first author is responsible for writing the manuscript. Of course, it may not come as a surprise that in some laboratories, it is the first author’s PI—and not the first author himself/herself—who actually wrote the manuscript. Nevertheless, as a graduate student or post-doctoral fellow, you should learn how to write because your career depends on your writing skills. Reading is easy but writing is difficult.

The corresponding author may not contribute in laboratory experiments but he or she provides the funds for research in the laboratory. Hence, the corresponding author is usually the PI of the laboratory and is responsible for the approval of the manuscript and communicating with the editorial office and others in the field.

Affiliation refers to the work and communication addresses of the authors.

Note that a specific journal requires a specific format of listing authors’ names and this may be subject to change.

The following are a few examples (for illustration only):

- *Science*  
 Joseph Kaufman<sup>1</sup>, Lin Tang<sup>2</sup>, Richard Ensminger<sup>2</sup>, and Kim Hales<sup>1,\*</sup>  
<sup>1</sup>Department of Internal Medicine, University of xxx, Street name, City name, State name, zip code, Country.

<sup>2</sup>Department of Biology, University of yyy, Street name, City name, State name, zip code, Country.

\*To whom correspondence should be addressed. E-mail: xxx

- *Nature*

Joseph Kaufman<sup>1</sup>, Lin Tang<sup>2</sup>, Richard Ensminger<sup>2</sup> & Kim Hales<sup>1</sup>

1. Department of Internal Medicine, University of xxx, Street name, City name, State name, zip code, Country.

2. Department of Biology, University of xxx, Street name, City name, State name, zip code, Country.

Correspondence to: Kim Hales<sup>1</sup> (E-mail: xxx)

## 25.4 MATERIALS AND METHODS

There may be a number of materials and methods used in your research. However, only those directly related to and resulted in data for publication are included in the manuscript. Some authors prefer to write pages of Materials and Methods, including those that are nonrelevant. We think that nonrelevant materials and methods could dilute the quality of your manuscript. We recommend that the section of Materials and Methods should be short but complete and simple but repeatable by others in the field. To beginners and foreigners, pay attention to verb tenses (verb forms that indicate time): past tense, the present tense, and verb passive forms as well as singular and plural subjects, etc. Many mistakes or errors in grammar could have a negative impact on the review outcome of your manuscript. In general, experiments are described using verbs in past tense and in passive form.

Depending on the guidelines of a specific journal, some journals place Materials and Methods or Experimental Procedures in Supplemental Materials such as *Nature*, *Cancer Cell*, etc. A couple of illustrative examples of description of materials and methods or experimental procedures are listed below.

**Detection of mutant gene X<sup>ΔE2-3</sup> expression in gene X-deficient brain tumor by RT-PCR** To determine whether gene X deletion can cause tumor formation in transgenic mice, RT-PCR analyses were performed as previously described (Wilson *et al.*, 2009). Briefly, total RNA was isolated from gene X-deficient mouse brain tumor and wild type gene X mouse brain tissues. The RNA and primers (forward 5'-TGCAACGTCTAGGTTCAAC-3' and reverse 3'-CCTACGATCATGGCTTAC-5') were used in RT-PCR using Amplifer9600 (XYZ, CA). GAPDH primers were utilized as internal control. The RT-PCR products (approximately 1.2 Kb in wt or 0.3 Kb in gene X<sup>ΔE2-5</sup> brain tissues, N=5) were then analyzed using 1% agarose gel electrophoresis. RT-PCR analysis was repeated three times.

**Analysis of protein X in DNA-gene X transfected mouse embryonic stem (ES) cells by western blot** Mouse ES cells were transfected with DNA-gene X construct driven by CMV promoter or DNA vector as a control for 24 h (Tang *et al.*, 2008). Proteins were extracted from the control group and DNA-gene X transfected cells. The proteins were subjected to 10% SDS-PAGE using protein rainbow markers (XYZ, MA), followed by

transferred onto PVDF membrane (Wu *et al.*, 2005). The membrane was blocked in 5% nonfat dry milk and was incubated with monoclonal antibody (1:10 $\times$ ) against protein X (antibody kindly provided by Dr. xxx, University of xxx) at 4°C overnight with slow shaking. After washing and blocking, the membrane was incubated with peroxidase-conjugated secondary antibodies (1:25K dilution) at room temperature for 1 h. The membrane was washed and then subjected to detection and analysis.

**Detection of mutant gene X <sup>$\Delta$ E2-3</sup> positive cells in gene X-deficient brains by immunostaining** To localize the expression of gene X <sup>$\Delta$ E2-3</sup> in the mutant brain during tumor development, the brains were dissected and examined for enlargement from the gene X <sup>$\Delta$ E2-3</sup> mice at ages of 3, 4, and 5 months, respectively. The dissected tissues were processed for paraffin-embedded and serial 5  $\mu$ m paraffin sections were carried out. Serial sections were stained with antiprotein X exons 2 to 3 antibody and visualized with DAB staining under microscope xx (Louis *et al.*, 2010).

## 25.5 RESULTS

This is the core part or the main body of your manuscript. Compared with the other parts or sections of the manuscript, writing results takes the bulk of your time because this includes preparation, analysis, and editing of data in the form of tables, photographs, figures, diagrams, etc. Some of these procedures may need to be repeated many times. A full-length article to be submitted to *Science*, *Nature*, or *Cell* may require 5 to 10 figures plus tables and diagrams, which should be innovative and of high quality. Given the fact that the Results section consumes a tremendous amount of time and effort, we recommend that the author begin to sequentially prepare and save when individual experimental data or figures become available during research (“good habit”) instead of waiting for the last moment (“less good habit”). Naturally, the sequentially prepared results may need to be edited based on the guidelines of the journal to which the manuscript is being submitted. Nevertheless, “good habit” will speed up the process.

Different authors have different styles of presenting their results: data, figures, table(s), and diagram(s). Moreover, different journals have different requirements and formats for figures and other data. One figure may consist of multiple diagrams, a table, and a figure such as Figure 1: A (cloning diagram), B (fluorescent data), C (RT-PCR gel picture), D (genotype data), E (Southern blot figure), etc. Therefore, please refer to specific journal guidelines carefully. Nonetheless, the general guideline is that one should present important and solid data or figures that are scientific, original, repeatable, and convincing. It is important that nonrelevant or least important data or figures should not be included in the manuscript unless the reviewers specifically request for them. Also, pay attention to verb tenses (present, past, future, etc.), verb forms, and subjects (singular or plural), etc. In this section, if the results are scientific, solid, original, and repeatable, the presentation of conclusion(s) using verbs in the present tense may be appropriate. The subject “we” is quite often used (e.g., “We first performed RT-PCR analysis of brain tumors. . .,” “We investigated. . .,” “We demonstrated. . .”). The illustrative examples are as follows.

To determine whether mutant gene X can cause tumor formation in mice, we generated DNA construct, gene  $X^{\Delta E2-3}$ , for targeting the expression of gene X (Figure 2. A). We isolated genomic DNA from control mouse brain and mutant mouse brain with tumor and performed Southern blot analysis using exon 2 as probe ( $n=5$ ). We found that gene X was targeted in mutant mice (Lane 4, Figure 2 B). Moreover, RT-PCR confirmed that no detectable gene X mRNA expression was observed in mutant mice with brain tumor formation (Lane 3, Figure 2 C). These data demonstrated that targeted gene X is causal factor for tumor formation in mice.

Furthermore, we investigated protein-X level in positive mouse brain tissues and mutant gene  $X^{\Delta E2-3}$  in mouse brain tumor by western blot analysis and immunostaining using antibody against gene X exons 2 to 3. Western blot data revealed that there was no protein-X observed in mouse brain tumor targeted with mutant gene X (Lanes 3 and 4, Figure 3. A). Western blot data are consistent with immunostaining results (Figure 3. B). Taken together, these studies demonstrate that mutant gene  $X^{\Delta E2-3}$  can cause mouse brain tumor formation.

## 25.6 ABSTRACT (SUMMARY IN SOME JOURNALS)

Once you finish writing the results, the abstract is relatively easy. Abstract (some journals replace Abstract with Summary) is the maximum “zoom in” or concentration of the results. It is short (approximately several hundred words, one to two paragraphs) and conclusive. In general, when writing an abstract, one does not use verbs in the past tense or in passive form. The abstract should contain one or two sentences of logical introduction that led to your research (background, blank), your findings, any breakthrough and implication in the field, etc.

In short, the abstract plus the title can be considered as the “face and head” of the paper and should be interesting to readers. Usually, if a reader is interested in the title and/or abstract, he or she will read the entire paper. Below is just an illustrative example.

Recent studies have identified genes that are altered in patients with brain tumors. However, the mechanisms by which alterations of the gene are poorly understood. By targeting gene X in-frame deletion mutation to the brain tumor in mice, we find that deletion of exons 2–3 of gene X mutation induce brain tumor formation. Our data show that accumulation of mutant gene X proteins correlates with the progression of brain tumor in mice.

## 25.7 INTRODUCTION

The author should provide a sufficient research background in the field. In particular, recent studies that are related to your research should be logically introduced. Different authors use different styles in writing the Introduction. Nevertheless, the important criteria are as follows. What are previous findings? Who, when, where,



and how? What are blank points or areas? What are your hypotheses and research objective? How did you accomplish it? Below is an illustrative example.

Liver cancer is a leading death cancer in human. Recently, gene X caused liver cancer has been identified (Kaugam, *et al.*, 2001; Kim *et al.*, 2003).

...

More recently, we and others have identified gene X mutants in liver cancer tissues (Taq *et al.*, 2006; Wilson *et al.*, 2007). However, the mechanisms by which alterations of the gene are poorly understood. We hypothesized that the mutation of gene X may play a major role in the cancer development. Therefore, we generated gene X mutants by targeting the coding frame and produced transgenic mice. We found that deletion of exons 2–3 of gene X correlates with liver cancer development.

As for the citation of references, different journals have different requirements. The author(s) should read these instructions carefully.

## 25.8 DISCUSSION

In the Discussion section, you have an opportunity to elucidate your data, findings, implication of your data, and your future research focus and direction. This section could be relatively difficult for beginners and/or nonnative English speakers. It is recommended that the author read more articles written by native English experts and spend a little more time on this section. Some authors prefer to write a long (multiple pages) discussion. Others prefer a relatively short but sufficient section. We recommend the latter. The criteria for a good Discussion section are that it should be analytical, logical, and rational. You should focus on and elucidate your important results. How to explain and what do your data mean? What are the similarities or differences when compared with previous studies (cited references)? Why are there differences? What are your new findings and conclusion? What are the research and/or clinical implications of your findings? What areas and/or issues are still unknown and need further investigation? So long as you have addressed these questions, your Discussion should be sufficient. An illustrative example is shown below.

**A major role of gene X deficiency in brain tumor formation** We and others previously cloned and characterized gene X (Zhu *et al.*, 2003; Rilty *et al.*, 2004). This study demonstrates that deletion of exons 3–5 in gene Y can induce brain tumor formation in mice. Similar results were also reported in rats (Doetch *et al.*, 2005). In contrast, previous studies showed that wild type or deletion of exon 6 of gene X exhibited no evidence of tumor formation in the brain (Leng *et al.*, 2005).

...

Together, our results reveal a critical role of gene Y deficiency in brain tumor development in mice and indicate clinical implication in human with brain tumors. However, the specific mechanisms by which how gene-Y defi-

ciency signals and what pathway involved during brain tumor formation are not well understood. Furthermore, whether a single nucleotide mutations in exon 4 or 5 of gene Y needs further investigation, etc.

## 25.9 ACKNOWLEDGMENTS

This section provides the author(s) with an opportunity to appreciate those who are not coauthors but have helped in research and/or reviewed the manuscript. Below is an illustrative example:

We thank P. Williams and M. Kim for their technical assistance and Dr. E. Wilson for his critical review of this manuscript. This work is supported by grants from the National Institutes of Health (NIH, R01, NSxxx).

## 25.10 REFERENCES

In general, references refer to the papers or other articles that are related to the present research and manuscript. All the references listed in this section should be cited in the manuscript. All the references cited should be relevant. It would be a mistake to believe that the more references listed, the better the manuscript is.

Author(s) should pay attention to the specific reference format of a specific journal because different journals (e.g., *Science*, *Nature*, *Cell*, *JBC*) have different formatting requirements, including authors' names, journal issues, volume and issue numbers, pages, year, book chapters, etc. Some journals do not require the article title. Therefore, read the instructions carefully while writing your manuscript. In addition, some commercially available software can quickly assemble references based on a specific journal format, which can speed up your preparation.

## 25.11 ADJUSTMENT OF FORMAT OF MANUSCRIPT

At this point, you are almost finished with your manuscript. However, it is not done yet and it is just a draft. As mentioned above, the format and the order of sections during writing may not be the same as that required by a specific journal. Hence, the author should adjust the format accordingly.

For example:

Title and authors page  
Abstract or Summary  
Introduction  
Materials and Methods  
Results  
Discussion  
Acknowledgments  
References

## 25.12 FINE-TUNING AND SUBMISSION OF MANUSCRIPT

This is an important process. Before submission, we highly recommend that the manuscript be read or reviewed by coauthors or other experts in the field, and that the author make appropriate changes based on comments from others, including spelling and grammar check. After fine-tuning, you may submit your work electronically or by mail according to the instructions of a specific journal.

In summary, the entire process of writing and submitting of the manuscript is outlined in Figure 24.1.

## 25.13 SOME OBSERVATIONS ON TO WHICH JOURNAL TO SUBMIT YOUR MANUSCRIPT

Certainly, it is almost every author's hope to publish his or her paper in top-tier, highly prestigious journals such as *Science*, *Nature*, *Cell*, etc. Unfortunately, this is impossible for everyone or for all the papers penned by the same author(s). Therefore, the authors should be rational when deciding where to send their work. For example, *Science* requires new research findings that are not only innovative and breakthrough but are of general interest to the public. For instance, if you discovered a gene that can increase the survival percentage of patients with kidney cancer, your paper may not be published in *Science* but could be more likely published in *Nature* or *Cancer Research*. However, if you discovered a gene that can cure HIV patients, once and for all, your finding could have a great chance to be published in *Science* or *Nature*.

Nevertheless, one should have the right to try. If you believe that your paper can be published in *JBC*, you could try *Cell* first. If you think that your paper can be published in *Cell*, you may try *Nature* first. Where to submit is your decision. Some journals such as *Science* require recommendation from several experts' support letters for submitting a manuscript. If some experts refuse to recommend (except for potential conflict of interest or competition if any) the manuscript, you know that your paper may not be qualified to be published in the desired journal.

## 25.14 WAITING FOR REVIEWERS' COMMENTS, REVISION OF MANUSCRIPT BASED ON REVIEWERS' CRITIQUE, AND RESUBMISSION OF MANUSCRIPT

After you have submitted your manuscript to a specific journal, the editorial office will send it to reviewers (usually three) based on a quick review of the manuscript. It will take a relatively long time (1 to 3 months) to receive the reviewed comments from the editorial office. Reviewers' names are usually not disclosed but you have opportunity to read all the comments. In general, if only some minor revisions or editorial revision is required, you are lucky. In some cases, a severe critique can lead to more experiments; you may have to do so if you hope to publish in that journal. In some cases, a manuscript can be completely rejected without a chance for resubmission to that particular journal. This is a very disappointing moment and you need to calm down and analyze the manuscript carefully. Perhaps your data are not strong

enough or the research findings are not suitable for that journal. In rare cases, a reviewer may not be from your field and could not understand your research, or there could be a conflict of interest and/or competition in the field. If this were the case and you believe that your findings are solid and strong, you should communicate with the editor or editor-in-chief directly.

As shown in Figure 24.1, after revision, you should submit your manuscript as soon as possible. If your revision satisfies the reviewers and/or editor(s), the manuscript will be accepted for publication. At this point, you may cite your paper “in press.” Congratulations! (You may now update your publication record and your resume.)

## REFERENCES

1. Brown, D. A., and J. K. Rose. 1992. Sorting of GPI-anchored proteins to glycolipid-enriched membrane subdomains during transport to the apical cell surface. *Cell* 68: 533–544.
2. Schnell, J. R., and J. J. Chou. 2008. Structure and mechanism of the M2 proton channel of influenza A virus. *Nature* 451: 591–595.
3. Bruce, E. A., P. Digard, and A. D. Stuart. 2010. The rab11 pathway is required for influenza A virus budding and filament formation. *Journal of Virology* 84: 5848–5859.
4. Kaiser, H. J., D. Lingwood, I. Levental, J. L. Sampaio, L. Kalvodova, L. Rajendran, and K. Simons. 2009. Order of lipid phases in model and plasma membranes. *Proceedings of the National Academy of Sciences of the United States of America* 106: 16645–16650.
5. Ma, C., A. L. Polishchuk, Y. Ohigashi, A. L. Stouffer, A. Schon, E. Magavern, X. Jing, J. D. Lear, E. Freire, and R. A. Lamb. 2009. Identification of the functional core of the influenza A virus A/M2 proton-selective ion channel. *Proceedings of the National Academy of Sciences of the United States of America* 106: 12283–12288.
6. Pinto, L. H., and R. A. Lamb. 2006. The M2 proton channels of influenza A and B viruses. *Journal of Biological Chemistry* 281: 8997–9000.
7. Wu, W., and M. J. Welsh. 1996. Expression of HSP27 correlates with resistance to metal toxicity in mouse embryonic stem cells transfected with sense or antisense HSP27 cDNA. *Applied Toxicology and Pharmacology* 141: 330–339.
8. Romer, W., L. L. Pontani, B. Sorre, C. Rentero, L. Berland, V. Chambon, C. Lamaze, P. Bassereau, C. Sykes, and K. Gaus. 2010. Actin dynamics drive membrane reorganization and scission in clathrin-independent endocytosis. *Cell* 140: 540–553.
9. Amarzguioui, M., T. Holen, E. Babaie, and H. Prydz. 2003. Tolerance for mutations and chemical modification in siRNA. *Nucleic Acids Research* 31(2): 589–595.
10. Randall, G., A. Grakoui, and C. M. Rice. 2003. Clearance of replicating hepatitis C virus replicon RNAs in cell culture by small interfering RNAs. *Proceedings of the National Academy of Sciences of the United States of America* 100(1): 235–240.
11. Vickers, T. A., S. Koo, C. F. Bennett, S. T. Crooke, N. M. Dean, and B. F. Baker. 2002. Efficient reduction of target RNAs by siRNA and RNase H dependent antisense agents: A comparative analysis. *Journal of Biological Chemistry* 278: 7108–7118.
12. Robert, M. F., S. Morin, N. Beaulieu, F. Gauthier, I. C. Chute, A. Barsalou, and A. R. MacLeod. 2003. DNMT1 is required to maintain CpG methylation and aberrant gene silencing in human cancer cells. *Nature Genetics* 33(1): 61–65.

---

# 26 How to Protect Your Discovery and Invention *Patent 101*

## 26.1 INTRODUCTION

It has been demonstrated that research involving gene biotechnologies can result in discoveries, intellectual properties (IPs), and inventions. Protection of IPs by patents has become increasingly important in biotechnological, biomedical, pharmaceutical, and other industrial fields.<sup>1-2</sup> However, researchers in the academic setting generally focus on their research for paper publications but not on patent(s). Why? There are two major factors. One is that some academic researchers may lack knowledge in terms of inventions and patents. The other is that most academic researchers are pure science research-oriented and hence they are particularly interested in research publications but not in inventions and/or patents. Nevertheless, recently a number of new biotechnology firms established with inventions from universities have changed some academic researchers' focus and interest. What are intellectual properties? What is invention? How do you protect your IPs and/or invention? This chapter describes and provides some basic tools or guidelines on these topics—basically Patent 101. For detailed information and procedures, please consult with appropriate legal services.

## 26.2 RESEARCH DISCOVERIES VS. IPS, INVENTION

One common question is, “How do I know if my research results are just pure science-related discoveries or have some IP potentials?” First, if the methods, techniques, and/or procedures used in your research have been published by others (nothing of your own or new), you do not have IP claims for methodologies and/or procedures. Second, if your research results just showed some natural similarities and differences compared with other reports in the same areas but have no obvious novel creation, no new breakthroughs, or commercial potential, then your research may just be pure, natural science-related and may not have any IP claims for your findings.<sup>3-5</sup> Therefore, the major criteria for claiming IPs and/or invention include, but are not limited to:

1. One's conception ideas for new methods, technologies, procedures, and applications.
2. One's own intellectual creations: (a) novel method, technology, or process; (b) obviously improved methodology, technique, or procedure; (c) novel or obviously improved formations of a compound; (d) recombinant cDNAs,

genes, peptides, or proteins but not the natural forms of the genes, cDNAs, or proteins; (e) novel gene expression and detection technology and platform, (f) novel compound or drug; (g) novel animal models, etc.

3. Novel research breakthrough findings with clinical or medical and/or commercial applications: for example, if one created a recombinant, novel peptide or protein, or compound and preclinical research results showed its potential for cure or life extension in patients with prostate cancer by blocking the key enzyme X and/or by killing cancer cells, the creator should immediately proceed to IP claims and protection by patents.

### 26.3 IP OR INVENTION DOCUMENTATION

When you have new idea or plan to pursue an invention, the first and most important step is to document your novel conception in a notebook and/or computer file: (1) What? (describing your new idea and for what purpose), (2) When? (date, year), (3) Where? (place), (4) Who? (witness), (5) Signatures (yours and that of the witness), and (6) Confidentiality (advise everyone involved including the witness not to tell anyone without consulting legal services). Having documented your idea(s), you should conduct a brief patent database search using key words or phrases (e.g., United States Patent and Trademark Office [USPTO], [www.USPTO.gov](http://www.USPTO.gov), or database from other countries). This is very important because if your idea for an invention is already in the database, then your idea is not novel and cannot be patented. However, if your idea cannot be found in the database (of course, preliminary database search may not be sufficient because some data such as provisional patent applications may not be available to the public), proceed to Technology Disclosure (the official document) with the appropriate legal services.

### 26.4 TECHNOLOGY DISCLOSURE

Technology disclosure can be considered the first official document of the legal service for the initiation of the patent process. Different universities or organizations may have different format of technology disclosure forms. In general, the form should cover the following information (this example is just for illustrative purposes):

1. Title of Invention  
(e.g., Methods and Reagents for Killing Prostate Cancer Cells and Utilities)
2. Brief Description of the Invention
3. Contributors/Inventors  
Information includes: name, contribution %, citizenship, organization, address, and contact information, etc.)
4. Funding Source for the Invention
5. Publication Date (any abstract, manuscript, or presentation slides made public, when and where?, etc.)
6. Commercial Potential/Potential Licensees
7. Declaration

(e.g., We certify that all of the information provided herein is complete and accurate to the best of our knowledge. . . . Signature and date.)

Note that the declaration is the most important statement. As emphasized previously, unlike research paper for publication, technology disclosure followed by patent application will have legal consequences. If the idea is not yours or you did not tell the truth about the technology, you need to be very careful because you may be legally held liable in the future; this includes potential lawsuits, which could be very bad for you financially and/or professionally.

8. Witness (signature and date)

Other information includes File # and date of receipt by the legal service.

Having filed the Technology Disclosure, the legal office will offer some legal advice, review the disclosure, laboratory notebooks, electronic files, and conduct brief patent database search. The patent lawyer will then provide the inventor(s) with a legal opinion regarding the patentability of your invention.

Legal advice may include, but is not limited to, the following:

- (a) As required by patent laws, document and keep all notebooks, laboratory data, results, electronic files, and emails related to the invention with signatures and date.
- (b) Keep the legal service updated/informed about the progress of the invention.
- (c) Do not disclose or publish the invention without permission from the legal service.
- (d) If permitted, the information used for any communications or presentations should be labeled “confidential” or “patent application in process.”

Proceed to Provisional Application for Patent.

## 26.5 PROVISIONAL APPLICATION FOR PATENT

After filing Technology Disclosure to the legal services, if your invention is still in the developmental stages (i.e., experimental process in general) and in order to protect your IP/invention, the legal services may first submit a Provisional Application for Patent in the USPTO before filing a full patent application. In USPTO, a provisional patent application will not be examined for patentability, will not be eligible for pre-grant publication, and will lose its applicability 12 months after its filing date. The advantage of filing a provisional patent application is to protect and prevent potential leaking/infringement of the invention by others. In some countries or regions, if there is no provisional patent application, whoever invented first will be granted the patent (e.g., United States); in other countries, whoever filed the application first may be granted the patent. For instance, two separate individuals have the same or very similar inventions: one initiated the invention earlier but completed and filed the invention later than the other person. In the United States, the person who initiated the invention earlier will be granted the patent (this is the so-called *who*

*invented it first*). In contrast, in some countries, the person who started the invention later but completed and filed the patent application earlier may be granted the patent (this is the so-called *who filed first*).

A provisional application for patent is a much shorter form of the full-length patent application. It covers the title of invention, inventor(s) and address, abstract, or description of the invention, a couple of examples if any, major claims, and brief references. It is very similar to its technology disclosure. If a legal service is not available, you may write and submit it by yourself with the USPTO cover sheet and fee.

Proceed to the Full-Length Patent Application.

## 26.6 FULL-LENGTH OR COMPLETE PATENT APPLICATION

Unlike a provisional patent application, it is highly recommended that the full-length patent application be written and/or processed by the legal services because, unlike research paper manuscripts for publication, patent—by definition—is a legal issue governed by patent laws. Of course, if a patent application is handled by an attorney, the fee is not cheap. Nevertheless, the inventor may negotiate with a patent lawyer or legal services to reduce the costs by taking the following option: (1) the draft of patent application to be written by the inventor; (2) the draft to be reviewed and edited by a patent lawyer or appropriate legal services; and (3) the final patent application to be submitted by the patent lawyer.

A full-length patent application should be written in the format of two columns per page, double spaced. The complete patent application should consist of, but not limited to, the following contents:

- Title
- Inventor(s)
- Assignee
- Abstract
- Background of the Invention
- Summary of the Invention
- Brief Description of the Drawings and Figures
- Description of Illustrative Embodiments
- References
- Claims of the Invention

### 26.6.1 TITLE

Unlike a research paper, the title of the invention should be very short and should reveal the potential commercial uses and/or values of the invention. An illustrative example: “A Method and Reagents for Killing Prostate Cancer Cells.”

### 26.6.2 INVENTOR(S)

It is imperative that one understand the major difference between the inventor(s) of a patent and the author(s) of a research paper. For the publication of a research paper,



all individuals who have contributed or are involved in research with or without data can be listed as the coauthors of the paper. However, based on the patent laws, an inventor: (1) shall directly contribute to the initial idea of the invention (namely, conception idea), (2) shall design and execute experiments (know how or reduce to practice), or (3) shall contribute to strategy changes during the procedures to make the invention work (ideas and reduce to practice). If a person merely carried out experiments to obtain data without idea or strategy contributions, he or she cannot be considered the inventor of the patent but can be a coauthor of a research paper relating to the invention or technology.

The inventor's citizenship, address, country, and contact information should be included in the patent application.

### **26.6.3 ASSIGNEE**

Assignee refers to the university or organization that provided the funds and facilities for the invention (e.g., Harvard University, Cambridge, MA, USA; Apple Inc., Cupertino, CA, USA). Therefore, the assignee is the owner of the patent but an inventor does not have any ownership of the patent unless the inventor and assignee is the same person.

### **26.6.4 ABSTRACT**

The abstract should be short and conclusive and should show the invention's commercial potential. Below is an illustrative example:

The present invention is a general method for killing prostate cancer cells.

The cancer cells are treated with reagents xxx coupled with xxx. . . . This method may be applied to treatment of patients with prostate cancer and may also be applied to a variety of cancer cells in patients.

### **26.6.5 BACKGROUND OF INVENTION**

Similar to the introduction section of a research paper, the background of the invention should cover: (1) Field of the invention, (2) Description of Related Art or Prior Art, and (3) Disadvantages of Prior Art and Advantages of the Invention. It is recommended that one refer to some well-written patents in the similar field, which are available from patent databases.

Field of the invention is specific. For example, the present invention relates generally to the field of treatment of patients with cancers. More particularly, it concerns the inactivation of prostate cancer cells.

Description of related art should cite and discuss previous studies and/or invention. These include, but are not limited to: (1) references related to the method(s) or procedures of the present invention; (2) reagents or compounds related to the present invention; (3) formulation of compounds related to the present invention; and (4) equipment or devices related to the present invention.

The disadvantages of prior references and advantages of this invention should be addressed to draw attention to your invention. Keep in mind that patent application

has legal issues. Therefore, it is very important that all prior art directly related to your invention shall be cited. If you intentionally missed or concealed important prior references, and these are later found by patent examiners or other dispute parties, there will be legal consequences, which may include potential patent infringement lawsuit(s).

### 26.6.6 SUMMARY OF INVENTION

Summary is not the same as the abstract of the invention. The Summary summarizes and/or discusses the method, composition or reagents, and the data or results of the invention. The following is an illustrative example:

The present invention provides a general method for killing prostate cancer cells. The method comprises the steps of obtaining a sample (i.e., cancer cell line); obtaining a composition; obtaining agent (i.e., peptide); admixing the agent and sample and incubating. A composition is understood to be any compositions that may contain cancer cells, including, but not limited to, a cell line, a tissue sample, a reagent, and a solution.

In one embodiment, the present invention relates to reagents for use in methods for inactivating prostate cancer cells and such methods comprising: (a) . . . ; (b) . . . ; (c) . . . ; and (d) . . .

One of the advantages of the inventor's method for inactivating prostate cancer cells is that method can protect normal cells during treatment. This method may also be applied to kill other cancer cells.

...

### 26.6.7 BRIEF DESCRIPTION OF DRAWINGS AND FIGURES

This section briefly describes the figures and/or drawings attached to your application. In patent filing, you may not have to include figures, photos. Instead, drawings or just text description may be acceptable. However, when you attach figures or drawings, you should describe each. Illustrative examples are listed below:

The following drawings form part of the present specification and further demonstrate certain aspects of the present invention.

FIG. 1. . . . .

FIG. 2. . . . .

### 26.6.8 DESCRIPTION OF ILLUSTRATIVE EMBODIMENTS

This section describes in detail: (1) what methods, reagents, and organisms were utilized; (2) how experiments or procedures were performed; and (3) what results (figures, drawings, tables) and conclusions have been drawn. These can be divided into specific areas of the invention: Examples 1, 2, 3, . . . . The following is an illustrative example (not real data):

The present invention relates to methods for killing cancer cells, which employ at least one reducing reagent. Generally, the reducing agent is added to buffers, solutions, water, or culture medium containing cancer cells. The cells are then killed by incubating at 37°C for 12 h. The preferred reducing reagents are xxx, xxx, xxx, and xxx. To effectively kill cancer cells, the presently preferred method is to add xxx to final concentration of xx mM to sample and then incubate at 37°C for 12 h. The following examples provide detailed description and utilities of the present invention.

It should be appreciated by those skilled in the art that the methods disclosed in the examples which follow represent methods discovered by the inventors to function well in the practice of the invention. However, those who are skilled in the art should appreciate that many modifications can be made in the specific embodiments which are disclosed and still obtain a similar result without departing from the spirit and scope of the invention.

### **Example 1**

Use of Agent xxx Coupled with Heating Kills Prostate Cancer Cells *In Vitro*  
(Describe the conditions, experiment and results, etc.)

### **Example 2**

Elimination of Cancer Cells is Dependent on the Agent xxx Concentration and Incubation Time  
(Describe different concentrations of the agent, treatment conditions, and results, etc.)

### **Example 3**

Brain Tumor Cells Can be Killed by Agent xxx and Incubation  
(Description of the procedures and data)

### **Example 4**

Use of Agent xxx in Buffer xxx Kills Brain Tumor Cells in Mice  
(Materials, methods, and results)

All of the above compositions and methods disclosed and claimed herein can be produced and executed without undue experimentation in light of the present disclosure. Although the compositions and methods of the present invention have been described as preferred embodiments, it will be apparent to those skilled in the art that certain agents may be modified or substituted for the agents described herein while the same or similar results would be achieved. Those of skilled in the art are aware that variations may be applied to the compositions and methods and in the steps of the method described herein without departing from the spirit, scope, and the concept of the invention as defined by the appended claims.

### 26.6.9 REFERENCES

Cite all related references and pay attention to specific format of databases from different countries.

### 26.6.10 CLAIMS OF INVENTION

This is the “heart” of the invention. Any potential values or potential legal dispute will be directly linked specific claims of the patent. Therefore, one should pay close attention to the claims of the invention. In general, the broader its scope and the more details it covers, the better the patent is and the more protections and values the patent has. If the inventor writes the claims, it is highly recommended that the claims be reviewed by an experienced patent attorney.

As an illustrative example, if you generated a recombinant peptide or protein coupled with a buffer that can kill cancer cells, you may need to claim and cover as broadly as possible even if you do not have experimental data yet. The following claims are for illustrative purpose (not real claims) only.

What is claimed is

1. A method of killing cancer cells comprising:
  - (a) Obtaining at least one cancer cell
  - (b) Obtaining an agent
  - (c) Obtaining a solution
  - (d) Preparing an admixture of cell, agent, and buffer
  - (e) Incubating the admixture to a temperature and for a time required to result in killing cancer cells present in the admixture
2. The method of claim 1, wherein cancer cell comprises:
  - (a) Cultured cancer cell
  - (b) Cancer cell from dissected tissue
  - (c) Cancer cell from organism
3. Method of claim 2, wherein cancer cell comprises any types of cancer cells.
4. Method of claim 1, wherein an agent comprises:
  - (a) Recombinant cDNA
  - (b) Recombinant gene
  - (c) Recombinant peptide
  - (d) Recombinant protein
  - (e) Recombinant antibody
  - (f) Chemical compound
5. Method of claim 4, wherein cDNA or gene comprises at least two nucleotides.
6. Method of claim 4, wherein recombinant cDNA comprises nucleotide sequence: ATGCCTATGCATGCAATCTG . . .
7. Method of claim 4, wherein peptide or protein comprises at least two amino acids.
8. Method of claim 4, wherein recombinant peptide comprises amino acid sequence: xxxxx . . .

9. Method of claim 4, wherein antibody comprises at least one antigen binding site.
10. Method of claim 4, wherein recombinant protein comprises amino acid sequences: xxxxx . . .
11. Method of claim 4, wherein chemical compound comprises at least one chemically made molecule.
12. Method of claim 11, wherein molecule comprises structure: xxx.
13. Method of claim 1, wherein a solution comprising:
  - (a) Buffer
  - (b) Cell culture medium
  - (c) Blood
  - (d) Body fluid
14. Method of claim 1, wherein preparing an admixture comprises:
  - (a) First preparing cell sample
  - (b) Preparing recombinant agent
  - (c) Preparing solution by adding the agent and chemical compound
  - (d) Adding the solution to the sample
  - (e) Mixing and incubating at 37°C for 12 h
  - (f) Examining killing of the cells in the sample
15. Method of claim 14, wherein cell sample comprises:
  - (a) Cultured cells
  - (b) Cells in dissected tissues
  - (c) Cells in animals
  - (d) Cells in human subjects

Please note that the preceding are just illustrative claims. One may expand the major claims to more specific and broader areas to protect the invention. It is highly recommended that a patent application be reviewed and submitted by an experienced lawyer. Depending on USPTO, it may take 1 year (very priority patent application) or 2 to 5 years or even longer to officially issue a patent. In the United States, a patent may protect your IPs for up to approximately 20 years. If you are granted a major patent with great commercial uses, and if you are both the inventor and assignee, your investment and hard work are rewarded and your life may be changed from now on by attracting funds and starting a company and/or licensing the technology to others. Congratulations!

Finally, the inventor should keep all laboratory notebooks, data sheets, results, documents, emails, etc. It is good practice to keep duplicate copies of some documents and place them in a safe place.

## REFERENCES

1. Pasloske, B. I., and W. Wu. 2004. Methods and reagents for inactivating ribonucleases RNase A, RNase 1 and Rnase T1. US Patent, 6,777, 210, B1.
2. Pasloske, B. I., and W. Wu. 2004. Methods and reagents for inactivating ribonucleases. US Patent, 6,825, 340 B2.
3. Wong et al. 1993. Excretion of heterologous of proteins from *E. coli*. US Patent 5,233,407.

4. Wu, W. 2004. Down-regulation of gene expression in mammalian systems via current siRNA technology. In *Gene Biotechnology*, ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang, 493–508. Boca Raton, FL: CRC Press.
5. Siegmund, D., P. Hadwiger, K. Pfizenmaier, H. P. Vornlocher, and H. Wajant. 2002. Selective inhibition of FLICE-like inhibitory protein expression with small interfering RNA oligonucleotides is sufficient to sensitize tumor cells for TRAIL-induced apoptosis. *Molecular Medicine* 8(11): 725–732.

---

# 27 Determination of Transgene Copy Numbers and Practical Biocalculation

## 27.1 INTRODUCTION


In current biotechnology and molecular biology research, gene transfer and generation of transgenic animals play a major role in exploring the functions and biology of the gene of interest. To characterize the transgenic animals well, it is necessary to address an important question: How many copies of the transgene have been integrated into the genome of the transgenic animals? This chapter describes the standard and widely used approach: Southern blotting for determining the transgene copy numbers and for identifying the multiple insertion sites in the transgenic animals.<sup>1-2</sup>

In addition, this chapter provides some important examples of biocalculation such as molecular weight (MW), moles, molarity, conversions among or between DNA, RNA, and proteins, oligonucleotides, peptides, statistic mean, variance, and standard deviation (SD). These concepts, equations, and practical calculations are important and widely used in current biotechnology research. However, a lot of people including graduate students, researchers, and some faculty members are confused about these methods.<sup>3-4</sup> One can imagine that if buffers or solutions for important research projects were made incorrectly (e.g., wrong weight and molarity), the outcome—including data, results, and conclusions—would be significantly impacted by these buffers and/or solutions, which may contain DNA, RNA, proteins, compounds, or other solutes. Therefore, this chapter attempts to help clear things up by describing several important concepts and methods, particularly practical biocalculation.

## 27.2 DETERMINATION OF GENE COPY NUMBERS IN TRANSGENIC ANIMALS

Figure 27.1 illustrates an example of selection of restriction enzyme digestion and design of probe.

Protocols for carrying out Southern blotting are described in Chapter 7. Based on Southern blotting analysis, one can calculate the gene copy numbers by comparing the signal intensity of the detected band(s) from the isolated genomic DNA of the transgenic animals to the copy numbers of the transgene standards (the injected cDNA or gene in plasmid or linear form). Typically, the transgene is blotted using



**FIGURE 27.1** Diagram of transgene concatemer integration into chromosome. Restriction enzyme cuts once in the transgene DNA and generates similar size DNA fragments as the transgene (e.g., 2.5 kb) and 5'-, 3'-unpredictable fragment size. The probe is designed to either overlap the restriction enzyme cut site and will hybridize to unique 5'- and 3'-DNA fragments of unpredictable size, or hybridize to one side of the restriction enzyme cutting site and will hybridize to the unique 5' or 3' fragment.

picograms that are equal to 1, 5, 10, 20, 30, copies, etc. The following is an example of determination of the copy numbers of transgene in transgenic mice.

1. Calculate and set up transgene copy standards for Southern blotting  
 Assumption: The Haploid content of a mammalian genome is  $3 \times 10^9$  bp.  
 Assumption: The size of the transgene insert is 2500 bp.  
 Assumption: Five micrograms of tail genomic DNA per well will be loaded into the gel.

Because transgenic founder mice are hemizygous, the mass or amount of the transgene for the standards can be calculated as follows.

$$\text{mass of transgene DNA} \div 2.5 \mu\text{g genomic DNA} = N \text{ bp transgene DNA} \\ \div 3 \times 10^9 \text{ bp genomic DNA}$$

Since the size of the transgene insert in this example is 2500 bp,

$$\text{mass of transgene DNA} \div 2.5 \mu\text{g genomic DNA} = 2500 \text{ bp transgene DNA} \\ \div 3 \times 10^9 \text{ bp genomic DNA}$$

$$\text{mass of transgene DNA} = (2.5 \mu\text{g genomic DNA} \times 2500 \text{ bp transgene DNA}) \\ \div 3 \times 10^9 \text{ bp genomic DNA}$$

$$\text{mass of transgene DNA} = 0.000000208 \mu\text{g or } 0.0021 \text{ ng or } 2.1 \text{ pg (picograms)}$$

Thus, the transgene copy standards can be prepared as follows:


Transgene Copy Numbers	Amount of Transgene DNA (pg)
0	0
1	2.1
5	10.5
10	21
20	42
30	63



2. Add 5 µg control mouse tail DNA (no transgene DNA) to each of the six microtubes (labeled 0, 1, 5, 10, 20, 30 as copy numbers). Separately, add 5 µg transgenic mouse tail DNA (with transgene) from each transgenic mouse to appropriate tubes.
3. Add the same amount of appropriate restriction enzyme(s) to each of the tubes described above.
4. Carry out appropriate restriction enzyme(s) digestion, followed by heat inactivation of the enzyme (e.g., 70°C for 30 min).
5. In the order shown in the preceding table, add the amount of transgene DNA (either cDNA or gene but not entire plasmid vector) into the labeled tubes for standards above.
6. Perform Southern blotting (see Chapter 7 for detailed protocols).
7. Analyze and determine the copy numbers of the transgene based on the signal intensity comparison (Figure 27.2).

As illustrated in Figure 27.2, based on the signal intensity of the transgene copy standards, mouse 1 has 10 to 15 gene copies and two unique bands. Mouse 2 has approximately 30 copies and three unique bands, an indication of integration in two chromosomes.

It should be noted that determination of gene copy number can be done using commercially available instrument (e.g., TaqMan RT-PCR systems from Applied Biosystems).



**FIGURE 27.2** Illustration of determination of gene copy numbers by comparison of signal intensity based on Southern blot analysis.

### 27.3 MOLECULAR WEIGHT

The MW of a substance (chemicals, compounds, DNA, RNA, protein, etc.) is the weight of 1 mol of that substance.

The following are common weight conversions:

$$1 \text{ lb} = 16 \text{ oz}$$

$$1 \text{ oz} = 30 \text{ g}$$

$$1 \text{ kg} = 1000 \text{ g (gram)}$$

$$1 \text{ g} = 1000 \text{ mg (milligram)}$$

$$1 \text{ mg} = 1000 \text{ } \mu\text{g (microgram)}$$

$$1 \text{ } \mu\text{g} = 1000 \text{ ng (nanogram)}$$

$$1 \text{ ng} = 1000 \text{ pg (picogram)}$$

$$1 \text{ pg} = 1000 \text{ fg (femtogram)}$$

### 27.4 CALCULATION OF MOLECULAR WEIGHT OF OLIGONUCLEOTIDES

$$\begin{aligned} \text{ssDNA oligonucleotide molecular weight} &= (A_n \times 313.21) \\ &+ (T_n \times 304.2) + (C_n \times 289.18) + (G_n \times 329.21) - 61.96 \end{aligned}$$

where:

$n$  = number of each respective nucleotide

61.96 gm/mol = removal of  $\text{HPO}_2$  (63.98) and addition of two hydrogens (2.02)

$$\begin{aligned} \text{dsDNA molecular weight} &= (A_n \times 313.21) + (T_n \times 304.2) + (C_n \times 289.18) \\ &+ (G_n \times 329.21) + 158 \end{aligned}$$

where:

$n$  = number of each respective nucleotide

158 gm/mol = addition of a monophosphate to each strand

$$\begin{aligned} \text{dsDNA molecular weight by restriction enzyme digestion} &= (A_n \times 313.21) \\ &+ (T_n \times 304.2) + (C_n \times 289.18) + (G_n \times 329.21) + 79 \end{aligned}$$

where:

$n$  = number of each respective nucleotide

79 g/mol = 5' monophosphate left by most restriction enzymes and no phosphate at the 5' end of strands by primer extension

$$\begin{aligned} \text{RNA molecular weight} &= (A_n \times 329.21) + (U_n \times 306.17) \\ &+ (C_n \times 305.18) + (G_n \times 345.21) + 159.0 \end{aligned}$$

where:

$n$  = number of each respective nucleotide

159 g/mol = 5' triphosphate

## 27.5 AMINO ACIDS

Amino Acid	3-Letter Code	1-Letter Code	Molecular Weight (g/mol)
Alanine	Ala	A	89
Cysteine	Cys	C	121
Aspartate	Asp	D	133
Glutamate	Glu	E	147
Phenylalanine	Phe	F	165
Glycine	Gly	G	75
Histidine	His	H	155
Isoleucine	Ile	I	131
Lysine	Lys	K	146
Leucine	Leu	L	131
Methionine	Met	M	149
Asparagine	Asn	N	132
Proline	Pro	P	115
Glutamine	Gln	Q	146
Arginine	Arg	R	174
Serine	Ser	S	105
Threonine	The	T	119
Valine	Val	V	117
Tryptophan	Trp	W	204
Tyrosine	Tyr	Y	181

Average MW of amino acid: 110 daltons (Da)

## 27.6 SPECTROPHOTOMETRIC CONVERSIONS

1 OD<sub>260</sub> unit of double-stranded DNA or dsDNA = 50 µg/ml

1 OD<sub>260</sub> unit of single-stranded DNA or ssDNA = 33 µg/ml

1 OD<sub>260</sub> unit of ssRNA = 40 µg/ml (total RNA)

1 OD<sub>260</sub> unit of ssRNA = 42 µg/ml (mRNA)

Average MW of dsDNA bp = 660

Average MW of ssDNA base = 330

Average MW of ssRNA base = 340

## 27.7 DNA MOLAR CONVERSIONS

1 µg of 1000 bp DNA = 1.52 pmol (3.03 pmol of ends)

1 pmol of 1000 bp DNA = 0.66 µg

For dsDNA:  $\mu\text{g} = \text{pmol} \times N \times 660 \text{ pg/pmole} \times 1 \mu\text{g}/10^6 \text{ pg}$   
 $\text{pmole} = \mu\text{g} \times 10^6 \text{ pg}/1 \mu\text{g} \times \text{pmole}/660 \text{ pg} \times 1/N$

For ssDNA:  $\mu\text{g} = \text{pmol} \times N \times 330 \text{ pg/pmole} \times 1 \mu\text{g}/10^6 \text{ pg}$   
 $\text{pmole} = \mu\text{g} \times 10^6 \text{ pg}/1 \mu\text{g} \times \text{pmole}/330 \text{ pg} \times 1/N$

where  $N$  is the number of nucleotides and 330 pg/pmole is the average MW of a nucleotide.

## 27.8 PROTEIN MOLAR CONVERSIONS

- 1 kilodalton (kDa) = 1000 Da
- 100 pmol of 1 kDa protein = 0.1  $\mu\text{g}$
- 100 pmol of 10 kDa protein = 1  $\mu\text{g}$
- 100 pmol of 40 kDa protein = 4  $\mu\text{g}$
- 100 pmol of 80 kDa protein = 8  $\mu\text{g}$

## 27.9 DNA–PROTEIN CONVERSIONS

- 1 kb DNA = 333 amino acids (AAs) = 36.7 kDa protein
- Average MW of AA = 110 Da
- 500 bp DNA = 167 AAs = 18.3 kDa protein
- MW of 50 kDa protein = 50,000 g/mol

It should be noted that all preceding conversions and/or calculations are relative values (and therefore not absolutely accurate).

## 27.10 MOLARITY

Molarity (M) is a measurement of concentration of a solution or buffer. Molarity is equivalent to moles (mol) of a solute in 1 liter (l) of solution:  $M = \text{mol/l}$ .

### 27.10.1 DEFINITION OF MOLE

A mole or mol for short (also known as Avogadro's number) is equal to  $6.022 \times 10^{23}$  atoms or molecules. The molar mass (MM) of compounds and elements is the mass, in grams, equal to the atomic and formula masses of those compounds and elements. MM is expressed in grams/mole.

### 27.10.2 HOW TO CONVERT SOLUTION OR BUFFER DENSITY INTO MOLES OR MOLAR CONCENTRATION

To obtain an accurate calculation, one needs to figure out the molecular weight of the chemical or compound to be calculated. For example: NaOH, molar mass (MM) = 23 (Na) + 16 (O) + 1 (H) = 40. Depending on the specific concentration to be calculated, the MM of NaOH can be expressed as any of the following:

- 40 g/mol
- 40 mg/mmol
- 40  $\mu\text{g}/\mu\text{mol}$

Remember that molar refers to the concentration per liter and molar mass is measured in grams. Thus, 1 M NaOH = 40 g.

So, if the density of the NaOH solution is 60 g/l, concentration = density of the solution  $\div$  molar mass =  $60 \text{ g/l} \div 40 \text{ g/mol} = 1.5 \text{ mol}$  or 1.5 M.

However, if the density of the NaOH solution is 5 mg/ml, then density in 1 l =  $5 \times 1000 \text{ ml} = 5000 \text{ mg/l}$ ,  $5000 \text{ mg/l} \div 1000 = 5 \text{ g/l}$ ; thus, concentration = density of solution  $\div$  molar mass =  $5 \text{ g/l} \div 40 \text{ g/mol} = 0.125 \text{ M}$ .

Hence, g/l, mg/ml, or  $\mu\text{g/ml}$  can be converted into M or mol/l. First, convert mg,  $\mu\text{g}$ , or ng to g, and convert ml,  $\mu\text{l}$  to l. Next, divide g/l by the molecular weight of the solute to get moles per liter, which is molarity (M). Therefore,  $\text{mg/ml} = 1 \text{ M}$  (molar), and 1 mol/l has a molarity of 1.

### 27.10.3 HOW TO CONVERT A SPECIFIC VOLUME OF A SPECIFIC CONCENTRATION (100 mM) OF A SOLUTION OR BUFFER INTO WEIGHT

Taking NaOH again as an example, if you used 100  $\mu\text{l}$  of 100 mM NaOH solution in an experiment, how many milligrams or gram of the solute (NaOH) did you utilize? Well, since 100 mM NaOH = 100 mg/l, and 100  $\mu\text{l}$  of the solution used =  $100/1000 = 0.1 \text{ l}$ , it turns out that  $100 \text{ mg/l} \times 0.1 \text{ l} = 10 \text{ mg}$  or  $10 \text{ mg}/1000 = 0.01 \text{ g}$  of NaOH was used in your experiment.

### 27.10.4 COMMON BUFFER OR SOLUTION VOLUME CONVERSIONS

- 1 gallon = 3.78 l
- 1 gallon = 4 quarts
- 2 cups = 1 pint
- 4 cups = 1 quart
- 1 quart = 0.95 l
- 1 l = 10 dl
- 1 l = 1000 ml
- 1 ml = 1000  $\mu\text{l}$
- 1  $\mu\text{l}$  = 1000 nl

### 27.10.5 EXAMPLE OF PREPARATION OF A PRIMER SOLUTION

If you ordered a 20-nM scale of oligonucleotide primer (20-mer, 20 nucleotides in length) and received from the manufacturer a vial containing the synthesized primer in the form of dry powder and you added 200  $\mu\text{l}$  water to the vial to dissolve the primer, what is the concentration of the primer in the tube?

One way to calculate the concentration is to use the 20-nM scale ordered. Because 20 nM refers to the final concentration of the primer in dissolved in 1 l or 1000 ml, the total amount of primer dissolved in 200  $\mu\text{l}$  water should result in a much higher concentration as compared to 1 l. Thus, the actual concentration of the primer in the vial =  $1000 \text{ ml}/0.2 \text{ ml} (200 \mu\text{l}) \times 20 \text{ nM} = 100,000 \text{ nM}$ , or  $100,000/1000 = 100 \mu\text{M}$ . You may use this as the primer stock solution and dilute it appropriately before setting up a PCR reaction.

### 27.10.6 EXAMPLE OF PREPARATION OF A PEPTIDE SOLUTION

If you ordered 20 mg of a peptide (30 amino acids in length) and received from the manufacturer a vial containing the synthesized peptide in the form of dry powder

and you added 100  $\mu\text{l}$  water to dissolve it, how do you calculate the final concentration of the peptide in the tube?

One method is to base it on the weight ordered and the size of the peptide. Because the average MW of an amino acid is 110 Da, 30 amino acids will be  $110 \times 30 = 3300$  Da or  $3300/1000 = 3.3$  kDa or 3300 g/mol, meaning that 1 M of this peptide is 3300 g (remember that molar refers to the concentration per liter). Thus, 20 mg of the peptide ordered is:  $(20 \text{ mg} \div 1000) = 0.02$  g,  $0.02 \div 3300 = 0.000006$  M, or  $0.000006 \div 1000 = 0.006$  mM. Note that 0.006 mM refers to the concentration in 1 l. Since the total amount of the peptide was dissolved in 0.1 ml water, the final concentration of the peptide solution is  $1000/0.1 \times 0.006 = 60$  mM.

## 27.11 CALCULATION OF MEAN

The mean is the most commonly used statistical measure in biotechnology, pharmaceuticals, and other fields. It is the average value of a group data and is calculated by summing all individual data or observations and dividing the sum by the number of individuals or items in the group or sample. For instance, a group of people were treated with a new drug for body weight loss (just for illustration). After a 1-year treatment coupled with standard exercise, the drug is effective and these patients showed obvious weight loss compared to placebo- or non-treated people. The data are shown below.

Treated Individual	Treated Weight Loss (lb)	Untreated Individual	Untreated Weight Loss (lb)
1	50	1	3
2	49	2	5
3	48	3	5
4	52	4	6
5	49	5	4
6	49	6	5
7	55	7	6
8	48	8	5
9	53	9	2

Question #1: What is the mean weight loss for the treated and untreated people?

Question #2: What is the SD of the body weight loss?

Question #3: After the drug treatment, is the weight loss statistically significant?

To answer these important questions, the data listed in the preceding table need to be statistically analyzed.

The mean in this example is the average weight loss of subjects in the treated or placebo (untreated) group. Thus, the mean for the drug treated group (T) and untreated group (UT) are as follows:

$$\text{Mean (T)} = (50 + 49 + 48 + 52 + 49 + 49 + 55 + 48 + 53)/9 = 50.4 \text{ (lb)}$$

$$\text{Mean (UT)} = (3 + 5 + 5 + 6 + 4 + 5 + 6 + 5 + 2)/9 = 4.5 \text{ (lb)}$$

Clearly, the drug treatment resulted in obvious body weight loss with an average of 50.4 lb, which is approximately 11 times that in the untreated (or placebo) group.

### 27.12 VARIANCE AND SD

Standard deviation is a measure of the amount of variation in data, sample, or population. To calculate for the SD, we need to figure out the variance (*V*). Individual variance is a measure of the difference or distance between individual data and group mean value and calculated by subtracting the mean value from individual data (positive or negative). Variance (*V*) is the average of individual variance and is calculated by summing all the individual variance data and dividing the sum by the number of individuals or items in the group or sample. Taking this body weight loss for example, mean (T) is 50.4 lb and mean (UT) is 4.5 lb. Thus, *V*(T) or *V*(UT) is as follows:

Treated	Weight Loss (lb)	V(T)	Untreated	Weight Loss (lb)	V(UT)
1	50	2.3	1	3	-1.5
2	49	-1.4	2	5	0.5
3	48	0.3	3	5	0.5
4	52	4.3	4	6	1.5
5	49	-1.4	5	4	-0.5
6	49	1.3	6	5	0.5
7	55	7.3	7	6	1.5
8	48	0.3	8	5	0.5
9	53	<u>2.6</u>	9	2	<u>-2.5</u>
		15.6/9			0.5/9

$$V(T) = 15.6/9 = 1.733, V(UT) = 0.5/9 = 0.056$$

Now, SD can be calculated: positive square root of the variance.


$$SD(T) = 1.3166$$

$$SD(UT) = 0.2357$$

It should be noted that variance, SD, and Student’s *t*-test can be calculated using an appropriate commercial software.

Based on the SD, the drug induced considerable body weight loss with relatively small variation among patients.

If the calculated mean value and SD are plotted as shown in Figure 27.3, a conclusion can be reached. Given that the average weight loss in the treated group is almost



**FIGURE 27.3** Illustration of new drug treatment for body weight loss.

11 times of that in the placebo group, and that the SD between the two groups do not overlap each other plus statistical analysis ( $p < 0.0001$ ), the body weight loss in the drug-treated group vs. placebo (un-treated group) is significant. Therefore, the new drug is effective.

## REFERENCES

1. Wu, W. 1995. Gene transfer and expression in animals. In *Handbook of Molecular and Cellular Methods in Biology and Medicine*, ed. P. B. Kaufman, W. Wu, D. Kim, and L. Cseke. Boca Raton, FL: CRC Press.
2. Wu, W. 2004. Characterization of DNA or gene by Southern blot hybridization. In *Gene Biotechnology*, 2nd edn., ed. W. Wu, M. J. Welsh, P. B. Kaufman, and H. Zhang. Boca Raton, FL: CRC Press.
3. Camper, S. A. 1987. Research application of transgenic mice. *Biotechniques* 5: 638–650.
4. Sokal, R. R., and F. J. Rohlf. 1981. Estimation and hypothesis testing. In *Biometry*. New York, NY: W. H. Freeman and Company.



# Index

Page numbers followed by *f* and *t* indicate figures and tables, respectively.

## A

Avian myeloblastosis virus (AMV), 127  
Acid guanidinium thiocyanate–phenol–chloroform method, 38–39, 40*f*  
Acrylamide, 256  
Actin detection, 253*f*  
Agarose gel, 30, 78–81  
    electrophoresis, alkaline, 47–49, 48*f*  
    electrophoresis of DNAs, 157–159  
    slices  
        high-speed centrifugation of, 22–23, 78–80  
        melting and thawing of, 80  
    well, 81  
Alkaline agarose gel electrophoresis, 47–49, 48*f*  
Alkaline buffer, 161, 445  
Alkaline method, 88–94, 99–101. *See also* Plasmid DNA  
Alkaline phosphatase-conjugated antibodies, 262  
Amino acids, 525  
Aminoglycoside antibiotics, use of, 200  
Ammonium persulfate solution (APS), 109  
Ampicillin-resistant (*Amp<sup>r</sup>*) gene, 384, 397  
Amplicover Clip, 308, 309  
Animal model, 6, 8*f*  
Anionic detergent, 251  
Antibody-conjugated probes, 174  
Antibody(ies)  
    alkaline phosphatase-conjugated, 262  
    biotin-labeled, 262  
    heavy chains of, 443  
    light chains of, 439, 443  
    monoclonal antibodies, 451–452, 455*f*  
        infection of bacteria, 452, 455  
        phage–antibody particles by biopanning, 455–456  
    phage display of, 440  
    structure of, 252–253  
    western blot hybridization, 252–253  
Antibody libraries. *See* Human antibody libraries  
Antibody variable regions (V genes), 446, 447*t*–448*t*, 449*t*  
Antisense DNA/RNA strategies. *See* Gene underexpression by antisense DNA/RNA approaches  
Antisense oligonucleotide approaches. *See* Gene underexpression by antisense DNA/RNA approaches  
Antisense RNA analysis by northern blotting, 219*f*

AOX1 gene, 397, 398*f*, 408*f*  
Autoradiography, 174–178  
Avian myeloblastosis virus (AMV), 20  
Avogadro's number, 526  
Axons, disruption of, 355

## B

BackTranslate program, 150–151  
Bacterial expression vectors, 382–384, 385*f*  
Bacteriophage  $\lambda$  library  
    high molecular weight of genomic DNA, 320–321  
    isolated DNA, 338  
    lambda vectors, selection of, 320, 320*f*, 321*f*  
    ligation of DNA inserts  
        packaging of ligated DNA, 326  
        partially filled-in genomic DNA, 325, 328  
        partially filled-in lambdaGEM -12 arms, 325  
        partially filled-in vector arms, 328  
        titration of packaged phage on luria–bertani plates, 326–327  
    liquid method for DNA isolation, 335–336  
    partial fill-in of recessed 3'-termini, 324  
    restriction mapping of bacteriophage DNA, 336–338, 338*f*  
    *Sau3A*I in genomic DNA digestion  
        large scale preparation of, 323–324  
        optimal partial digestion determination, 322–323  
    screening of  
        with nonisotopic labeled probe, 333–334  
        with  $\alpha$ -<sup>32</sup>P-labeled probe, 328–333, 332*f*  
        specific clones, isolation of, 328  
Bacteriophage T7 promoter, 382  
Bank of sterile males by vasectomy, 221–222, 490  
Basic Local Alignment Search Tool. *See* BLAST programs  
Bicinchoninic acid (BCA) assay, 254  
Binding proteins, 477–479  
Bioinformation superhighway. *See also* GCC program  
    communication with GenBank via internet  
    BLAST programs, use of, 135–139  
    submission of sequence, 133–135  
    computer analysis of DNA sequences  
    entry and editing of sequence, 140  
    Fetch program, use of, 152–153

- Bioinformation superhighway (*continued*)  
 multiple fragments, assembly of, 142–145  
 restriction enzyme digestion site, 145–148  
 similarity between two sequences,  
 148–149  
 Translate program, 150–152
- Biotin detection solution, 300
- Biotin-dUTP, 173, 316
- Biotin-11-dUTP, 167
- Biotin-labeled antibodies, 262
- Biotinylated dATP, 98
- Blastocyst, 493, 494  
 injection pipettes, 224, 493
- Blastocyst-stage embryos  
 preparation of, 222–223, 491–492  
 from pseudopregnant mice, 222–223
- BLAST programs  
 BLASTN, 135–138  
 BLASTP, 139  
 BLASTX, 138–139
- Blunt-end cDNAs, 52
- Bone marrow stem cells, 9f
- Bradford assay in protein concentration, 255
- 5-bromo-4-chloro-3-indolyl phosphate (BCIP),  
 292, 297–298
- Buffered minimal glycerol (BMG), 411
- Buffered minimal methanol (BMM), 411
- C**
- CaCl<sub>2</sub> method, 386  
 for cell transformation, 86–87
- Calcium phosphate methods, 464
- Calcium phosphate precipitation, 190–192
- Calf intestinal alkaline phosphatase (CIAP), 77
- Cambridge Antibody Technology and Novagen  
 Corporation, 441
- Capillary method, 237, 237f
- CAT genes. *See* Chloramphenicol acetyl  
 transferase (CAT) genes
- C57BL/6J estrous females, selection of, 220–221,  
 377–378
- cDNA/mRNA hybrids, 50
- cDNAs  
 amplification by RT-PCR, 20–22  
 analysis of, 47–49  
 characterization of, 60  
 cloning, 33, 34f  
 vectors used for, 34f  
 identification of, 10, 12f  
 to  $\lambda$ gt11 expression vectors, ligation of, 61  
 library  
 amplification of, 60  
 screening of, 67  
 rapid cloning of. *See* Protein-protein  
 interaction identification  
 synthesis of. *See* Human antibody libraries  
 to vectors, ligation of, 56–57  
 yield calculation, 47
- Cellular DNA analysis. *See* Radioactivity *in situ*  
 hybridization (RISH)
- Cellular protein extraction. *See* Western blotting  
 for gene expression analysis
- Chemiluminescence detection method, 115–116,  
 173–174, 179, 262
- Chloramphenicol acetyl transferase (CAT) genes,  
 184, 203  
 enzyme assay, 204
- Claims of invention, 518–519
- Cloning of cDNA, 384–385, 398–399
- Cloning vector selection, 75, 472–473, 472f, 487
- Coimmunoprecipitation, 477
- Colorimetric detection method, 262  
 for DNA sequences, 116–117, 116f  
 for filters, 174, 179
- Colorimetric substrates, 297
- Competent cell preparation  
 for CaCl<sub>2</sub> transformation before ligation,  
 85–86  
 for electroporation, 86
- Complementary DNA. *See* cDNAs
- Complete expression cDNA library  
 characterization of troubleshooting guide,  
 69–70  
 ligation of cDNAs, 61  
 principles of, 61, 62f  
 screening of  
 immunoscreening of cDNA library,  
 63–67, 65f  
 $\lambda$  phage DNAs, isolation of, 67–69  
<sup>32</sup>P-labeled DNA as probe, 67
- Compressions, 99
- Conditional gene knockout (CKO), 13, 14f  
 Cre-loxP DNA constructs, generation of,  
 484–488, 485f, 486f  
 principles of, 483–484  
 stable transgenic mouse line A and B, 497  
 transgenic mouse line C, 497–499  
 transgenic mouse line generation, 488–497
- Constitutive promoter vectors, 183f  
 constitutive promoters, 183–184  
 Kozak sequence, 185  
 reporter genes  
 $\beta$ -galactosidase gene, 184  
 $\beta$ -glucuronidase (GUS) gene, 185  
 CAT gene, 184  
 luciferase gene, 184–185  
 selectable marker genes, 184  
 splicing regions, 185
- Contamination, 342
- Coomassie blue staining, 411f
- CPrimer f program, 19, 306, 307
- Cre-Lox recombination process, 13, 483–484. *See*  
 also Conditional gene knockout (CKO)

- cloning, 487
    - vector selection, 487
  - exon/gene selection, 484
    - mRNA as template, 486
    - RT-PCR, performance of, 486–487
    - trizol reagent, use of, 485–486
    - promoter for expression of Cre, 487
  - Cre recombinase, 484
  - Cryosectioning. *See* Radioactivity *in situ* hybridization (RISH)
  - CsCl gradient, 92–94
  - Cyanogen bromide (CNBr), 395
  - Cytomegalovirus (CMV), 183
  - Cytoplasmic extract preparation for CAT assay, 203–204
- D**
- DE-81 filter-binding assay, 168, 279
  - Denhardt's solution, 287, 333
  - Deoxynucleoside 5'-triphosphates (dNTPs), 97
  - D-galactose, 156
  - 2-D gel electrophoresis, 263–265
  - Dideoxynucleotide chain termination method, 124
  - Diethyl pyrocarbonate (DEPC), 35, 38, 233
  - Digoxigenin-11-dUTP, 167, 316
  - DIG-UTP-labeled probes, 173
  - Direct DNA sequencing by PCR, 124–127
  - Directional cloning strategy, 62*f*
  - Direct labeling of ssDNA, 163–165, 164*f*
  - Discovery and invention protection
    - full-length/complete patent application abstract, 515
    - assignee, 515
    - background of invention, 515–516
    - claims of invention, 518–519
    - figures and/or drawings, 516
    - illustrative embodiments, description of, 516–517
    - inventor(s), 514–515
    - references, 518
    - summary of invention, 516
    - title, 514
  - intellectual properties (IPs), 511–512
  - invention documentation, 512
  - provisional application for patent, 513–514
  - research discoveries, 511
  - technology disclosure, 512–513
  - Disease-related new protein(s), discovery of, 10, 13*f*
  - DNA
    - amplification, 305–307, 305*f*, 306*f*
    - constructs and silencer, 365
    - insertion verification, 94–95
    - isolation, 157, 335–336, 338
    - localization of. *See* Fluorescence *in situ* hybridization (FISH)
    - microarray. *See* Gene expression, high-throughput analysis of
    - molar conversions, 525
    - polymerase, 30
    - templates, preparation of. *See* Nonisotopic DNA sequencing method
    - transfer onto nylon membrane, 114–115
  - DNA Database of Japan (DDBJ), 133, 134
  - DNA fragments. *See also* Subcloning of genes
    - amplification of, 358–360
    - by PCR, 29–30
    - elution of
      - in agarose gel well, 81
      - by high-speed centrifugation of agarose gel slices, 78–80
      - by melting and thawing of agarose gel slices, 80
      - using NA45 DEAE membrane, 81
    - purification of, 78–81. *See also* DNA fragments, elution of
  - DNA/genes, characterization of. *See* Southern blot hybridization
  - DNA microarrays
    - fluorescent probe preparation from mRNA, 431–433
    - generation of, 433
    - hybridization of, 434
    - isolation of total RNA from cells or tissues, 430–431
    - prehybridization of, 433–434
    - scanning of, 435–437
    - washing of, 434–435
  - DNA plasmid. *See* Plasmid DNA
  - DNA polymerase, 22, 30, 119, 167, 359
    - avian myeloblastosis virus (AMV), 127
    - DNA sequencing, 98
    - T4, 33, 61
  - DNA probes, preparation of, 237
  - DNA-protein conversions, 526
  - DNA sequencing, 95–96
    - of bacterial colonies, 475
    - computer analysis of. *See* GCC program
    - by PCR, direct, 124–127
    - by primer walking, 120
    - by unidirectional deletions, 120–124
  - DNase treatment, 277
  - DNAs onto nylon membranes, blotting of
    - downward capillary transfer, 161–163, 162*f*
    - upward capillary transfer (6 to 12 h), 159–161, 160*f*
  - Dot blot hybridization, 244*f*
  - Dot blotting, 388
  - Double knockout. *See* Gene double knockout
  - Double selection of cells, 370–371
  - Double-stranded cDNAs, 50–52
  - Double-stranded DNAs, 445–446
  - Double-stranded hairpin siRNA oligonucleotides, 460

Double-stranded oligonucleotide fragment for cloning, 459–460  
 Double-stranded plasmid DNA, 99–101, 103–107  
 Down-regulation of gene expression, 467–468, 468*f*. *See also* Short-interfering RNA (siRNA) technology  
 Downward capillary transfer, 161–163, 162*f*  
 Drug-binding protein, 3*f*, 8*f*  
 Drug discovery, 2, 3*f*  
 dsDNA  
   3'-end labeling of, 170–171  
   nick translation labeling of, 68, 167  
   random primer digoxigenin labeling of, 165–167, 166*f*  
   random primer labeling of, 170  
 Dulbecco's modified Eagle medium (DMEM), 38, 39, 192, 211, 465

## E

*E. coli*  
   BL21 (DE3), transformation of, 382*f*, 386  
   One-Shot TO P10 competent cells, 474  
   strains, 385*f*, 387–388  
 ECL kit, 163–165  
 ECL-labeled probes, 172–173  
*EcoRI* linkers/adapters, ligation of  
   to cDNAs, 55–56  
   double-stranded cDNAs, carry out size  
     fractionation of, 52  
   internal *EcoRI* sites of cDNAs, protection of, 52–53  
   to methylated cDNAs, 53–54  
 Electroblothing, 259–260  
 Electrophoresis, 257–258  
   in DNA sequencing, 112–114  
   of PCR products, 360–362  
   of RNAs, 234–237  
   of total RNA, 40*f*  
 Electroporation, 198–199, 218, 367–368, 400–401  
   for cell transformation, 86, 87–88  
 Embedding, 272  
 Embryonic stem cell injection, 224  
   pipettes, 493  
 Embryonic stem cells, growth of, 343  
 Embryo transfer pipettes, 224, 493  
 3'-end labeling of ssDNA, 170–171  
 Endogenous RNase, 38  
 Enzymatic detection of hybridized signals, 297–298  
 Enzyme digestion sites identification, 151–152  
 Eppendorf tube, 460  
 Estrous females and sterile males, pairing of, 222, 491  
 Eukaryotic cells, transfection of. *See* Protein-protein interaction identification

Eukaryotic systems, proteins in. *See* Recombinant proteins, expression and purification of  
 Exogenous RNase, 38  
 Exons. *See* Cre-Lox recombination process  
   deletion of, 355, 356*f*  
   sequences, 28–29, 28*f*  
 Expression of protein. *See also* Protein-protein interaction; Recombinant proteins, expression and purification of  
   induction by heat shock, 388–389  
   induction with IPTG, 386–387  
   large expression of, 411  
   optimum conditions for, 410–411, 411*f*  
   in prokaryotic systems, 382–395  
 Expression vector, 34, 34*f*, 61, 185*f*, 382, 398–399  
   bacterial, design and selection of, 382–384  
   plasmid-based, 183–190

## F

Fetch program, use of, 152–153  
 Fibroblast feeder layers, 344  
 First strand cDNAs, synthesis of. *See* Subtracted cDNA library  
 First strand DNAs, 442–445, 443*f*  
 Fixation, 274–275  
   solution preparation, 270–271  
 Fluorescence detection of hybridized signals, 298–300  
 Fluorescence *in situ* hybridization (FISH), 291  
   hybridized signals  
     enzymatic detection of, 297–298  
     fluorescence detection of, 298–300  
   nonisotopic probes  
     nick translation labeling of dsDNA, 293  
     random primer digoxigenin labeling of dsDNA, 292–293  
     riboprobe/RNA labeling, 293–296  
   *in situ* hybridization of specimens, 296–297  
 Fluorescence real-time PCR, 416  
 Fluorescent microscopy, 479  
 Fluorescent probes from mRNA, 431–433  
 Fluorescent protein as fusion tag, 479  
 Formaldehyde agarose gel, 234  
 Formamide gels, 119  
 Forward primers (FP), 18, 28–29, 28*f*, 486  
 Founder mice, generation of, 227–228, 496–497  
 Fragment assembly. *See* GCC program  
 Fragment sizes, 147–148  
 Freeze sectioning, 274, 275*f*  
 FuGene 6 reagent, 475–476  
 Full-length/complete patent application. *See* Discovery and invention protection  
 Functional genome analysis, 415–417, 416*f*, 499  
   primers and probes, design of, 420–421  
   real-time RT-PCR

- assembly of reactions, 421–422, 421*f*
  - data analysis, 423–426, 423*f*, 424*f*, 426*t*
  - programming and performance of, 422–423
  - validation, 426
  - RNA pool preparation, 419–420
  - total RNA isolation
    - from cultured cells, 418–419
    - from tissues/organs, 417–418
- G**
- GA3-binding protein(s), 6, 10, 11*f*
  - $\beta$ -galactosidase assay, 205–206
  - $\beta$ -galactosidase gene, 184
  - $\beta$ -galactosidase staining of cells, 371–372
  - GCC program
    - amino acid sequences from GenBank, 152–153
    - comparison program, 148–149
    - entry and editing of sequence
      - sequence editing/modification, 142
      - sequence entry, 140–141
      - sequence output, review of, 142
    - enzyme digestion sites identification, 151–152
    - fragment assembly
      - GelAssemble program, 145
      - GelEnter program, 143–144
      - GelMerge program, 144
      - GelOverlap program, 144
      - GelStart program, 142–143
    - fragment sizes, 147–148
    - map program, 146–147
    - nucleotide from GenBank, 152–153
    - protein translation, 146–147
    - translation of amino acid sequences/nucleic acid sequences
      - BackTranslate program, 150–151
      - Translate program, 150
  - GelAssemble program, 145
  - Gelatin-coating of slides, 270
  - GelEnter program, 143–144
  - GelMerge program, 144
  - GelOverlap program, 144
  - Gel preparation, sequencing, 108–112
  - GelStart program, 142–143
  - GenBank. *See also* Bioinformation superhighway
    - amino acid sequences from, 152–153
    - communication with, via internet, 133–139
    - nucleotide from, 152–153
  - Gene double knockout, 351–352
    - DNA constructs and silencer, 365
    - hyg<sup>r</sup>* (hygromycin resistance) gene vector for
      - second copy of, 364, 364*f*
    - hyrt<sup>r</sup>* gene vector, 364–365, 365*f*
    - manipulation of specific gene
      - deletion of exons, 355, 356*f*
      - disruption of axon, 355
      - isogenic DNA by PCR, 356–362, 357*f*
    - mutant mice, 379
    - neo<sup>r</sup>* (neomycin resistance) gene vector for
      - first copy of, 363–364, 363*f*
    - targeted embryonic stem cell clones
      - $\beta$ -galactosidase staining of cells, 371–372
      - double selections of cells, 370–371
      - single selection of cell, 371
      - southern blot analysis, 372–377
      - triple selections of cells, 371
    - and temporal silence, 352–354
    - transfection of embryonic stem cells
      - by electroporation, 367–368
      - by lipofectin reagents, 368–369
    - transgenic offspring generation
      - C57BL/6J estrous female selection, 377–378
  - Gene expression, high-throughput analysis of, 429–430, 430*f*
    - DNA microarray generation, 433
    - fluorescent probes from mRNA, 431–433
    - hybridization, 434
    - prehybridization of gene chips, 433–434
    - scanning of gene chips, 435–437, 435*f*
    - total RNA, isolation of, 431–432
    - washing, 434–435
  - Gene expression at functional genomic level. *See* Northern blot hybridization for gene expression
  - Gene expression at proteomic level. *See* Western blotting for gene expression analysis
  - Gene isolation. *See* Bacteriophage  $\lambda$  library
  - Gene knockout approach, 2, 5*f*
  - Gene overexpression by sense RNA
    - flaws in, 207–208
    - flowchart of, 182*f*
    - plasmid-based expression vectors
      - constitutive promoter vectors, 183–185, 183*f*
      - inducible promoter vectors, 185, 185*f*
      - retrovirus vectors, 186–190, 187*f*, 188*f*, 189*f*
    - plasmid sense cDNA constructs, preparation of, 190
    - primary principles of, 181–183, 182*f*
    - stable transfection of mammalian cells
      - by electroporation, 198–199
      - by liposomes, 198
      - by retrovirus vectors, 199
    - stably transfected cell clones, characterization of, 200–201
      - expression assay of reporter gene, 203–207
      - northern blotting in, 202, 202*f*
      - southern blot analysis, 202–203, 203*f*
      - western blotting in, 201–202, 201*f*

- Gene overexpression by sense RNA (*continued*)  
 stably transfected cell lines, selection of, 199–200  
 transgenic mice, characterization of, 207–208  
 transient transfection of mammalian cells  
 by calcium phosphate precipitation, 190–192  
 by retrovirus vectors, 193–198
- GenePix 4000a microarray scanner, 435, 435*f*
- GenePixArrayList (GAL), 436
- GenePixSetting File (GPS), 436
- Gene Pulser, 199
- Gene subcloning. *See* Subcloning of genes
- Gene targeted by new drug, 2, 4*f*
- Gene targeting sandwiches, 353
- Gene therapy in immune-deficient system, 6, 9*f*
- Gene underexpression by antisense DNA/RNA approaches  
 antisense oligonucleotide approaches  
 design and synthesis of, 209–211  
 inhibition of gene expression, 213–214  
 optimum dose of oligomers, 211–213, 213*f*  
 treatment of cultured cells, 211  
 plasmid antisense cDNA constructs, 214–215  
 plasmid-based expression vectors, 214  
 stable transfection of cultured cells  
 by electroporation, 218  
 by liposomes, 215–217  
 by microinjection, 217–218  
 by retrovirus vectors, 218  
 stably transfected cell clones, characterization of  
 by northern blotting, 219, 219*f*  
 by southern blot analysis, 219–220, 219*f*  
 by western blotting, 218, 218*f*  
 transgenic mice, characterization of, 228–229  
 transgenic mice, generation of  
 method A. *See* Transgenic mice from stably transfected ES cells  
 method B. *See* Transgenic mice production from oocytes
- Gene verification, 2, 5*f*
- Gene X-deficient brain tumor, 504, 507
- Genomic DNA isolation, 24–25
- Genomic DNA libraries. *See* Bacteriophage  $\lambda$  library
- Gloves, 159, 161
- $\beta$ -Glucuronidase (GUS) gene, 185
- Good writing practice (GWP), 501
- Green fluorescent protein (GFP), 467
- H**
- Hairpin siRNA-encoding oligonucleotides, 459
- Hairpin siRNA oligo insert, cloning, 460–462, 460*f*, 461*f*
- HAP chromatography, 50
- Heart hypertrophy, 6, 8*f*
- Heat shock in protein expression, 388
- Heavy chains of antibody, 443
- Hemocytometer plate, 348*f*
- Herpes simplex virus *thymidine kinase* gene (HSV-*tk*), 353
- High-speed centrifugation of agarose gel slices, 78–80
- His<sup>+</sup>Mut<sup>+</sup> phenotypes, 407
- His<sup>+</sup>Mut<sup>+</sup> phenotype, 407
- His tag, 472*f*
- His-tag, protease cleavage of  
 chemical cleavage with cyanogen bromide (CNBr), 395  
 enzymatic cleavage of leader sequence factor Xa, 392–395  
 thrombin, 395
- His-tag affinity column chromatography, 390–392
- His-tag sequence, 383, 397
- Histidine, 406
- Hoeffler TE 42 blotting apparatus, 260
- Human antibody libraries, 439–441  
 antibody variable regions (V genes), 446, 447*t*–448*t*, 449*t*  
 lymphocytes from tissues, preparation of, 442  
 monoclonal antibodies, 451–452, 455*f*  
 infection of bacteria, 452, 455  
 phage–antibody particles by biopanning, 455–456  
 recombinant DNA generation, 451, 453*f*  
 synthesis of cDNAs  
 double-stranded DNAs, 445–446  
 first strand DNAs, 442–445, 443*f*  
 VH–linker–VL in, 449, 450*f*  
 white blood cells (WBCs), preparation of, 441
- Human disease-causing gene. *See* Conditional gene knockout (CKO)
- Hybridization of cDNAs, 49–50
- Hybridized signal detection, 285–288  
 chemiluminescence detection, 262  
 colorimetric detection, 262
- Hydroxyapatite chromatography, cDNA/mRNA  
 hybrid separation from single-stranded cDNAs using, 36
- Hyg<sup>r</sup>* (hygromycin resistance) gene vector, 364, 364*f*
- Hygromycin resistance gene, 352, 364, 364*f*
- Hygromycin- $\beta$ -phosphotransferase gene, 200
- Hyrt<sup>r</sup>* gene vector, 364–365, 365*f*
- I**
- IAA-binding protein(s), 6, 10, 11*f*
- Immune-deficient system, rescue of, 6, 9*f*
- Immunoscreening of expression cDNA library, 63–67
- Immunostaining, 499, 505
- Incubation of antibodies, 172–173
- Induced proteins, identification of, 12*f*

Inducible promoter vectors, 185, 185f  
 Injected blastocysts, reimplantation of, 225, 494, 496–497  
 Injected eggs, reimplantation, 227–228  
*In situ* hybridization  
   of DNA, 277  
   of RNA, 277  
*In situ* PCR hybridization  
   biotin-dUTP in, 316  
   digoxigenin-11- dUTP in, 316  
   low copy gene detection, 304, 304f  
     designed primers, 307  
     detection by RISH/FISH, 311–312  
     DNA amplification, 305–307, 305f, 306f  
     *in situ* PCR, performance of, 308–311  
     tissue fixation/embedding, 307  
   principles of, 303–304  
*In situ* plaque hybridization, 67  
*In situ* RT-PCR hybridization  
   biotin-dUTP in, 316  
   digoxigenin-11- dUTP in, 316  
   low abundance mRNA detection, 312–314, 313f  
     *in situ* reverse transcription reaction on sections, 314–315  
 Integration copy number determination  
   genomic DNA, isolation of, 202–203  
   by southern blot analysis, 203, 219–220, 219f  
 Intellectual properties (IPs), 511–512  
 Intron sequences, 28–29, 28f  
 Invention. *See also* Discovery and invention  
   protection  
     claims of, 518–519  
     documentation, 512  
     summary of, 516  
*In vitro* packaging, 57–58  
 Isoelectric focusing (IEF) gel, 263  
 Isogenic DNA preparation by PCR  
   amplification of DNA fragments, 358–360  
   electrophoresis of PCR products, 360–362  
   primers, design of, 356–357, 357f  
   purification of PCR bands, 362  
 Isopropyl- $\beta$ -D-thiogalactoside (IPTG), 383, 386–387  
 Isotopic DNA probes  
   DE-81 filter-binding assay, 168  
   3'-end labeling of ssDNA, 170–171  
   nick translation labeling of dsDNA, 168  
   random primer labeling of dsDNA, 170  
   trichloroacetic acid precipitation, 168–170  
 Isotopic DNA sequencing method, 117–118  
 Isotopic probes. *See* Radioactivity *in situ* hybridization (RISH)

**J**

JM109, 85, 387–388

**K**

Klenow enzyme, 165  
 Kozak sequence, 185

**L**

*lacI* gene, 383  
*lac* operator, 383  
*Lac* promoter, 451  
 Lambda cloning vector, 338f  
 LambdaGEM-12 arms, 325  
 Lambda vectors, selection of, 320, 320f, 321f  
 Lauroylsarcosine buffer in protein extraction, 253–254  
 Lethal gene, 13  
 Leukemia inhibitory factors, 343  
 L-galactose, 156  
 $\lambda$ gt11 expression vectors, 61  
 $\lambda$  phage DNAs, isolation of, 67–69  
 Ligated DNA transformation. *See* Subcloning of genes  
 Ligation of cDNAs to lamda gt10. *See* Subtracted cDNA library  
 Light chains of antibody, 439, 443  
 Linear polypeptide chains, 251  
 Lipofectamine 2000, 476  
 Lipofectin reagents, 368–369  
 Liposomes, 198, 215–217  
 Lipotransfection method, disadvantage of, 216  
 Liquid method, 67  
 Liquid transfer, 260  
 Long terminal repeats (LTRs), 186  
 Low copy gene detection. *See In situ* hybridization  
 Luciferase assay, 204–205  
 Luciferase gene, 184–185  
 Luria–Bertani (LB) plate, 58, 326  
 Lymphocytes preparation from tissues, 442  
 Lysis buffer, 463, 476

**M**

Mammalian cells and systems, 181–182  
   characterization of stably transfected cell lines, 200  
   analysis of gene overexpression at the protein level by western blotting, 201  
   determination of integration copy number by southern blot analysis, 202–203  
   examination of expression of sense RNA by northern blotting, 202  
   expression assay of a reporter gene, 203–207  
   characterization of transgenic mice, 207  
   design and selection of plasmid-based expression vectors, 183–184

- Mammalian cells and systems (*continued*)  
 constitutive promoter vectors, 183–185  
 retrovirus vectors, 186–190  
 generation of transgenic mice from sense ES clones, 207  
 preparation of sense cDNA constructs, 190  
 selection of stably transfected cell lines with appropriate drugs, 199–200  
 stable transfection of mammalian cells with sense DNA constructs  
 transfection by electroporation, 198–199  
 transfection by liposomes, 198  
 transfection by retrovirus vectors, 199  
 transient transfection of mammalian cells with sense constructs  
 transfection by calcium phosphate precipitation, 190–192  
 transfection by retrovirus vectors, 193–198
- Map program, 146–147  
 MapSort program, 147  
 Membrane filter, 462  
 blocking and hybridization of, 262–262
- Methylated cDNAs, 53  
 Methylation, 52–53  
 Microarrays, DNA  
 fluorescent probe preparation from mRNA, 431–433  
 generation of, 433  
 hybridization of, 434  
 isolation of total RNA from cells or tissues, 430–431  
 prehybridization of, 433–434  
 scanning of, 435–437  
 washing of, 434–435
- Microcentrifuge tube, 49  
 Microinjection  
 of DNA constructs into oocytes, 227, 496  
 transfection by, 217–218
- Micromanipulation apparatus  
 blastocyst injection pipettes, 493  
 embryo transfer pipettes, 493  
 ES cell injection pipettes, 493  
 holding pipette, 492  
 preparation, 223–224
- Minimal dextrose histidine (MDH), 408–409  
 Minimal dextrose (MD), 408  
 Minimal methanol histidine (MMH), 409  
 Minimal methanol (MM), 409  
 Miniprep method, 88–90  
 Mitotically inactivated STO cells, 343–344  
 Model mammalian cell line. *See* Mouse embryonic stem cells
- Molar concentration, 526–527  
 Mole, definition of, 526  
 Molecular weight calculation, 524  
 Moloney murine leukemia virus (MoMLV), 20, 186
- Monoclonal antibodies, 451–452, 455*f*. *See also* Human antibody libraries  
 infection of bacteria, 452, 455  
 phage–antibody particles by biopanning, 455–456
- Mouse embryonic stem cells  
 cell counting, 347–348, 348*f*  
 cell density determination, 347–348  
 freeze back, 346  
 leukemia inhibitory factor, 341–343  
 mitotically inactivated STO cells, 343–344  
 fibroblast feeder layers, 344  
 thawing and reculture, 346–347  
 trypsinizing of mammalian cells, 344–346
- mRNA  
 expression by semiquantitative PCR approach, 241–245  
 inhibition of (via siRNA), 463, 466  
 isolation, 443*f*  
 purification of. *See* Subtracted cDNA library  
 mRNA abundance analysis. *See* Radioactivity *in situ* hybridization (RISH)
- mRNA analysis  
 by northern blot hybridization, 232*f*  
 by northern blotting, 202, 202*f*
- Multiple cloning site (MCS), 63, 74, 75, 320, 357*f*, 365, 384, 397
- Mutant gene X<sup>ΔE2–3</sup> expression detection, 504  
 Mutant mice, 379  
 Mutant protein, functional analyses of, 7*f*
- N**
- NA45 DEAE membrane, 81  
 National Center for Biotechnology Information (NCBI), 133  
 National Institutes of Health (NIH), 1  
 Neomycin resistance (*neo*) gene, 352, 363–364, 363*f*  
*Neo*<sup>r</sup> (neomycin resistance) gene vector, 363–364, 363*f*  
 Neutral buffer, 161  
 New drug-targeting protein(s), identification of, 2, 3*f*  
 Nick translation labeling of dsDNA, 167, 168, 293  
 Nitroblue tetrazolium (NBT), 292, 297–298  
 Nitrocellulose, 259–260  
 Nonisotopic DNA probes  
 direct labeling of ssDNA, 163–165, 164*f*  
 nick translation labeling of dsDNA, 167  
 random primer digoxigenin labeling of dsDNA, 165–167, 166*f*
- Nonisotopic DNA sequencing method  
 detection methods  
 chemiluminescent detection, 115–116  
 colorimetric detection, 116–117, 116*f*  
 DNA templates, preparation of



- double-stranded plasmid DNA purification, 99–101
    - ssDNA, purification of, 102–103
  - DNA transfer onto nylon membrane, 114–115
  - electrophoresis, 112–114
  - gel preparation, 108–112
  - sequencing reactions
    - for double-stranded plasmid DNA, 103–107
    - for ssDNA, 107
  - Nonisotopic labeled probe, 333–334
  - Nonradioactive labeling of DNA, 164*f*
  - Northern blot hybridization for gene expression
    - blotting of RNAs onto nylon membranes, 237
    - electrophoresis of RNAs, 234–237
    - isotopic/nonisotopic DNA/RNA probes
      - DNA probes, preparation of, 237
      - RNA probes, preparation of, 238–241
    - mRNA expression by semiquantitative PCR approach, 241–245
    - principles of, 232–233, 232*f*
  - Northern blotting, 202, 202*f*, 219, 219*f*
  - in inhibition of mRNA, 466, 466*f*
  - Novel genes, isolation of, 2, 3*f*, 6, 8*f*
  - Nucleic acid sequencing, factors in
    - compressions, 99
    - DNA polymerase, 98
    - nonisotopic/isotopic dNTP, 98–99
    - primers, 98
    - quality of template, 98
  - Nylon membrane
    - blotting of RNAs onto, 237
    - filter, 160*f*
- O**
- Oligo(dT)-cellulose column, 42–45
  - Oligomers
    - optimum dose of, 211–213, 213*f*
    - size selection, 459
  - Oligonucleotide primers, 305
  - Oligonucleotides, 170
    - design of. *See* Short-interfering RNA (siRNA) technology
    - molecular weight, 524
  - Oligo Version 4.0, 19, 306, 307
  - Oocytes, preparation of, 225–227, 496–497
  - Open reading frame (ORF), 475
  - Optimal ligation of vectors with cDNA inserts, 56
  - Overexpression of specific proteins, in eukaryotic systems, 395–398
    - carry out fusion protein purification and cleavage, 412
    - cloning of a cDNA to be expressed into expression vectors, 398–399
    - expression of proteins in transformants, 410–412
    - identification of transformants containing cDNA to be expressed, 409
    - screening and isolation of His<sup>+</sup>Mut<sup>+</sup> and His<sup>+</sup>Mut<sup>+</sup> phenotype, 407–409
    - transformation of yeast *Pichia* with expression DNA constructs, 399–407
- P**
- $\alpha$ -<sup>32</sup>P-labeled probe, 328–333, 332*f*
  - Paraformaldehyde (PFA) solution, 270
  - Partial digestion of genomic DNA
    - large scale preparation of, 27–28
    - with *Sau3AI*, 26–27
  - Patent 101. *See* Discovery and invention protection
  - Patent application, full-length/complete, 514–519. *See also* Discovery and invention protection
  - Patent application, provisional, 513–514
  - PCR. *See also* Polymerase chain reaction (PCR)
  - PeptideMap program, 151
  - Peptide solution preparation, 527–528
  - Peroxidase-conjugated antibodies, 262
  - PFA solution. *See* Paraformaldehyde solution
  - Phage-antibody particles by biopanning, 455–456
  - Phage display technology, to produce monoclonal antibodies, 439–441. *See also* Human antibody libraries
    - design of primers for construction of antibody V gene repertoire, 446–449
    - expression, biopanning, and characterization of phage produces monoclonal antibodies on its tip, 451–456
    - generation of recombinant DNA constructs for expressing recombinant antibodies on surface of phage, 451
    - isolation of total RNA from lymphocytes, 442
    - PCR amplification, 449–451
    - preparation of white blood cells (WBCs) or lymphocytes for RNA isolation, 441–442
    - synthesis of cDNAs, 442–446
  - Phagemid vectors, 102
  - Phenol/chloroform extraction, 89
  - Phenylmethylsulfonyl fluoride (PMSF), 390
  - Phosphate buffer, 446
  - Pichia pastoris*, 395, 396*f*
  - <sup>32</sup>P-labeled DNA as probe, 67
  - Plasmid antisense cDNA constructs, 214–215
  - Plasmid backbone, 363, 365, 384, 397
  - Plasmid-based expression vectors, 214. *See* Gene overexpression by sense RNA
  - Plasmid DNA
    - large-scale preparation of (Protocol 2), 91–92
    - linearization of, 399–400
    - minipreparation of (Protocol 1), 88–90

- Plasmid DNA (*continued*)  
 purification, 462–463  
 purification by CsCl gradient (Protocol 3), 92–94
- Plasmid linearization reaction, 294
- Polaroid camera, 158
- Poly(A)<sup>+</sup>RNAs, 42  
 purification of, 42–44
- Poly-l-lysine in slide treatment, 270
- Polymerase chain reaction (PCR), 83–85  
 in direct DNA sequencing, 124–127  
 in electrophoresis, 360–362  
 fluorescence real-time, 416  
 gene double knockout, 356–362  
 in mRNA expression, 241–245  
*in situ*, 308–311
- Polypropylene tube, 38
- Polyvinylidene difluoride (PVDF), 249
- Potassium acetate solution, 463
- Pregnant mare's serum (PMS), 225, 494
- Prehybridization, 171–172  
 of gene chips, 433–434
- Primers, 98, 120, 305, 307  
 annealing of, 127  
 design of, 356–357, 357*f*, 473  
 and probes, design of, 420–421  
 solution preparation, 527  
 for V genes amplification, 446, 447*t*–448*t*, 449*t*  
 walking, 120
- Probes  
 fluorescent, 431–433  
 isotopic, 275–289  
 nonisotopic, 292–296  
 DNA/RNA, 237–241  
 preparation of, 163–171  
 primers and, 420–421
- Probind filters, 89
- Prokaryotic systems, proteins in. *See*  
 Recombinant proteins, expression and  
 purification of
- Promoter sequence amplification, 29
- Protease cleavage site (PCS), 383–384, 397
- Protease digestion, 276–277
- Protein  
 analysis by western blotting, 201, 201*f*, 213*f*, 214*f*, 218*f*  
 detection by western blot hybridization, 250*f*  
 extraction for reporter activity assays, 467  
 functional domain of. *See* Site-specific  
 mutagenesis  
 isolation for western blotting, 466  
 molar conversions, 526  
 overexpression in yeast, flowchart of, 398*f*  
 translation, 146–147
- Protein–protein interaction, 10, 13*f*
- Protein–protein interaction identification, 472*f*  
 binding proteins, 477–479  
 cloning with detection minitag, 479–480  
 coimmunoprecipitation, 477  
 designing/cloning/mapping, 480, 480*f*, 481*f*  
 eukaryotic cells, transfection of  
 FuGene 6 reagent, use of, 475–476  
 lipofectamine 2000, use of, 476  
 fluorescent protein as fusion tag, 479  
 interactive proteins, 481  
 PCR-TA cloning without DNA ligase, 471, 472*f*  
 chemically treated *E. coli* One-Shot TO  
 P10 competent cells, 474  
 cloning vector selection, 472–473, 472*f*  
 DNA sequences of bacterial colonies, 475  
 PCR reactions, performance of, 473–474  
 primer design, 473  
 TA cloning, 474  
 protein extraction, 476–477
- Pseudopregnant mice, 222, 491
- Purification, 164, 165*f*, 332*f*, 451*f*. *See also*  
 Recombinant proteins, expression and  
 purification of  
 of DNA fragments, 76–81  
 of PCR bands, 362  
 of plasmid DNA by alkaline method, 86–94  
 of Poly(A)<sup>+</sup>RNAs, 42–44  
 of radioactive probe, 280–281  
 of ssDNA, 102–103
- R**
- 3'-RACE. *See* Rapid amplification of 3'-cDNA  
 ends
- 5'-RACE. *See* Rapid amplification of 5'-cDNA  
 ends
- Radioactivity *in situ* hybridization (RISH)  
 cryosectioning  
 fixation, 274–275  
 freeze sectioning, 274, 275*f*  
 frozen specimens, preparation of,  
 273–274  
 embedding, 272  
 fixation of cultured cells on slides, 271  
 fixation solution preparation  
 4% (w/v) PFA fixative, 270–271  
 hybridized signal detection, 285–288  
 isotopic probes, use of  
 dewaxing of sections, 275  
 DNase treatment, 277  
 protease digestion, 276–277  
 random primer labeling of dsDNA, using,  
 278–281  
 RNase treatment, 277  
 by transcription *in vitro* labeling, 281–283  
 sectioning and mounting, 273  
 silane-coated glass slides, preparation of, 270

- gelatin-coating of slides, 270
- poly-l-lysine in slide treatment, 270
- silanization of slides, 270
- in situ* hybridization, 283–285
- tissue fixation, 271–272
- Random primer digoxigenin labeling of dsDNA, 165–167, 166*f*, 292–293
- Random primer labeling of dsDNA, 170, 278–279
  - DE-81 filter-binding assay, 279
  - radioactive probe, purification of, 280–281
  - specific activity of probe, calculation of, 279–280
  - TCA precipitation, 279
- Rapid amplification of 3'-cDNA ends, 24, 25*f*
- Rapid amplification of 5'-cDNA ends, 23–24, 24*f*
- Real-time RT-PCR. *See* Functional genome analysis
- Recombinant DNA generation, 451, 453*f*
- Recombinant proteins, expression and purification of
  - in eukaryotic systems, 395–398, 396*f*
    - cloning of cDNA, 398–399
    - His<sup>+</sup>Mut<sup>+</sup> phenotypes, 407
    - His<sup>+</sup>Mut<sup>+</sup> phenotype, 407
    - large scale expressions of protein, 411
    - protein expression, optimum conditions for, 410–411
    - total protein extraction, 412
    - transformants identification, 409
    - Yeast *Pichia*, transformation of, 399–407
  - in prokaryotic systems
    - bacterial expression vectors, 382–384, 385*f*
    - cloning of cDNA inserts into vectors, 384–385
    - dot blot in, 388
    - protease cleavage of His-Tag, 392–395
    - protein expression of interest in bacteria, 386–388
    - SDS-PAGE in, 388
    - total protein extraction, 389–390
    - western blotting in, 388
    - His-Tag affinity column chromatography, 390–392
- Regeneration dextrose (RD), 406
- Replication-competent retrovirus vector, 186*f*, 194*f*, 197*f*
- Replication-incompetent retroviruses, 197–198
- Replication-incompetent viral vector, 189*f*
- Reporter activity assays, protein extraction for, 467
- Reporter gene. *See also* Constitutive promoter vectors
  - expression assay of, 203–207
  - activity assay of CAT
    - CAT enzyme assay, 204
    - cytoplasmic extract, preparation of, 203–204
    - $\beta$ -galactosidase assay, 205–206
    - $\beta$ -galactosidase staining of cells, 206–207
    - Luciferase assay, 204–205
    - in transgenic mouse line C, 499
- Reporter gene analysis. *See* Short-interfering RNA (siRNA) technology
- Research design for novel gene identification, 3*f*
- Research grant funding
  - conditional gene knockout (CKO) approach, 13, 14*f*
  - disease-related new protein discovery, 10, 13*f*
  - drug-targeting protein identification, 2, 3*f*
  - functional domain identification, 6, 7*f*
  - gene knockout approach in, 2–
  - growth hormones, discovery of, 6, 10, 11*f*
  - heart hypertrophy, 6, 8*f*
  - immune-deficient system, rescue of, 6, 9*f*
  - novel gene isolation, 2, 3*f*
  - novel gene targeted by new drug, 2, 4*f*
  - novel proteins/cDNAs/genes, identification of, 10, 12*f*
  - objectives of, 1–2
  - toxicant-binding proteins, 6, 8*f*
- Research manuscript writing
  - abstract, 506
  - acknowledgments, 508
  - authors and affiliation, 503–504
  - choice of journals, 509
  - discussion, 507–508
  - fine tuning, 509
  - format of manuscript, adjusting, 508
  - introduction, 506–507
  - materials and methods, 504–505
  - outlines of, 501–502, 502*f*
  - references, 508
  - resubmission of manuscript, 509
  - results, 505–506
  - reviewer's comments/revision, 509
  - submission of manuscript, 509
  - title, 503
- Restriction enzyme digestion. *See* Subcloning of genes
  - of DNA, 157
  - for DNA insertion verification, 94–95, 94*f*
  - protocols for, 76–78
  - of vectors, 60
- Restriction enzymes, selection of, 73–75
- Restriction mapping of bacteriophage DNA, 336–338, 338*f*
- Retrovirus vectors, 186–190, 187*f*, 188*f*, 189*f*, 193–198, 199
- Retrovirus vectors, transfection by
  - with high titer stock of replication-incompetent retroviruses, 197–198, 198*f*

- Retrovirus vectors, transfection by (*continued*)  
 stably transfected producer cell lines,  
 194–195  
 viral supernatant, preparation of, 193–194,  
 194*f*  
 viral titer, determination of, 195–196  
 virus stock, amplification of, 196–197
- Reverse primers, 18, 28–29, 28*f*, 486
- Reverse transcription-polymerase chain reaction  
 (RT-PCR)  
 in Cre-Lox recombination process, 486–487  
 real-time. *See* Functional genome analysis
- Ribonuclease inhibitor, 432
- Riboprobe, 293–296
- Ribosome binding site (RBS), 383, 396
- RNA  
 isolation, 431–432. *See* Functional genome  
 analysis  
 labeling, 293–296  
 measurement of, 40–42  
 pool preparation, 419–420
- RNA probes  
 preparation of, 238–241  
 by transcription *in vitro*, preparation of,  
 238–241
- RNase contamination, 38
- RNA sequencing  
 annealing of primer, 127  
 labeling reactions, 127–128  
 termination reactions, 128–132
- RNase treatment, 277
- Rous sarcoma virus (RSV), 186, 188*f*
- RT-PCR. *See* Reverse transcription-polymerase  
 chain reaction
- S**
- Saccharomyces cerevisiae*, 395
- Saran Wrap film, 115, 262
- Sau3AI*  
 in genomic DNA digestion, 322–324  
 in partial DNA digestion, 26–28
- Scientific manuscript. *See* Research manuscript  
 writing
- SDS-PAGE, 388. *See* Western blotting for gene  
 expression analysis
- SDS-separation gel preparation, 255–256
- Selectable marker genes, 184
- Semidry electroblotting, 252*f*, 259–260
- Semiquantitative PCR products, 244*f*, 245*f*
- Sephadex column chromatography, 165*f*
- Sequence editing/modification, 142
- Sequence entry, 140–141
- Sequence output, 142
- Serial reinfection of fresh target cells, 196
- Short-interfering RNA (siRNA) technology, 457,  
 458*f*  
 cloning hairpin siRNA oligo insert, 460–462,  
 460*f*, 461*f*  
 double-stranded oligonucleotide fragment for  
 cloning, 459–460  
 down regulation of gene expression, 467–468,  
 468*f*  
 northern blotting in, 466, 466*f*  
 oligonucleotides, design of  
 hairpin siRNA-encoding oligonucleotides,  
 459  
 oligomer size selection, 459  
 siRNA target site selection, 458–459  
 plasmid DNA purification, 462–463  
 reporter gene analysis  
 protein extraction for reporter activity  
 assays, 467  
 protein isolation for western blotting, 466  
 transient transfection of cells, 463–465  
 western blotting in, 467, 467*f*
- Sigmacoat, 109
- Signal sequence (SS), 396
- Silane-coated glass slides, preparation of. *See*  
 Radioactivity *in situ* hybridization  
 (RISH)
- Silanization of slides, 270
- Single-chain Fv molecule (scFv), 440
- Single selection of cells, 371
- Single-step cloning by PCR, 83–85, 83*f*
- Single-stranded cDNAs, 50
- Single-stranded DNA (ssDNA), 102–103, 107  
 direct labeling of, 163–165, 164*f*
- siRNA. *See* Short-interfering RNA technology
- Site-specific mutagenesis, 6, 7*f*
- Sodium dodecyl sulfate-polyacrylamide gel  
 electrophoresis (SDS-PAGE), 212,  
 249, 388–389, 389*f*
- Sodium dodecyl sulfate (SDS), 233
- Solution volume conversions, 527
- Southern blot analysis, 202–203, 203*f*, 219–220,  
 219*f*  
 data analysis, 373–375  
 genomic DNA isolation, 373  
 western blot analysis, 375–377, 377*f*
- Southern blot hybridization, 245*f*  
 agarose gel electrophoresis of DNAs, 157–159  
 blotting of DNAs onto nylon membranes,  
 159–163  
 hybridized signal(s), detection of  
 by autoradiography, 174–179  
 chemiluminescence detection (method A),  
 173–174  
 colorimetric detection of filters  
 (method B), 174  
 isolation of DNA, 157  
 prehybridization and hybridization, 171–172  
 principles and procedures, 155–157  
 probes, preparation of

- isotopic DNA probes, 168–171
  - nonisotopic DNA probes, 163–167
  - restriction enzyme digestion of DNA, 157
  - washing and/or incubation of antibodies
    - with biotin–dUTP - or DIG –UTP-labeled probes, 173
    - with ECL-labeled probes, 172–173
    - with isotopic probes, 173
  - Southern blotting, 219–220, 219*f*
  - Specific cDNA isolation by PCR
    - agarose gels, use of, 30
    - DNA fragment amplification, 29–30
    - forward and reverse primers
      - exon and intron sequences, 28–29, 28*f*
      - promoter sequence amplification, 29
    - full-length cDNAs (isolation by RT-PCR method), 17–23, 18*f*
    - genomic DNA, isolation of, 24–25
    - 3'-RACE, 24, 25*f*
    - 5'-RACE, 23–24, 24*f*
    - Sau3AI* in partial digestion of genomic DNA
      - large scale production of, 27–28
      - optimization of, 26–27
  - Spectrophotometric conversions, 525
  - Spheroplasts, 402–404, 402*f*, 405–407
  - ssDNA. *See* Single-stranded DNA
  - Stable transfection of cultured cells. *See* Gene underexpression by antisense DNA/RNA approaches
  - Stable transfection of mammalian cells. *See* Gene overexpression by sense RNA
  - Stable transgenic mouse lines A and B, 497
  - Stably transfected cell clones. *See also* Gene overexpression by sense RNA
    - characterization of. *See* Gene underexpression by antisense DNA/RNA approaches
  - Stably transfected cell lines, selection of
    - aminoglycoside antibiotics, use of, 200
    - hygromycin- $\beta$ -phosphotransferase gene, 200
    - thymidine kinase, 200
    - tryptophan synthetase, 200
  - Stably transfected producer cell lines, production of, 194–195
  - Stacking gel preparation, 256–257
  - Standard deviation, 529–530
  - Sterile males, 221–222
  - Streptavidin–alkaline phosphatase conjugate (SAAP), 115
  - Subcloning of genes
    - advantages of, 73
    - DNA fragments, purification of, 78–81. *See also* DNA fragments, elution of
    - DNA insertion verification, 94–95
    - DNA sequencing, 95–96
    - ligated DNA into bacteria, transformation of
      - Protocol 1, 85–86
      - Protocol 2, 86–87
      - Protocol 3, 87–88
    - ligation of DNA fragments, 81–83
    - plasmid DNA, isolation and purification of
      - Protocol 1, 88–90
      - Protocol 2, 91–92
      - Protocol 3, 92–94
    - restriction enzyme digestion
      - cloning vectors, selection of, 75
      - protocols for, 76–78
      - restriction enzymes, selection of, 73–75
    - single-step cloning by PCR, 83–85, 83*f*
  - Subtracted cDNA library, 36, 37*f*
    - cDNA, characterization of, 60
    - cDNA /mRNA hybrids, separation of, 50
    - double-stranded cDNAs, synthesis of, 50–52
    - first strand cDNAs, synthesis of
      - analysis of, 47–49, 48*f*
      - synthesis of, 45–47
      - TCA assay and calculation of, 47
    - generation of
      - amplification of cDNA library, 60
      - titration of packaged phage, 58–60, 58*f*
      - in vitro* packaging, 57–58
    - hybridization, 49–50
    - ligation of cDNAs to lamda gt10
      - EcoRI* linkers/adapters, 52–56
      - restriction enzyme digestion of vectors, 56
      - to vectors, 56–57
    - mRNAs, purification of
      - minipurification of, 44–45
      - purification of poly(A)<sup>+</sup>RNA s, 42–44
    - specific cDNA, isolation of, 60
    - total RNAs
      - rapid isolation of, 36, 38
      - rapid isolation of, 39–40
      - measurement of, 40–42
  - Supernatant fluid, 23
  - Superovulation, 220, 221, 489
- ## T
- TA cloning, 474
  - Taq* polymerase, 471, 473
  - Targeted embryonic stem cell clones. *See* Gene double knockout
  - TCA precipitation. *See* Trichloroacetic acid (TCA) precipitation
  - Technology disclosure, 512–513
  - Terminal transferase, 170–171
  - Terminator sequence, 384, 397
  - Tetramethylethylenediamine (TEMED), 109, 111
  - Thymidine kinase, 200
  - Tissue fixation, 271–272
  - Titration of packaged phage, 58–60, 58*f*
    - on luria-bertani plates, 326–327

- Total protein extraction, 388, 412
- Total RNA  
 electrophoresis of, 40*f*  
 isolation of, 36, 38  
 rapid isolation of, 38–39, 39–40  
 from cultured cells, 38–39  
 from tissues, 38
- Toxicant-binding protein(s), 6, 8*f*
- Transcription *in vitro* labeling, 281–283
- Transgene copy number determination  
 amino acids, 525  
 DNA molar conversions, 525  
 DNA-protein conversions, 526  
 mean calculation, 528–529  
 molarity  
 molar concentration, 526–527  
 mole, definition of, 526  
 peptide solution preparation, 527–528  
 primer solution preparation, 527  
 solution volume conversions, 527  
 molecular weight, 524  
 of oligonucleotides, 524  
 protein molar conversions, 526  
 spectrophotometric conversions, 525  
 in transgenic animals, 521–523, 522*f*, 523*f*  
 variance and standard deviation, 529–530
- Transgenic mice, characterization of, 207–208
- Transgenic mice production from oocytes  
 founder mice, generation of, 227–228  
 microinjection of DNA constructs into oocytes, 227  
 oocytes, preparation of, 225–227
- Transgenic mice production from stably transfected ES cells  
 bank of sterile males by vasectomy, 221–222  
 blastocyst-stage embryos from pseudopregnant mice, 222–223  
 C57BL/6J estrous females, selection of, 220–221  
 ES cells injection into blastocysts, 224  
 estrous females and sterile males, pairing of, 222  
 micromanipulation apparatus preparation, 223–224  
 reimplantation of injected blastocysts, 225
- Transgenic mouse line C, generation of  
 functional and phenotypic analyses, 499  
 functional genome analysis, 498–499, 498*f*  
 genotypic analysis, 498  
 immunostaining, 499  
 reporter gene, 499
- Transgenic mouse lines with *loxP*-Cre system cassettes  
 bank of sterile males by vasectomy, preparation of, 490  
 blastocyst-stage embryos preparation, 491–492  
 estrous females and sterile males, pairing of, 491  
 microinjection of DNA constructs into oocytes, 496  
 micromanipulation apparatus, 492–493  
 oocytes, preparation of, 494–496  
 reimplantation of injected blastocysts, 494  
 reimplantation of injected eggs, 496–497  
 stably transfected ES cell injection into blastocysts, 493
- Transgenic mouse lines with *loxP*-Cre system cassettes  
 C57BL/6J estrous females, selection of, 489
- Transgenic offspring generation, 377–378
- Transient transfection of mammalian cells. *See* Gene overexpression by sense RNA
- Translate program, 150
- Trichloroacetic acid (TCA), 443  
 assay, 47  
 precipitation, 168–170, 279
- Triethanolamine (TEA) buffer, 288
- Triple selections of cells, 371
- Trizol reagents, 39–40, 417, 485–486
- Trypsinizing of mammalian cells, 344–346
- Tryptophan synthetase, 200
- Type B enzymes, 74
- U**
- Ultrapure grade agarose, 156
- Unidirectional deletions, 120–124
- United States Biochemical (USB), 98, 120
- Untranslated region (UTR), 356
- Upward capillary transfer, 159–161, 160*f*
- UV-spectrophotometer, 40
- V**
- Variable domains of heavy chain (VH), 439, 449, 450*f*
- Variable domains of light chains (VL), 439, 449, 450*f*
- Vasectomy, 221
- V genes (antibody variable regions), 446, 447*t*–448*t*, 449*t*
- Viral supernatant, preparation of, 193–194, 194*f*
- Viral titer, determination of, 195–196
- Voltage booster, 88
- W**
- Western blotting, 201–202, 201*f*, 218, 218*f*, 375–377, 377*f*, 388, 504  
 in inhibition of gene expression, 467  
 in protein analysis, 213*f*, 214*f*, 218*f*  
 protein isolation for, 466

Western blotting for gene expression analysis,  
249–251, 250*f*  
cellular proteins extraction  
  using Bradford assay, 255  
  using lauroylsarcosine buffer, 253–254  
2-D gel electrophoresis in, 263–265  
principles of, 251–253, 252*f*, 253*f*  
by SDS-PAGE  
  electrophoresis, 257–258  
  hybridized signal detection, 262  
  membrane filter, blocking and  
    hybridization of, 261–262  
  modified CB method, use of, 258–259  
  SDS-separation gel preparation, 255–256  
  stacking gel preparation, 256–257

  transfer of proteins, 259–260  
Whatman filter paper, 160, 162  
White blood cells (WBCs), 441

## Y

Yeast artificial chromosomes (YAC), 319  
Yeast *Pichia*, transformation of, 399–407  
  by electroporation, 400–401  
  linearization of plasmid DNA, 399–400  
  spheroplasts for, 402–404, 402*f*, 405–407

## Z

Zymolyase digestion, 402